

Wikiprint Book

Title: Doc/ComputingCenters/LSCE

Subject: Igcmg_doc - Doc/ComputingCenters/LSCE

Version: 12

Date: 10/22/21 18:50:12

Table of Content

How to use the IPSL models and tools at obelix/LSCE cluster	3
1. Modipsl and compiling	3
2. libGCM and environment	3
3. Disk space and archive directory	3
4. Example of parallel MPI job	3
5. Specific installation of LMDZ	4

How to use the IPSL models and tools at obelix/LSCE cluster

The LSCE computing environment is detailed here: <https://w3.lsce.ipsl.fr/informatique/util/index.php>. You can only access this web page via the LSCE network. The direct access to the cluster is only possible from the LSCE or from the TGCC machines. The cluster can be accessed via ssh and xdmcp protocols.

- `asterix` : interactive use. The network includes a cluster for the interactive mode. This cluster is considered as a unique machine called `asterix`.
- `obelix` : computing cluster. The LSCE has a small computing cluster. See its users' manual here: <https://w3.lsce.ipsl.fr/informatique/util/calcul/batch.php>. This cluster is considered as a unique machine called `obelix`. Installation, compiling and running is done from `obelix`.

1. Modipsl and compiling

Install and compile from `obelix`. By default the compiling is done for MPI parallel mode. The compiler is `ifort` (*Intel* compiler). The `Ixiv8` target in `modipsl/util/AA_make.gdef` is used on `obelix`. Currently the components ORCHIDEE, LMDZ, IOIPSL and XIOS can be installed on `obelix` using the default compiling options in `modipsl`.

2. libGCM and environment

`libGCM` can be used at `obelix`. Computing, rebuild and time-series are performed. No pack, atlas or monitoring is done.

The default shell at LSCE is `tcsh`, which syntax is different from the `ksh` syntax used by `libGCM`. No specific configuration of your account is needed to compile and run using `libGCM`. But you can use the environment proposed on the shared account by copying the file `/home/users/igcmg/.bashrc` in your `$HOME`.

3. Disk space and archive directory

The home for each login in `/home/user/` have very small space. You need to have write access to another disk depending on the project you work on. All login can write to the disk `/home/scratch01/login`. Note that files older than 30 days can be deleted without warning on this disk.

The simulation output is stored in `/home/scrath01`. You need to change it to set a permanent archive by using `ARCHIVE` variable in `config.card`.

The default archive directory at `obelix` is set to `/home/scratch01/yourlogin`. To store your simulation on a permanent disk you need to set `ARCHIVE=/home/diskXXX/yourlogin` in `config.card` section [UserChoices].

Example: `config.card`

```
[UserChoices]
JobName=test01
TagName=OL2
SpaceName=PROD
ExperimentName=clim
ARCHIVE=/home/orchidee02/login
...
```

Change login to your personal login. In the example according to the above `config.card` the simulation will be stored in `/home/orchidee02/login/IGCM_OUT/OL2/PROD/clim/test01`.

4. Example of parallel MPI job

Here is an example of a simple job to run the `orchidee_ol` executable. All input files and the executable must be in the directory before running the executable.

```
#####
## OBELIX      LSCE ##
#####
#PBS -N MyTest
#PBS -m a
#PBS -j oe
```

```

#PBS -q medium
#PBS -o Script_Output
#PBS -S /bin/ksh
#PBS -l nodes=1:ppn=8

## First source following to acces the command module under ksh
source /usr/share/Modules/init/ksh

## Source same modules as used during compilation. See examples below depending on the configurations used.
# For ORCHIDEE_3 and more recent offline versions or coupled v6.2 and more recent versions:
#source ../config/ORCHIDEE_OL/ARCH/arch-ifort_LSCE.env
#source ../config/LMDZOR_v6/ARCH/arch-ifort_LSCE.env
# For ORCHIDEE_2_0, 2_1, 2_2 and coupled models v6.1.x:
#source /home/orchideeshare/igcmg/MachineEnvironment/obelix/env_atlas_obelix

## Go to current folder and execute
cd $PBS_O_WORKDIR
time mpirun orchidee_ol

```

To submit it you need to use the command **qsub**, and you can follow your simulation with the command **qstat -u login**

5. Specific installation of LMDZ

- Download a configuration as default. All LMDZOR_v6 configurations can be used at obelix. Fully coupled model IPSLCM has not been adapted for use at obelix.
- Change the default compilation from hybrid mode `mpi_omp` into `mpi` only. Do this in `config/LMDZOR_v6/AA_make` on the line **makelmdz_fcm** by changing **-parallel mpi_omp** into **-parallel mpi**. Recreate makefile by executing `modipsl/util/ins_make`. Compile as usual.
- Before launching
 - LMDZ has an option set in `run.def` parameter file to use different filters close to the north and south pole. The default filter set in v6 configurations is the `fft` filter because this is faster. In the obelix compile options no specific FFT has been added and therefore this option can not be used. It must be changed before running LMDZ. This is done by setting **use_filtre_fft=n** in `LMDZOR_v6/GENERAL/PARAM/run.def` file. This directory is copied at each creation of a submit directory by `ins_job`.
 - Adapt `config.card` to use only MPI. Set for example following:

```

[Executable]
#D- For each component, Real name of executable, Name of executable for oasis
ATM= (gcm.e.mpi.prod, lmdz.x, 7MPI, 1OMP)
SRF= ("", "")
SBG= ("", "")
IOS= (xios_server.exe, xios.x, 1MPI)

```