


PRISM
Project for Integrated Earth System Modelling
An Infrastructure Project for Climate Research in Europe
funded by the European Commission
under Contract EVR1-CT2001-40012



OASIS3 User Guide
prism_2-4

Edited by:
S. Valcke, CERFACS
A. Caubel, FSE
R. Vogelsang, SGI Germany
D. Declat, CERFACS

PRISM–Report No 2

5th Edition
December 21, 2004

Copyright Notice

© Copyright 2004 by CERFACS

All rights reserved.

No parts of this document should be either reproduced or commercially used without prior agreement by CERFACS representatives.

How to get assistance?

Assistance can be obtained as listed below.

PRISM documentations can be downloaded from the WWW PRISM web site under the URL:

<<http://prism.enes.org>>

Phone Numbers and Electronic Mail Adresses

Name	Phone	Affiliation	e-mail
Sophie Valcke	+33-5-61-19-30-76	CERFACS	

Contents

1	Acknowledgements	1
2	Overview of step-by-step use of OASIS3	3
3	Obtaining OASIS3 sources	4
3.1	The OASIS3 package	4
4	Interfacing a model with the PSMILe library	6
4.1	Initialisation	7
4.2	Grid data file definition	7
4.3	Partition definition	9
4.3.1	Serial (no partition)	9
4.3.2	Apple partition	9
4.3.3	Box partition	9
4.3.4	Orange partition	11
4.4	I/O-coupling field declaration	12
4.5	End of definition phase	13
4.6	Sending and receiving actions	13
4.6.1	Sending a coupling field	13
4.6.2	Receiving a coupling field	14
4.6.3	Auxiliary routines	14
4.7	Termination	15
4.8	Coupling algorithms - SEQ and LAG concepts	16
4.8.1	The lag concept	16
4.8.2	The sequence concept	19
4.8.3	A mix of lag and sequence: the sequential coupled model	19
4.8.4	Mixing sequential and parallel runs using <code>prism_put_restart_proto</code>	22
5	The OASIS3 configuration file <i>namcouple</i>	23
5.1	An example of a simple <i>namcouple</i>	23
5.2	First section of <i>namcouple</i> file	25
5.3	Second section of <i>namcouple</i> file	27
5.3.1	Second section of <i>namcouple</i> for EXPORTED, AUXILARY and EXPOUT fields	27
5.3.2	Second section of <i>namcouple</i> for IGNORED, IGNOUT, and OUTPUT fields	28
5.3.3	Second section of <i>namcouple</i> for INPUT fields	29
6	The transformations and interpolations in OASIS3	30
6.1	Using OASIS3 in the interpolator-only mode	30
6.2	The time transformations	31
6.3	The pre-processing transformations	31
6.4	The interpolation	33

6.5	The “cooking” stage	38
6.6	The post-processing	40
7	OASIS3 auxiliary data files	41
7.1	Field names and units	41
7.2	Grid data files	41
7.3	Coupling restart files	42
7.4	Input data files	43
7.5	Transformation auxiliary data files	44
7.5.1	Auxiliary data files for EXTRAP/NINENN, EXTRAP/WEIGHT, INTERP/SURFMESH, INTERP/GAUSSIAN, MOZAIC, and SUBGRID	44
7.5.2	Auxiliary data files for FILLING	45
7.5.3	Auxiliary data files for SCRIPR	45
8	Compiling and running with OASIS3	46
8.1	Compiling OASIS3 and the TOYCLIM coupled model	46
8.2	Configuring the TOYCLIM coupled model using OASIS3	48
8.3	Running the TOYCLIM coupled model using OASIS3	49
8.4	Running the TOYCLIM coupled model manually	49
8.5	Running OASIS3 in interpolator-only mode	50
A	The grid types for the transformations	51
B	Changes between versions	53
B.1	Changes between prism_2_4 and oasis3_prism_2_3	53
B.2	Changes between oasis3_prism_2_3 and oasis3_prism_2_2	54
B.3	Changes between oasis3_prism_2_2 and oasis3_prism_2_1	54
B.4	Changes between oasis3_prism_2_1 and oasis3_prism_1_2	55
C	Copyright statements	57
C.1	OASIS3 copyright statement	57
C.2	The SCRIP 1.4 copyright statement	57
D	The coupled models realized with OASIS	58

Chapter 1

Acknowledgements

We would like to thank the main past or present developers of OASIS are (in alphabetical order, with the name of their institution at the time):

Arnaud Caubel (FECIT/Fujitsu)
Damien Declat (CERFACS)
Veronika Gayler (MPI-M&D)
Jean Latour (Fujitsu-Fecit)
Eric Maisonnave (CERFACS)
Elodie Rapaport (CERFACS)
Hubert Ritzdorf (CCRLE-NEC)
Sami Saarinen (ECMWF)
Eric Sevault (Météo-France)
Laurent Terray (CERFACS)
Olivier Thual (CERFACS)
Sophie Valcke (CERFACS)
Reiner Vogelsang (SGI Germany)

We also would like to thank the following people for their help and suggestions in the design of the OASIS software (in alphabetical order, with the name of their institution at the time):

Dominique Astruc (IMFT)
Sophie Belamari (Météo-France)
Dominique Bielli (Météo-France)
Gilles Bourhis (IDRIS)
Pascale Braconnot (IPSL/LSCE)
Christophe Cassou (CERFACS)
Yves Chartier (RPN)
Jalel Chergui (IDRIS)
Philippe Courtier (Météo-France)
Philippe Dandin (Météo-France)
Michel Déqué (Météo-France)
Ralph Doescher (SMHI)
Jean-Louis Dufresne (LMD)
Jean-Marie Epitalon (CERFACS)
Laurent Fairhead (LMD)

Marie-Alice Foujols (IPSL)
Gilles Garric (CERFACS)
Eric Guilyardi (CERFACS)
Charles Henriët (CRAY France)
Pierre Herchuelz (ACCRI)
Maurice Imbard (Météo-France)
Luis Kornblueh (MPI-M)
Stephanie Legutke (MPI-M&D)
Claire Lévy (LODYC)
Olivier Marti (IPSL/LSCE)
Claude Mercier (IDRIS)
Pascale Noyret (EDF)
Andrea Piacentini (CERFACS)
Marc Pontaud (Météo-France)
René Redler (NEC-CCRLE)
Tim Stockdale (ECMWF)
Rowan Sutton (UGAMP)
Véronique Taverne (CERFACS)
Jean-Christophe Thil (UKMO)
Nils Wedi (ECMWF)

Chapter 2

Overview of step-by-step use of OASIS3

To use OASIS3 for coupling models and/or perform I/O actions, one has to follow these steps:

1. Obtain OASIS3 sources. (See section 3).
2. Identify the coupling or I/O fields and adapt the component models to allow their exchange with the PSMILe library based on MPI1 or MPI2 message passing¹. The PSMILe library is interfaced with the `mpp_io` library from GFDL (2) and therefore can be used to perform I/O actions from/to disk files. For more detail on how to interface a model with the PSMILe, see section 4. The TOYCLIM coupled model gives a practical example of toy models; the sources are given in directories `/prism/src/mod/toyatm`, `/toyoce`, `/toyche` and more details can be found in (7).
3. Define all coupling and I/O parameters and the transformations required to adapt each coupling field from its source model grid to its target model grid; prepare OASIS3 configuring file *namcouple*. OASIS3 supports many interpolation algorithms as it is interfaced with the SCRIP 1.4 library (1) (see appendix C.2). (See sections 5 and 6).
4. Generate required auxiliary data files. (See section 7).
5. Compile OASIS3, the component models and start the coupled experiment. OASIS3 and the TOYCLIM coupled model use the PRISM standard compiling environment (SCE) and standard running environment (SRE). (See section 8).

OASIS3 and the TOYCLIM coupled model has successfully run on Fujitsu VPP5000, NEC SX5 and SX6, SGI IRIX64, SGI Origin 3800, Linux Opteron, IBM Power4, and Cray X1. The appendix D lists (some of) the coupled models realized with OASIS within the past 5 years or so.

If you need extra help, do not hesitate to contact us (see contact details on the back of the cover page).

¹In OASIS3, the SIPC technique has also been maintained; for a practical toy model example, see the sources in `/prism/src/mod/sipcatmos`, `/sipcocean` and the running script and README in `/prism/util/running/toysvipc` (available from CERFACS CVS Server only). The PIPE and GMEM communication techniques should still work but are not maintained anymore and were not tested.

Obtaining OASIS3 sources

- ```
- prism/data/testinterp data for OASIS3 in interpolator mode NONE
 (CERFACS CVS only)
 /toyclim data and results for TOYCLIM coupled model
 /toysvipc data for the SIPC toy model
 (CERFACS CVS only)

- prism/src/lib/anaisg GAUSSIAN interpolation library
 /anaism SURFMESH interpolation library
 /clim CLIM/MPI1-MPI2 communication library
 /fscint INTERP interpolation library
 /mpp_io I/O library
 /psmile PRISM System Model Interface Library
 /scrip SCRIPR interpolation library
 /sipc SIPC communication library
 (CERFACS CVS only)

- prism/src/mod/oasis3/src OASIS3 main code
 /doc OASIS3 documentation
```



- /sipcatmos SIPC toy model 1 (CERFACS CVS only)
  - /sipcocean SIPC toy model 2 (CERFACS CVS only)
  - 
  - /toyatm TOYCLIM component model 1 and documentation
  - /toyoce TOYCLIM component model 2
  - /toyche TOYCLIM component model 3
- prism/util/compile/frames PRISM Standard Compiling Environment (SCE)
- prism/util/running/frames PRISM Standard Running Environment (SRE)
- prism/util/running/adjunct\_file configuring files for OASIS3
  - /testinterp environment to test the interpolator  
mode NONE (CERFACS CVS only)
  - /toysvipc environment to run the SIPC toymodel  
(CERFACS CVS only)

## Chapter 4

# Interfacing a model with the PSMILe library

At run-time, OASIS3 acts as a separate mono process executable which drives the coupled run, interpolates and transforms the coupling fields. To communicate with OASIS3 or directly between the component models, different communication techniques have been historically developed. The technique used for one particular run is defined by the user in the configuration file *namcouple* (see section 5). In OASIS3, the CLIM communication technique based on MPI1 or MPI2 message passing and the associated model interface library PSMILe, should be used<sup>1</sup>. For a practical toy model using the PSMILe library, see the sources in `/prism/src/mod/toytm`, `/toyche`, `/toyoce` and more details in (6).

To communicate with OASIS3 or directly with another component model using the CLIM/MPI communication technique, or to perform I/O actions, a component model needs to be interfaced with the PRISM System Model Interface library, PSMILe, which sources can be found in `prism/src/lib/psmile` directory. PSMILe supports:

- parallel communication between a parallel component model and OASIS3 main process,
- direct communication between two parallel component models when no transformations and no repartitioning are required,
- automatic sending and receiving actions at appropriate times following user's choice indicated in the *namcouple*,
- time integration or accumulation of the coupling fields,
- I/O actions from/to files.

To adapt a component model to PSMILe, specific calls of the following classes have to be implemented in the code:

1. Initialisation (section 4.1)
2. Grid data file definition (section 4.2)
3. Partition definition (section 4.3)
4. I/O-coupling field declaration (section 4.4)
5. End of definition phase (section 4.5)
6. I/O-coupling field sending and receiving (section 4.6)
7. Termination (section 4.7)

Finally, in section 4.8, different coupling algorithms are illustrated, and explanations are given on how to reproduce them with PSMILe by defining the appropriate indices of lag and sequence for each coupling

---

<sup>1</sup>The SIPC technique, based on UNIX shared-memory segments, was also maintained; for a practical toy model example using SIPC, see the sources in `/prism/src/mod/sipcatmos`, `/sipcocean` and some explanations in `/prism/util/running/toysvipc` (from CERFACS CVS only).

field.

## 4.1 Initialisation

All processes initialise the coupling and, if required, retrieve a local communicator for the component model internal parallelisation.

- `USE mod_prism_proto`  
Module to be used by the component models.
- `CALL prism_init_comp_proto (compid, modelname, ierror)`
  - `compid` [INTEGER; OUT]: component model ID
  - `modelname` [CHARACTER\*6; IN]: name of calling model (as in *namcouple*)
  - `ierror` [INTEGER; OUT]: returned error code.

Routine called by all component model processes, which initialises the coupling.<sup>2</sup>

- `CALL prism_get_localcomm_proto (local_comm, ierror )`
  - `local_comm` [INTEGER; OUT]: value of local communicator
  - `ierror` [INTEGER; OUT]: returned error code.

For MPI1: routine called by all model processes to get the value of a local communicator to be used by the model for its internal parallelisation.

In fact, with MPI1, all component models started in a pseudo-MPMD mode share automatically the same `MPI_COMM_WORLD` communicator. Another communicator has to be used for the internal parallelisation of each model. OASIS3 creates this model local communicator following a “coloring scheme”; its value is returned as the first argument of `prism_get_localcomm_proto` routine.

With MPI2, the communicator `MPI_COMM_WORLD` will be returned as local communicator.

Besides that, the differences between using PSMILe with MPI1 or MPI2 message passing are

- The `$CHANNEL` in the *namcouple*; see section 5.2.
- The way the models are started. With MPI2, only OASIS3 needs to be started at the command line; it will then spawn the component models at the beginning of the run. With MPI1, models have to be started by the user in a pseudo-MPMD mode; the way to do this depends on the computing platform. For more details, see section 8.3.

## 4.2 Grid data file definition

The grid data files *grids.nc*, *masks.nc* and *areas.nc* must be created by the user before the run, or can be written directly at run time by the component models.

If written by the component models, the writing of those grid files is driven by OASIS3 main process. It first checks whether the binary file *grids* or the netCDF file *grids.nc* exists (in that case, it is assumed that *areas* or *areas.nc* and *masks* or *masks.nc* files exist too), or if writing is needed. If *grids* or *grids.nc* exists, it must contain all grid information from all models; if it does not exist, each model must write its grid definition in the grid data files.

The coupler sends the information on whether or not writing is needed to the models following an OASIS internal order (below `prism_start_grids_writing`). If no writing is needed, nothing happens when calling the following `prism_write_xxxx` routines. If writing is needed, the first model creates the files, writes the data arrays (with `prism_write_grid`, `prism_write_corner`, `prism_write_mask`,

---

<sup>2</sup>The model may call `MPI_Init` explicitly, but if so, has to call it before calling `prism_init_comp_proto`; in this case, the model also has to call `MPI_Finalize` explicitly, but only after calling `prism_terminate_proto`.

`prism_write_area` calls), and then sends a termination flag to the coupler (below `prism_terminate_grids_writing` call). The coupler will send the starting flag to the next model; this ensures that only one model accesses the files at a time.

This section describes the PSMILE routines that may be called by the master process of each component model to write, at run time, the whole grid information to the grid data files. These routines have to be called just after `prism_init_comp_proto`.

The TOYCLIM coupled model (see the sources of the toy component models in `prism/src/mod/toyatm`, `/toyoce`, and `/toyche`) uses those routines to write its grid data files if `gridswr=1` in the running script `RUN_toyclim_<expid>` (see section 8.3).

- `USE mod_prism_grids_writing`

Module to be used by the component model to call grid writing routines.

- `CALL prism_start_grids_writing (flag)`

– `flag [INTEGER; OUT]`: returns 1/0 if grids writing is needed/not needed

Initialisation of grids writing.

- `CALL prism_write_grid (cgrid, nx, ny, lon, lat)`

– `cgrid [CHARACTER*4; IN]`: grid name prefix (see 5.3)

– `nx [INTEGER; IN]`: grid dimension in x-direction

– `ny [INTEGER; IN]`: grid dimension in y-direction

– `lon [REAL, DIMENSION(nx,ny); IN]`: array of longitudes (degrees East)

– `lat [REAL, DIMENSION(nx,ny); IN]`: array of latitudes (degrees North)

Writing of the model grid longitudes and latitudes. Note that OASIS automatically detects overlapping grid points (which is essential to have a correct conservative remapping SCRIPR/CONSERV, see section 6.4) only if their longitude is given with the same number (e.g. 360.0 for both, not 450.0 for one and 90.0 for the other).

- `CALL prism_write_corner (cgrid, nx, ny, nc, clon, clat)`

– `cgrid [CHARACTER*4; IN]`: grid name prefix

– `nx [INTEGER; IN]`: grid dimension in x-direction

– `ny [INTEGER; IN]`: grid dimension in y-direction

– `nc [INTEGER; IN]`: number of corners per grid cell (4)

– `lon [REAL, DIMENSION (nx,ny,nc); IN]`: array of corner longitudes (in degrees East)

– `lat [REAL, DIMENSION (nx,ny,nc); IN]`: array of corner latitudes (in degrees North)

Writing of the grid cell corner longitudes and latitudes (counterclockwise sense). Writing of corners is optional as corner information is needed only for some transformations (see section 7.2). If called, `prism_write_corners` needs to be called after `prism_write_grids`.

- `CALL prism_write_mask (cgrid, nx, ny, mask)`

– `cgrid [CHARACTER*4; IN]`: grid name prefix

– `nx [INTEGER; IN]`: grid dimension in x-direction

– `ny [INTEGER; IN]`: grid dimension in y-direction

– `mask [INTEGER, DIMENSION(nx,ny) ; IN]`: mask array (0 - not masked, 1 - masked)

Writing of the model grid mask.

- `CALL prism_write_area (cgrid, nx, ny, area)`

– `cgrid [CHARACTER*4; IN]`: grid name prefix

– `nx [INTEGER; IN]`: grid dimension in x-direction

– `ny [INTEGER; IN]`: grid dimension in y-direction

- `area [REAL, DIMENSION(nx,ny); IN]` : array of grid cell areas

Writing of the model grid cell areas. Writing of areas is optional as area information is needed only for some transformations (see section 7.2).

- `CALL prism_terminate_grids_writing()`

Termination of grids writing. A flag stating that all needed grid information was written will be sent to OASIS3 main process.

## 4.3 Partition definition

When a component of the coupled system is a parallel code, each coupling field is usually scattered among the different processes. With the PSMILe library, each process sends directly its partition to OASIS3 main process or directly to the other component model if no transformation nor repartition is required. To do so, each process implied in the coupling has to define its local partition in the global index space.

- `USE mod_prism_def_partition_proto`  
Module to be used by the component model to call `prism_def_partition_proto`.
- `CALL prism_def_partition_proto (il_part_id, ig_paral, ierror)`
  - `il_part_id [INTEGER; OUT]`: partition ID
  - `ig_paral [INTEGER, DIMENSION(:), IN]`: vector of integers describing the local partition in the global index space
  - `ierror [INTEGER; OUT]`: returned error code.

The vector of integers describing the process local partition, `ig_paral`, has a different expression depending on the type of the partition. In OASIS3, 4 types of partition are supported: Serial (no partition), Apple, Box, and Orange.

### 4.3.1 Serial (no partition)

This is the choice for a monoprocess model. In this case, we have `ig_paral(1:3)`:

- `ig_paral(1) = 0` (indicates a Serial “partition”)
- `ig_paral(2) = 0`
- `ig_paral(3) = the total grid size.`

### 4.3.2 Apple partition

Each partition is a segment of the global domain, described by its global offset and its local size. In this case, we have `ig_paral(1:3)`:


- `ig_paral(1) = 1` (indicates an Apple partition)
- `ig_paral(2) = the segment global offset`
- `ig_paral(3) = the segment local size`

Figure 4.1 illustrates an Apple partition over 3 processes.


### 4.3.3 Box partition

Each partition is a rectangular region of the global domain, described by the global offset of its upper left corner, and its local extents in the X and Y dimensions. The global extent in the X dimension must also be given. In this case, we have `ig_paral(1:5)`:

- `ig_paral(1) = 2` (indicates a Box partition)



**Figure 4.1:** Apple partition



**Figure 4.2:** Box partition

- `ig_paral(2)` = the upper left corner global offset
- `ig_paral(3)` = the local extent in X
- `ig_paral(4)` = the local extent in Y<sup>3</sup>
- `ig_paral(5)` = the global extent in X.

Figure 4.2 illustrates a Box partition over 3 processes.


#### 4.3.4 Orange partition

Each partition is an ensemble of segments of the global domain. Each segment is described by its global offset and its local extent. In this case, we have `ig_paral(1:N)` where  $N = 2 + 2 \times \text{number of segments}$ <sup>4</sup>.

- `ig_paral(1)` = 3 (indicates a Orange partition)
- `ig_paral(2)` = the total number of segments for the partition (limited to 200 presently, see note for `ig_paral(4)` for Box partition above)
- `ig_paral(3)` = the first segment global offset
- `ig_paral(4)` = the first segment local extent

<sup>3</sup>The maximum value of the local extent in Y is presently 338; it can be increased by modifying the value of `Clim_MaxSegments` in `prism/src/lib/clim/src/mod_clim.F90` and in `prism/src/lib/psmile/src/mod_prism_proto.F90` and by recompiling Oasis3 and the PSMILE library.

<sup>4</sup>As for the Box partition, the maximum number of segments is presently 338; it can be increased by modifying the value of `Clim_MaxSegments`



**Figure 4.3:** Orange partition for one process

- `ig_paral(5)` = the second segment global offset
- `ig_paral(6)` = the second segment local extent
- ...
- `ig_paral(N-1)` = the last segment global offset
- `ig_paral(N)` = the last segment local extent

Figure 4.3 illustrates an Orange partition with 3 segments for one process. The other process partitions are not illustrated.

## 4.4 I/O-coupling field declaration

Each process implied in the coupling declares each field it will send or receive during the simulation.

- `CALL prism_def_var_proto(var_id, name, il_part_id, var_nodims, kinout, var_actual_shape, var_type, ierror)`
  - `var_id` [INTEGER; OUT]: coupling field ID
  - `name` [CHARACTER\*8; IN]: field symbolic name (as in the *namcouple*)
  - `il_part_id` [INTEGER; IN]: partition ID (returned by `prism_def_partition_proto`)
  - `var_nodims` [INTEGER, DIMENSION(2); IN]: `var_nodims(1)` is the rank of field array (1 or 2); `var_nodims(2)` is the number of bundles (always 1 for OASIS3).



- `kinout [INTEGER; IN]: PRISM_In` for fields received by the model, or `PRISM_Out` for fields sent by the model
- `var_actual_shape [INTEGER, DIMENSION(2*var_nodims(1)); IN]:` vector of integers giving the minimum and maximum index for each dimension of the coupling field array; for OASIS3, the minimum index has to be 1 and the maximum index has to be the extent of the dimension.
- `var_type [INTEGER; IN]:` type of coupling field array; put `PRISM_Real` for single or double precision real arrays<sup>5</sup>. No automatic conversion is implemented; therefore, all coupling fields exchanged through OASIS3 main process must be of same type<sup>6</sup>.
- `ierror [INTEGER; OUT]:` returned error code.

## 4.5 End of definition phase

Each process implied in the coupling closes the definition phase.

- `CALL prism_enddef_proto(ierr)`
  - `ierror [INTEGER; OUT]:` returned error code.

## 4.6 Sending and receiving actions

### 4.6.1 Sending a coupling field

In the model time stepping loop, each process implied in the coupling sends its part of the I/O or coupling field.

- `USE mod_prism_put_proto`  
Module to be used by the component model to call `prism_put_proto`.
- `CALL prism_put_proto(var_id, date, field_array, info)`
  - `var_id [INTEGER; IN]:` field ID (from corresponding `prism_def_var_proto`)
  - `date [INTEGER; IN]:` number of seconds in the run at the beginning of the timestep
  - `field_array [REAL, IN]:` I/O or coupling field array
  - `info [INTEGER; OUT]:` returned info code i.e.
    - \* `PRISM_Sent(=4)` if the field was sent to another model (directly or via OASIS3 main process)
    - \* `PRISM_LocTrans(=5)` if the field was only used in a time transformation (not sent, not output)
    - \* `PRISM_ToRest(=6)` if the field was written to a restart file only
    - \* `PRISM_Output(=7)` if the field was written to an output file only
    - \* `PRISM_SentOut(=8)` if the field was both written to an output file and sent to another model (directly or via OASIS3 main process)
    - \* `PRISM_ToRestOut(=9)` if the field was written both to a restart file and to an output file.
    - \* `PRISM_Ok(=0)` otherwise and no error occurred.

---

<sup>5</sup>PRISM standard is to exchange coupling fields declared `REAL(kind=SELECTED_REAL_KIND(12,307))`. By default, all real variables are declared as such in OASIS3. To exchange single precision coupling fields, OASIS3 has to be compiled with the pre-compiling key `use_realtypesingle`, the coupling fields must be declared `REAL(kind=SELECTED_REAL_KIND(6,37))` in the component models

<sup>6</sup>Coupling fields exchanged directly between two component models can have a type different from the ones exchanged through OASIS3 main process, as long as they are single or double precision real arrays in both models.

This routine may be called by the model at each timestep. The sending is actually performed only if the time obtained by adding the field lag (see 4.8) to the argument `date` corresponds to a time at which it should be activated, given the coupling or I/O period indicated by the user in the *namcouple* (see section 5). A field will not be sent at all if its coupling or I/O period indicated in the *namcouple* is greater than the total run time.

If a local time transformation is indicated for the field by the user in the *namcouple* (INSTANT, AVERAGE, ACCUMUL, T\_MIN or T\_MAX, see section 6), it is automatically performed and the resulting field is finally sent at the coupling or I/O frequency.

For a coupling field with a positive lag (see 4.8), the OASIS3 restart file (see section 7.3) is automatically written by the last `prism_put_proto` call of the run, if its argument `date` + the field lag corresponds to a coupling or I/O period. To force the writing of the field in its coupling restart file, one can use `prism_put_restart_proto` (see below).

This routine can use the buffered `MPI_BSend` (by default) or the standard blocking send `MPI_Send` (if `NOBSEND` is specified in the *namcouple* -see `$CHANNEL` section 5.2) to send the coupling fields.

## 4.6.2 Receiving a coupling field

In the model time stepping loop, each process implied in the coupling receives its part of the I/O-coupling field.

- `USE mod_prism_get_proto`  
Module to be used by the component model to call `prism_get_proto`.
- `CALL prism_get_proto(var_id, date, field_array, ierror)`
  - `var_id` [INTEGER; IN]: field ID (from corresponding `prism_def_var_proto`)
  - `date` [INTEGER; IN]: number of seconds in the run at the beginning of the timestep
  - `field_array` [REAL, OUT]: I/O or coupling field array
  - `info` [INTEGER; OUT]: returned info code
    - \* `PRISM_Recvd`(=3) if the field was received from another model (directly or via OASIS3 main process)
    - \* `PRISM_FromRest` (=10) if the field was read from a restart file only (directly or via OASIS3 main process)
    - \* `PRISM_Input` (=11) if the field was read from an input file only
    - \* `PRISM_RecvOut` (=12) if the field was both received from another model (directly or via OASIS3 main process) and written to an output file
    - \* `PRISM_FromRestOut` (=13) if the field was both read from a restart file (directly or via OASIS3 main process) and written to an output file
    - \* `PRISM_Ok` (=0) otherwise and no error occurred.

This routine may be called by the model at each timestep. The `date` argument is automatically analysed and the receiving action is actually performed only if `date` corresponds to a time for which it should be activated, given the period indicated by the user in the *namcouple*. A field will not be received at all if its coupling or I/O period indicated in the *namcouple* is greater than the total run time.

## 4.6.3 Auxiliary routines

- `CALL prism_put_inquire(var_id, date, info)`
  - `var_id` [INTEGER; IN]: field ID (from corresponding `prism_def_var_proto`)

- `date [INTEGER; IN]`: number of seconds in the run at the beginning of the timestep
- `info [INTEGER; OUT]`: returned info code.

This routine may be called at any time to inquire what would happen to the corresponding field (i.e. with same `var_id` and at same `date`) below the corresponding `prism_put_proto`. The possible value of the returned info code are as for `prism_put_proto`:

- `PRISM_Sent(=4)` if the field would be sent to another model (directly or via OASIS3 main process)
- `PRISM_LocTrans(=5)` if the field would be only used in a time transformation (not sent, not output)
- `PRISM_ToRest(=6)` if the field would be written to a restart file only
- `PRISM_Output(=7)` if the field would be written to an output file only
- `PRISM_SentOut(=8)` if the field would be both written to an output file and sent to another model (directly or via OASIS3 main process)
- `PRISM_ToRestOut(=9)` if the field would be written both to a restart file and to an output file.
- `PRISM_Ok(=0)` otherwise and no error occurred.

This is useful when the calculation of the corresponding `field_array` is CPU consuming and should be avoided if the field is not effectively used below the `prism_put_proto`.

- `CALL prism_put_restart_proto(var_id, date, ierror)`
  - `var_id [INTEGER; IN]`: field ID (from corresponding `prism_def_var_proto`)
  - `date [INTEGER; IN]`: number of seconds in the run at the beginning of the timestep
  - `info [INTEGER; OUT]`: returned error code (should be `PRISM_ToRest=6` if the restart writing was successful)

This routine forces the writing of the field with corresponding `var_id` in its coupling restart file (see section 7.3). If a time operation is specified for this field, the value of the field as calculated below the last `prism_put_proto` is written. If no time operation is specified, the value of the field transferred to the last `prism_put_proto` is written.

## 4.7 Termination

- `CALL prism_terminate_proto(ierror)`
  - `ierror [INTEGER; OUT]`: returned error code.

Each process must terminate the coupling by calling `prism_terminate_proto`<sup>7</sup> (normal termination). Oasis will terminate after all processes implied in the coupling call `prism_terminate_proto`. With MPI2, the run may be considered finished when Oasis terminates; to avoid problem, place the call to `prism_terminate_proto` at the very end in the component model code.

- `CALL prism_abort_proto(compid, routine_name, abort_message)`
  - `compid [INTEGER; IN]`: component model ID (from `prism_init_comp_proto`)
  - `routine_name; IN]`: name of calling routine
  - `abort_message; IN]`: message to be written out.

If a process needs to abort (abnormal termination), it must do so by calling `prism_abort_proto`. This will ensure a proper termination of all processes in the coupled model communicator. This routine writes the name of the calling model, the name of the calling routine, and the message to the job standard output (stdout).

---

<sup>7</sup>If the process called `MPI_Init` (before calling `prism_init_comp_proto`), it must also call `MPI_Finalize` explicitly, but only after calling `prism_terminate_proto`.

## 4.8 Coupling algorithms - SEQ and LAG concepts

Using PSMILE library, the user has full flexibility to reproduce different coupling algorithms, without modifying the component model codes themselves. In the component codes, the sending and receiving routines, respectively `prism_put_proto` and `prism_get_proto`, can be called at each model timestep, with the appropriate `date` argument giving the actual time (at the beginning of the timestep), expressed in “number of seconds since the start of the run”. This `date` argument is automatically analysed by the PSMILE<sup>8</sup> and depending on the coupling period, the lag and sequencing indices (LAG and SEQ), chosen by the user for each coupling field in the configuration file *namcouple*, different coupling algorithms can be reproduced **without modifying anything in the component model codes themselves**. The lag and sequence concepts and indices are explained in more details here below. These mechanisms are valid for fields exchanged through OASIS3 main process and for fields exchanged directly between the component models.

### 4.8.1 The lag concept

If no lag index or if a lag index equal to 0 is given by the user in the *namcouple* for a particular coupling field, the sending or receiving actions will actually be performed, below the `prism_put_proto` called in the source model or below the `prism_get_proto` called in the target model respectively, each time the `date` arguments on both sides match an integer number of coupling periods.

To match a `prism_put_proto` called by the source model at a particular date with a `prism_get_proto` called by the target model at a different date, the user has to define in the *namcouple* an appropriate lag index, LAG, for the coupling field (see section 5). The value of the LAG index must be expressed in “number of seconds”; its value is automatically added to the `prism_put_proto` date value and the sending action is effectively performed when the sum of the date and the lag matches an integer number of coupling periods. This sending action is automatically matched, on the target side, with the receiving action performed when the `prism_get_proto` date argument equals the same integer number of coupling periods.

#### 1. LAG concept first example

A first coupling algorithm, exploiting the LAG concept, is illustrated on figure 4.4.

On the 4 figures in this section, short black arrows correspond to `prism_put_proto` or `prism_get_proto` called in the component model that do not lead to any sending or receiving action; long black arrows correspond to `prism_put_proto` or `prism_get_proto` called in the component models that do effectively lead to a sending or receiving action; long red arrows correspond to `prism_put_proto` or `prism_get_proto` called in the component models that lead to a reading or writing of the coupling field from or to a coupling restart file (either directly or through OASIS3 main process).

During a coupling timestep, model A receives  $F_2$  and then sends  $F_1$ ; its timestep length is 4. During a coupling timestep, model B receives  $F_1$  and then sends  $F_2$ ; its timestep length is 6.  $F_1$  and  $F_2$  coupling periods are respectively 12 and 24. If  $F_1/F_2$  sending action by model A/B was used at a coupling timestep to match the model B/A receiving action, a deadlock would occur as both models would be initially waiting on a receiving action. To prevent this,  $F_1$  and  $F_2$  produced at the timestep before have to be used to match respectively the model B and model A receiving actions.

This implies that a lag of respectively 4 and 6 seconds must be defined for  $F_1$  and  $F_2$ . For  $F_1$ , the `prism_put_proto` performed at time 8 and 20 by model A will then lead to sending actions (as  $8 + 4 = 12$  and  $20 + 4 = 24$  which are coupling periods) that match the receiving actions performed at times 12 and 24 below the `prism_get_proto` called by model B. For  $F_2$ , the

---

<sup>8</sup>With the PIPE, SIPC, GMEM and previously with the CLIM communication techniques, no such analysis was performed. For PIPE, SIPC, and GMEM, the sending actions on the source side would automatically match the receiving actions on the target side on a FIFO (First In First Out) basis.





Figure 4.4: LAG concept first example



**Figure 4.5:** LAG concept second example

prism\_put\_proto performed at time 18 by model B then leads to a sending action (as  $18 + 6 = 24$  which is a coupling period) that matches the receiving action performed at time 24 below the prism\_get\_proto called by model A.

At the beginning of the run, as their LAG index is greater than 0, the first prism\_get\_proto will automatically lead to reading  $F_1$  and  $F_2$  from their coupling restart files. The user therefore have to create those coupling restart files for the first run in the experiment. At the end of the run,  $F_1$  having a lag greater than 0, is automatically written to its coupling restart file below the last  $F_1$  prism\_put\_proto if the date +  $F_1$  lag equals a coupling time. The analogue is true for  $F_2$ . These values will automatically be read in at the beginning of the next run below the respective prism\_get\_proto.

## 2. LAG concept second example

A second coupling algorithm exploiting the LAG concept is illustrated on figure 4.5. During its timestep, model A receives  $F_2$ , sends  $F_3$  and then  $F_1$ ; its timestep length is 6. During its timestep, model B receives  $F_1$ , receives  $F_3$  and then sends  $F_2$ ; its timestep length is also 6.  $F_1$ ,  $F_2$  and  $F_3$  coupling periods are both supposed to be equal to 12.

For  $F_1$  and  $F_2$  the situation is similar to the first example. If  $F_1/F_2$  sending action by model A/B was used at a coupling timestep to match the model B/A receiving action, a deadlock would occur as both models would be waiting on a receiving action. To prevent this,  $F_1$  and  $F_2$  produced at the timestep before have to be used to match the model A and model B receiving actions, which means that a lag of 6 must be defined for both  $F_1$  and  $F_2$ . For both coupling fields, the prism\_put\_proto performed at times 6 and 18 by the source model then lead to sending actions (as  $6 + 6 = 12$  and  $18$

+ 6 = 24 which are coupling periods) that match the receiving action performed at time 12 and 24 below the `prism_get_proto` called by the target model.

For  $F_3$ , sent by model A and received by model B, no lag needs to be defined: the coupling field produced by model A at the coupling timestep can be “consumed” by model B without causing a deadlock situation.

As in the first example, the `prism_get_proto` performed at the beginning of the run for  $F_1$  and  $F_2$ , automatically read them from their coupling restart files, and the last `prism_put_proto` performed at the end of the run automatically write them to their coupling restart file. For  $F_3$ , no coupling restart file is needed nor used as at each coupling period the coupling field produced by model A can be directly “consumed” by model B.

We see here how the introduction of appropriate LAG indices results in receiving, below the `prism_get_proto` in the target model, coupling fields produced, below the `prism_put_proto` by the source model, the timestep before; this is, in some coupling configurations, essential to avoid deadlock situations.

### 4.8.2 The sequence concept

To exchange the coupling fields going through OASIS3 main process (i.e. with status EXPORTED, AUXILIARY, or EXPOUT, see section 5), in a given order at each coupling timestep, a sequence index SEQ must be defined for each of them. This is not required for I/O fields or for coupling fields exchanged directly between the component models, i.e. with status IGNOUT, INPUT or OUTPUT. SEQ gives the position of the coupling field in the sequence.


A coupling algorithm, showing the SEQ concept, is illustrated on figure 4.6. All coupling field produced by the source model at the coupling timestep can be “consumed” by the target model at the same timestep without causing any deadlock situation; therefore,  $LAG = 0$  for all coupling fields. However, at each coupling timestep, a particular order of exchange must be respected;  $F_1$  must be received by model A before it can send  $F_2$ , which in turn must be received by model B before it can send  $F_3$ . Therefore,  $SEQ = 1, 2, 3$  must be defined respectively for  $F_1$ ,  $F_2$  and  $F_3$ . As all fields can be consumed at the time they are produced ( $LAG=0$  for all fields), there no reading/writing from/to coupling restart files.

### 4.8.3 A mix of lag and sequence: the sequential coupled model

One can run the same component models simultaneously or sequentially by defining the appropriate LAG and SEQ indices. In the example illustrated on figure 4.7, the models perform their `prism_put_proto` and `prism_get_proto` calls exactly as in the first lag example above: model A receives  $F_2$  and then sends  $F_1$ ; its timestep length is 4. During a coupling timestep, model B receives  $F_1$  and then sends  $F_2$ ; its timestep length is 6.  $F_1$  and  $F_2$  coupling periods are both 12. By defining a LAG index of -8 for  $F_1$ , the models will now run sequentially.

As the LAG for  $F_2$  is positive (6), a reading of  $F_2$  in its coupling restart file is automatically performed below the initial `prism_get_proto`. As the LAG for  $F_1$  is negative (-8), no reading from file is performed initially and model B waits; at time 8, a sending action is effectively performed below model A  $F_1$  `prism_put_proto` (as  $8 + LAG(-8) = 0$  which is the first coupling timestep) and matches the initial model B  $F_1$  `prism_get_proto`. Below the last model A  $F_1$  `prism_put_proto` of the run at time 116, a sending action is effectively performed, as  $116 + LAG(-8) = 108$  is a coupling period (as the LAG is negative, the field is not written to its coupling restart file). Below the last model B  $F_2$  `prism_put_proto` of the run at time 114, a writing of  $F_2$  to its restart file is performed, as  $114 + LAG(6) = 120$  is a coupling period and as the LAG is positive.

If the coupling fields are transformed through OASIS3 main process, it is important to indicate a sequence index. In fact, at each OASIS3 main process coupling timestep,  $F_1$  is necessarily treated after  $F_2$ . Therefore,  $SEQ(F_1) = 2$  and  $SEQ(F_2) = 1$ .



**Figure 4.6:** The SEQ concept







Figure 4.7: Mix of LAF and SEQ concepts



**Figure 4.8:** An example using `prism_put_restart_proto`

#### 4.8.4 Mixing sequential and parallel runs using `prism_put_restart_proto`

In the example illustrated on figure 4.8, the models run sequentially for the first run only and then run simultaneously. For the first run, the LAG and SEQ indices must be defined as in section 4.8.3. After the first run, the situation is similar to the one of section 4.8.1, and positive LAG must be defined for  $F_1$  and  $F_2$ . As their lag is positive, their corresponding first `prism_get_proto` will automatically lead to reading  $F_1$  and  $F_2$  from coupling restart files. In this case, model A has to write  $F_1$  to its restart file explicitly by calling `prism_put_restart_proto` (illustrated on the figure by an orange arrow) at the end of the first run; in fact,  $F_1$  lag being then negative, such writing is not automatically done below the last `prism_put_proto` of the first run.

## Chapter 5

# The OASIS3 configuration file *namcouple*

The OASIS3 configuration file *namcouple* contains, below pre-defined keywords, all user's defined information necessary to configure a particular coupled run. The *namcouple* is a text file with the following characteristics:

- the keywords used to separate the information can appear in any order;
- the number of blanks between two character strings is non-significant;
- all lines beginning with # are ignored and considered as comments.
- **blank lines are not allowed.**

The first part of *namcouple* is devoted to configuration of general parameters such as the number of models involved in the simulation, the number of fields, the communication technique, etc. The second part gathers specific information on each coupling or I/O field, e.g. their coupling period, the list of transformations or interpolations to be performed by OASIS3 and their associated configuring lines (described in more details in section 6), etc.

In the next sections, a simple *namcouple* example is given and all configuring parameters are described. The additional lines containing the different parameters required for each transformation are described in section 6. An example of a realistic *namcouple* can be found in directory `/prism/util/running/adjunct_files/oasis3/namcouple.toyclim.use`.

### 5.1 An example of a simple *namcouple*

The following simple *namcouple* configures a run in which an ocean, an atmosphere and an atmospheric chemistry models are coupled. The ocean provides only the SOSSTSST field to the atmosphere, which in return provides the field CONSFTOT to the ocean. One field (COSENHFL) is exchanged directly from the atmosphere to the atmospheric chemistry, and one field (SOALBEDO) is read from a file by the ocean.

```

First section

$SEQMODE
1

$CHANNEL
MPI2 NOBSEND
1 1 arg1
```

```

 3 1 arg2
 3 1 arg3
#
$NFIELDS
 4
#
$JOBNAME
 JOB
#
$NBMODEL
 3 ocemod atmmod chemod 55 70 99
#
$RUNTIME
 432000
#
$INIDATE
 00010101
#
$MODINFO
 NOT
#
$NLOGPRT
 2
#
$SCALTYPE
 1
#
#####
Second section
#
$STRINGS
#
Field 1
#
SOSSTSST SISUTESU 1 86400 5 sstoc.nc EXPORTED
182 149 128 64 toce atmo LAG=+14400 SEQ=+1
P 2 P 0
LOCTRANS CHECKIN MOZAIC BLASNEW CHECKOUT
#
AVERAGE
INT=1
at31topa 91 2 48
CONSTANT 273.15
INT=1
#
Field 2
#
CONSFTOT SOHEFLDO 6 86400 7 flxat.nc EXPORTED
atmo toce LAG=+14400 SEQ=+1
P 0 P 2
LOCTRANS CHECKIN SCRIPR CHECKOUT

```

```

#
 ACCUMUL
 INT=1
 CONSERV LR SCALAR LATLON 10 FRACAREA FIRST
 INT=1
#
Field
#
 COSENHFL SOSENHFL 37 86400 1 flda3.nc IGNOUT
 atmo atmo LAG=+7200 SEQ=+1
 LOCTRANS
 AVERAGE
#
Field 4
#
 SOALBEDO SOALBEDO 17 86400 0 SOALBEDO.nc INPUT
#
#####

```

## 5.2 First section of *namcouple* file

The first section of *namcouple* uses some predefined keywords prefixed by the \$ sign to locate the related information. The \$ sign must be in the second column. The first ten keywords are described hereafter:

- **\$SEQMODE:** On the line below this keyword is the maximum number of fields that have to be, at one particular coupling timestep, necessarily exchanged sequentially in a given order. For **\$SEQMODE**  $\geq 1$ , the position of each coupling field in the sequence has to be given by its SEQ index (see below and also section 4.8).
- **\$CHANNEL:** On the line below this keyword is the communication technique chosen. Choices are **MPI1** or **MPI2** for the CLIM communication technique and related PSMILe library, using **MPI1** or **MPI2** message passing. To run OASIS3 as an interpolator only, put **NONE** (see also section 6.1). The communication technique using Unix System V Shared Memory Segments, **SIPC**, is also supported. **PIPE**, or **GMEM** should still work but are not officially supported anymore and were not tested (corresponding sources can be retrieved from CERFACS CVS Server only).

To use the CLIM/MPI2 communication technique, the lines below **\$CHANNEL** are, e.g. for 3 models:

```

$CHANNEL
MPI2 NOBSEND
1 1 arg1
3 1 arg2
3 1 arg3

```

where **MPI2** is the message passing used in CLIM and PSMILe, and **NOBSEND** indicates that standard blocking send **MPI\_Send** should be used in place of the buffered **MPI\_BSend** to send the coupling fields.<sup>1</sup>

---

<sup>1</sup>Use the standard blocking send **MPI\_Send** if the coupling fields are necessarily sent and received in the same order, or on platforms for which **MPI\_Send** is implemented with a mailbox (e.g. VPPs; in this case, make sure that the size of the mailbox is sufficient). Use the less efficient buffered send **MPI\_BSend** on platforms for which **MPI\_Send** is not implemented with a mailbox if the coupling fields are not sent and received in the same order.

Note that below the call to `prism_enddef_proto`, the PSMILe tests whether or not the model has already attached to an MPI buffer. If it is the case, the PSMILe detaches from the buffer, adds the size of the pre-attached buffer to the size needed for the coupling exchanges, and reattaches to an MPI buffer. The model own call to `MPI_Buffer_Attach` must therefore be

If NOBSEND is not specified, the buffered send `MPI_BSend` will be used.

The following lines (one line per model listed on the `$NBMODEL` line) indicate for each model the total number of processes, the number of processes implied in the coupling, and possibly launching arguments. Here the first model runs on one process which is of course implied in the coupling and the argument passed to the model is "arg1"; the second and third models run on 3 processes but only one process is implied in the coupling (i.e. exchanging information with OASIS3 main process), and the argument passed to the models are respectively "arg2" and "arg3".

To use the CLIM/MPI1 communication technique, the `$CHANNEL` lines are as for MPI2 except that MPI2 is replaced by MPI1 and there is no launching arguments.

To use the SIPC communication technique, the user has to write only SIPC below the `$CHANNEL` keyword (corresponding sources can be retrieved from CERFACS CVS Server only).

- `$NFIELDS`: On the line below this keyword is the total number of fields exchanged and described in the second part of the *namcouple*.
- `$JOBNAME`: On the line below this keyword is a `CHARACTER*3` or `CHARACTER*4` variable giving an acronym for the given simulation.
- `$NBMODEL`: On the line below this keyword is the number of models running in the given experiment followed by `CHARACTER*6` variables giving their names. Then the user may indicate the maximum Fortran unit number used by the models. In the example, Fortran units above 55, 70, and 99 are free for respectively the ocean, atmosphere, and atmospheric chemistry models. If no maximum unit numbers are indicated, OASIS3 will suppose that units above 1024 are free. If `$CHANNEL` is NONE, `$NBMODEL` has to be 0 and there should be no model name and no unit number.
- `$RUNTIME`: On the line below this keyword is the total simulated time of the run, expressed in seconds. If `$CHANNEL` is NONE, `$RUNTIME` has to be the number of time occurrences of the field to interpolate from the restart file.
- `$INIDATE`: On the line below this keyword is the initial date of the run. The format is `YYYYMMDD`. This date is important only for the `FILLING` transformation and for printing information in OASIS3 log file *cplout*.
- `$MODINFO`: If coupling restart files are binary files (see section 7.3), the line below this keyword indicates if a header is encapsulated or not: it can be YES or NOT.
- `$NLOGPRT`: The line below this keyword refers to the amount of information that will be written to the OASIS3 log file *cplout* during the run. With 0, there is practically no output written to the *cplout*; with 1, only some general information on the run, the header of the main routines, and the names of the fields when treated appear in the *cplout*. Finally, with 2, the full output is generated.
- `$CALTYPE`: This new keyword gives the type of calendar used. For now, the calendar type is important only if `FILLING` analysis is used for a coupling field in the run and for printing information in OASIS3 log file *cplout*. Below this keyword, a number (0, 1 or n ) must be indicated by the user:
  - 0 : a 365 day calendar (no leap year)
  - 1 : a 365 or 366 (leap years) day calendar A year is a leap year if it can be divided by 4; however if it can be divided by 4 and 100, it is not a leap year; furthermore, if it can be divided by 4, 100 and 400, it is a leap year.
  - n :  $n \geq 1$  day month calendar.

---

done before the call to `prism_enddef_proto`. Furthermore, the model is not allowed to call `MPI_BSend` after the call to `prism_terminate_proto`, as the PSMILE definitively detaches from the MPI buffer in this routine. See the example in the toyatm model in `prism/src/mod/toyatm/src`

### 5.3 Second section of *namcouple* file

The second part of the *namcouple*, starting after the keyword \$STRINGS, contains coupling information for each coupling or I/O field. Its format depends on the field status given by the last entry on the field first line (EXPORTED, IGNOUT or INPUT in the example above). The field status may be the following (AUXILARY and EXPORTED are supported by all communication techniques, while the others are supported only by the PSMILe i.e. the CLIM/MPI1 or CLIM/MPI2 communication technique):

- AUXILARY: sent by the source model, received and used by OASIS3 main process for the transformation of other fields.
- EXPORTED: exchanged between component models and transformed by OASIS3 main process.
- EXPOUT: exchanged, transformed and also written to two output files, one before the sending action in the source model below the `prism_put_proto` call, and one after the receiving action in the target model below the `prism_get_proto` call.
- IGNORED: exchanged directly between the component models without being transformed by OASIS3 main process. The grid and partitioning of the source and target models have to be identical.
- IGNOUT: exchanged directly between the component models without being transformed by OASIS3 main process and written to two output files, one before the sending action in the source model below the `prism_put_proto` call, and one after the receiving action in the target model below the `prism_get_proto` call. The grid and partitioning of the source and target models have to be identical.
- INPUT: simply read in from the input file by the target model PSMILe below the `prism_get_proto` call at appropriate times corresponding to the input period indicated by the user in the *namcouple*. See section 7.4 for the format of the input file.
- OUTPUT: simply written out to an output file by the source model PSMILe below the `prism_put_proto` call at appropriate times corresponding to the output period indicated by the user in the *namcouple*. The name of the output file (one per field) is automatically built based on the field name and initial date of the run (\$INIDATE).

#### 5.3.1 Second section of *namcouple* for EXPORTED, AUXILARY and EXPOUT fields

The first 3 lines for fields with status EXPORTED, AUXILARY and EXPOUT are as follows:

```
SOSSTSST SISUTESU 1 86400 5 sstoc.nc sstat.nc EXPORTED
182 149 128 64 toce atmo LAG=+14400 SEQ=+1
P 2 P 0
```

where the different entries are:

- Field first line:
  - SOSSTSST : symbolic name for the field in the source model (CHARACTER\*8). It has to match the argument name of the corresponding field declaration in the source model; see `prism_def_var_proto` in section 4.4.
  - SISUTESU : symbolic name for the field in the target model (CHARACTER\*8). It has to match the argument name of the corresponding field declaration in the target model; see `prism_def_var_proto` in section 4.4.
  - 1 : index in auxiliary file `cf_name_table.txt` used by OASIS3 and PSMILe to identify corresponding CF standard name and units (see 7.1).
  - 86400 : coupling and/or I/O period for the field, in seconds. (If \$CHANNEL is NONE, put “1”.)
  - 5 : number of transformations to be performed on this field.

- sstoc.nc : name of the coupling restart file for the field (CHARACTER\*8); it may be a binary of netCDF file (for more detail, see section 7.3).
- sstat.nc : name of the field output file, may be indicated for NONE (and PIPE) communication techniques only. It may be a binary of netCDF file (see section 7.3).
- EXPORTED : field status.
- Field second line:
  - 182 : number of points for the source grid first dimension (optional if a netCDF coupling restart file is used).
  - 149 : number of points for the source grid second dimension (optional if a netCDF coupling restart file is used).
  - 128 : number of points for the target grid first dimension (optional if a netCDF coupling restart file is used).
  - 64 : number of points for the target grid second dimension (optional if a netCDF coupling restart file is used).
  - toce : prefix of the source grid name in grid data files (see section 7.2) (CHARACTER\*4)
  - atmo : prefix of the target grid name in grid data files (CHARACTER\*4)
  - LAG=+14400: lag index for the field expressed in seconds (CLIM/MPI1 or CLIM/MPI2 communication technique only, see section 4.8). Note that in mode NONE a LAG has to be defined so that the input file is opened initially.
  - SEQ=+1: optional sequence index for the field (CLIM/MPI1 or CLIM/MPI2 communication technique only, see section 4.8).
- Field third line
  - P : source grid first dimension characteristic ('P': periodical; 'R': regional).
  - 2 : source grid first dimension number of overlapping grid points.
  - P : target grid first dimension characteristic ('P': periodical; 'R': regional).
  - 0 : target grid first dimension number of overlapping grid points.

The fourth line gives the list of transformations to be performed for this field. There is then one or more additional configuring lines describing some parameters for each transformation. These additional lines are described in more details in the section 6.

### 5.3.2 Second section of *namcouple* for IGNORED, IGNOUT, and OUTPUT fields

The first 2 lines for fields with status IGNORED or IGNOUT or OUTPUT are as follows:

```
COSENHFL SOSENHFL 37 86400 1 flda3.nc IGNOUT
atmo toce LAG=+7200 SEQ=+1
```

entries are as for EXPORTED fields, except that there is no output file name on the first line.

For OUTPUT fields, there is no target model and therefore no target symbolic name; the source symbolic name must be repeated twice on the field first line. Also, there is no coupling restart file name (*flda3.nc* here), no LAG index and no SEQ index.

For IGNORED fields, the name used in the coupling restart file (if any) must be the target symbolic name.

The third line is LOCTRANS if this transformation is chosen for the field. Note that LOCTRANS is the only transformation supported for IGNORED, IGNOUT and OUTPUT fields (as it is performed directly in the PSMILe below the `prism_put_proto` call). If LOCTRANS is chosen, a fourth line giving the name of the time transformation is required. For more detail on LOCTRANS, see section 6.2.



### 5.3.3 Second section of *namcouple* for INPUT fields

The first and only line for fields with status INPUT is:

```
SOALBEDO SOALBEDO 17 86400 0 SOALBEDO.nc INPUT
```

- SOALBEDO: symbolic name for the field in the target model (CHARACTER\*8 repeated twice)
- 17: index in auxiliary file `cf_name_table.txt` (see above for EXPORTED fields)
- 86400: input period in seconds
- 0: number of transformations (always 0 for INPUT fields)
- SOALBEDO.nc: CHARACTER\*32 giving the input file name (for more detail on its format, see section 7.4)
- INPUT: field status.

## Chapter 6

# The transformations and interpolations in OASIS3

Different transformations and 2D interpolations are available in OASIS3 to adapt the coupling fields from a source model grid to a target model grid. They are divided into five general classes that have precedence one over the other in the following order: time transformation (with CLIM/MPI1-MPI2 and PSMILe only), pre-processing, interpolation, “cooking”, and post-processing. This order of precedence is conceptually logical, but is also constrained by the OASIS3 software internal structure.

In the following paragraphs, it is first described how to use OASIS3 in an interpolator-only mode. Then a description of each transformation with its corresponding configuring lines is given.

### 6.1 Using OASIS3 in the interpolator-only mode

OASIS3 can be used in an interpolator-only mode, in which case it transforms fields without running any model. It is recommended to use first OASIS3 in this mode to test different transformations and interpolations without having to run the whole coupled system. In the interpolator-only mode, all transformations, except the time transformations, are available.

To run OASIS3 in an interpolator-only mode, the user has to prepare the *namcouple* as indicated in sections 5.2 and 5.3. In particular, NONE has to be chosen below the keyword \$CHANNEL; “0” (without any model name and Fortran unit number) must be given below the keyword \$NBMODEL; \$RUNTIME has to be the number of time occurrences of the field to interpolate from the NetCDF input file<sup>1</sup>; finally, the “coupling” period of the field (4th entry on the field first line) must be always “1”. Note that if \$RUNTIME is smaller than the total number of time occurrences in the input file, the first \$RUNTIME occurrences will be interpolated.

The name of the input file which contains the fields to interpolate is given by the 6th entry on the field first line (see 5.3). A positive LAG has to be defined for the field so that the input file is opened at the beginning of the run. After their transformation, OASIS3 writes them to their output file which name is the 7th entry on the first line. Note that all fields have to be present in the same restart file.

The time variable in the input file, if any, is recognized by the its attribute “units”. The acceptable units for time are listed in the *udunits.dat* file (3). This follows the CF convention. A practical example on how to use OASIS3 in a interpolator-only mode is given in *prism/util/running/toymodel/testinterp* (from CERFACS CVS only).

The configuring parameters that have to be defined in the *namcouple* for each transformation in the interpolator-only mode or in the coupling mode are described here after.

---

<sup>1</sup>For binary input file, only one time occurrence may be interpolated

## 6.2 The time transformations

LOCTRANS can be chosen as first transformation if CLIM/MPI1-MPI2 communication and the PSMILe interface are used. LOCTRANS requires one configuring line on which a time transformation, automatically performed below the call to PSMILe `prism_put_proto`, should be indicated:

- **INSTANT**: no time transformation, the instantaneous field is transferred;
- **ACCUMUL**: the field accumulated over the previous coupling period is transferred;
- **AVERAGE**: the field averaged over the previous coupling period is transferred;
- **T\_MIN**: the minimum value of the field for each source grid point over the previous coupling period is transferred;
- **T\_MAX**: the maximum value of the field for each source grid point over the previous coupling period is transferred;
- **ONCE**: only one `prism_put_proto` or `prism_get_proto` will be performed; this is equivalent to giving the length of the run as coupling or I/O period.

## 6.3 The pre-processing transformations

The following transformations are available in the pre-processing part of OASIS3, controlled by `preproc.f`.

- **REDGLO** (not recommended anymore as interpolations now exist directly for Reduced grids):  
REDGLO (routine `redglo.f`) performs the interpolation from a Reduced grid to a Gaussian one. The interpolation is linear and performed latitude circle per latitude circle. When present, REDGLO must be the first pre-processing transformation performed. The configuring line is as follows:

```
REDGLO operation
$NNBRLAT $CDMSK
```

where xxx is half the number of latitude circles of the Gaussian grid. For example, for a T42 with 64 latitude circles, \$NNBRLAT is "NO32". In the current version, it can be either NO16, NO24, NO32, NO48, NO80, NO160. \$CDMSK is a flag indicating if non-masked values have to be extended to masked areas before interpolation (\$CDMSK = SEALAND) using the Reduced grid mask (see section 7.2) or if the opposite has to be performed (\$CDMSK = LANDSEA). If \$CDMSK = NOEXTRAP, then no extrapolation is performed.

- **INVERT**:

INVERT (routine `invert.f`) reorders a field so that it goes from south to north and from west to east (the first point will be the southern and western most one; then it goes parallel by parallel going from south to north). INVERT should be used only for fields associated to A, B, G, L, Z, or Y grids (see annexe A) but produced by the source model from North to South and/or from East to West. INVERT does not work for Reduced ('D') or unstructured ('U') grids (see annexe A).

The generic input line is as follows:

```
INVERT operation
$CORLAT $CORLON
```

\$CORLAT = NORSUD or SUDNOR and \$CORLON = ESTWST or WSTEST describes the orientation of the source field in longitude and latitude, respectively.

- **MASK**:

MASK (routine `masq.f`) is used before the analysis EXTRAP. A given REAL value VALMASK is assigned to all masked points following the source grid mask (see section 7.2), so they can be detected by EXTRAP.

The generic input line is as follows:

```
MASK operation
$VALMASK
```

approaches the maximum value that your computing platform can represent; choose a value well outside the range of your field values but not too large.

- **EXTRAP:**

EXTRAP (routine `extrap.f`) performs the extrapolation of a field over its masked points. The analysis MASK must be used just before, so that EXTRAP can identify masked points. Note that EXTRAP does not work for Reduced ('D') or unstructured ('U') grids (see section A).

Two methods of extrapolation are available. With NINENN, a N-nearest-neighbour method is used. The procedure is iterative and the set of remaining masked points evolves at each iteration. The configuring line is:

```
EXTRAP operation for $CMETH = NINENN
$CMETH $NV $NIO $NID
```

$\$CMETH = NINENN$ ;  $\$NV$  is the minimum number of neighbours required to perform the extrapolation (with a maximum of 4)<sup>2</sup>;  $\$NIO$  is the flag that indicates if the weight-address-and-iteration-number dataset will be calculated and written by OASIS3 ( $\$NIO=1$ ), or only read ( $\$NIO=0$ ) in file *nweights* (see section 7.5);  $\$NID$  is the identifier for the weight-address-iteration-number dataset in all the different EXTRAP/NINENN datasets in the present coupling.<sup>3</sup>

With  $\$CMETH = WEIGHT$ , an N-weighted-neighbour extrapolation is performed. In that case, the user has to build the grid-mapping file, giving for each target grid point the weights and addresses of the source grid points used in the extrapolation; the structure of this file has to follow the OASIS3 generic structure for transformation auxiliary data files (see section 7.5).

The configuring line is:

```
EXTRAP operation for $CMETH = WEIGHT
$CMETH $NV $CFILU $NUMLU $NID
```

$\$CMETH = WEIGHT$ ;  $\$NV$  is the maximum number of neighbours required by the extrapolation operation;  $\$CFILU$  and  $\$NUMLU$  are the grid-mapping file name and associated logical unit;  $\$NID$  is the identifier for the relevant grid-mapping dataset in all different EXTRAP/WEIGHT transformations in the present coupling.

- **CHECKIN:**

CHECKIN (routine `chkfld.f`) calculates the mean and extremum values of the source field and prints them to the coupler log file *cplout*.

The generic input line is as follows:

```
CHECKIN operation
$NINT
```

$\$NINT=1$  or 0, depending on whether or not the source field integral is also calculated and printed.

- **CORRECT:**

CORRECT (routine `correct.f`) reads external fields from binary files and uses them to modify the coupling field. This transformation can be used, for example, to perform flux correction on the field.

This transformation requires at least one configuration line with two parameters:

```
CORRECT operation
$XMULT $NBFIELDS
```

---

<sup>2</sup>For some grids, the extrapolation may not converge if  $\$NV$  is too large.

<sup>3</sup>An EXTRAP/NINENN analysis is automatically performed within GLORED analysis but the corresponding datasets have to be distinct; this is automatically checked by OASIS3 at the beginning of the run.

\$XMULT is the multiplicative coefficient of the current field, and \$NBFIELDS the number of additional fields to be combined with the current field. For each additional field, an additional configuring line is required:

```
nbfields lines
 $CLOC $AMULT $CFIELD $NUMLU
```

\$CLOC and \$AMULT, \$CFIELD and \$NUMLU are respectively the symbolic name, the multiplicative coefficient, the file name and the associated logical unit on which the additional field is going to be read. The structure of the file has to follow the structure of OASIS3 binary coupling restart files (see section 7.3).

## 6.4 The interpolation

The following interpolations, controlled by `interp.f`, are available in OASIS3.

- **BLASOLD:**

BLASOLD (routine `blasold.f`) performs a linear combination of the current coupling field with other coupling fields or with a constant before the interpolation *per se*.

This transformation requires at least one configuring line with two parameters:

```
BLASOLD operation
 $XMULT $NBFIELDS
```

\$XMULT is the multiplicative coefficient of the current field, and \$NBFIELDS the number of additional fields to be combined with the current field. For each additional field, an additional input line is required:

```
nbfields lines
 $CNAME $AMULT
```

where \$CNAME and \$AMULT are the symbolic name and the multiplicative coefficient for the additional field. To add a constant value to the original field, put \$XMULT = 1, \$NBFIELDS = 1, \$CNAME = CONSTANT, \$AMULT = value to add.

- **SCRIPR:**

SCRIPR is new in OASIS3 and gathers the interpolation techniques offered by Los Alamos National Laboratory SCRIP 1.4 library<sup>4</sup>(1). SCRIPR routines are in `prism/src/lib/scrip`. See also the SCRIP 1.4 documentation in `prism/src/mod/oasis3/doc/SCRIPusers.pdf`. Linking with NetCDF library is mandatory when using SCRIPR interpolations.

The following types of interpolations are available:

- DISTWGT performs N nearest-neighbour interpolation (N neighbours). All grid types are supported. If the N nearest neighbours of a target grid point are masked, no value is calculated for that point; transformations MASK and EXTRAP should be used to avoid problems for those points. No values are calculated for masked target grid points.

The configuring line is:

```
SCRIPR/DISWGT
 $CMETH $CGRS $CFTYP $REST $NBIN $NV $ASSCMP $PROJCART
* $CMETH = DISTWGT.
* $CGRS is the source grid type (LR, D or U)- see annexe A.
* $CFTYP is the field type: SCALAR if the field is a scalar one, or VECTOR_I or VECTOR_J
 whether the field represents respectively the first or the second component of a vector field
```

---

<sup>4</sup>See the copyright statement in annexe C.2.

(see paragraph **Support of vector fields** below). Note that VECTOR, which is fact leads to a scalar treatment of the field (as in the previous versions), is still supported.

- \* \$REST is the search restriction type: LATLON or LATITUDE (see SCRIP 1.4 documentation). Note that for D or U grid, the restriction may influence slightly the result near the borders of the restriction bins.
  - \* \$NBIN the number of restriction bins (see SCRIP 1.4 documentation).
  - \* \$NV is the number of neighbours used.
  - \* \$ASSCMP: optional, for VECTOR\_I or VECTOR\_J vector fields only; the source symbolic name of the associated vector component.
  - \* \$PROJCART: optional, for vector fields only; should be PROJCart if the user wants the vector components to be projected in a Cartesian coordinate system before interpolation (see paragraph **Support of vector fields** below).
- GAUSWGT performs N nearest-neighbour interpolation weighted by a gaussian function. All grid types are supported. Behaviour for source and target masked points is the same than for DISTWGT. The configuring line is:

```
SCRIPR/GAUSWGT
$CMETH $CGRS $CFTYP $REST $NBIN $NV $VAR $ASSCMP $PROJCART
* $CMETH = GAUSWGT
* $VAR, which must be given as a REAL value (e.g 2.0 and not 2), defines the weight given to a neighbour source grid point as inversely proportional to $\exp(-1/2 \cdot d^2/\sigma^2)$ where d is the distance between the source and target grid points, and $\sigma^2 = \$VAR \cdot \bar{d}^2$ where \bar{d}^2 is the average distance between two source grid points (calculated automatically by OASIS3).
```

- BILINEAR performs bilinear interpolation.
- BICUBIC performs a bicubic interpolation.

For BILINEAR and BICUBIC, Logically-Rectangular (LR) and Reduced (D) source grid types are supported. If the some of the source grid points NORMlly used in the bilinear or bicubic interpolation are masked, another algorithm is applied; at least, the nearest non-masked source neighbour is used. No values are calculated for masked target grid points.

The configuring line is:

```
SCRIPR/BILINEAR or SCRIPR/BICUBIC
$CMETH $CGRS $CFTYP $REST $NBIN $ASSCMP $PROJCART
* $CMETH = BILINEAR or BICUBIC
* $CGRS is the source grid type (LR or D)
* $CFTYP, $NBIN, $ASSCMP $PROJCART are as for DISTWGT.
* $REST is as for DISTWGT, except that only LATITUDE is possible for a Reduced (D) source grid.
```

- CONSERV performs 1st or 2nd order conservative remapping, which means that the weight of a source cell is proportional to area intersected by target cell. Values are possibly calculated for all target grid points whether they are masked or not. The source grid mask is taken into account in the NORMlisation (see below).

The configuring line is:

```
SCRIPR/CONSERV
$CMETH $CGRS $CFTYP $REST $NBIN $NORM $ORDER $ASSCMP $PROJCART
* $CMETH = CONSERV
* $CGRS is the source grid type: LR, D and U are supported for 1st-order remapping if the grid corners are given by the user in the grid data file which is, in this case, necessarily
```

a netCDF file (`grids.nc`, see section 7.2); only LR is supported if the grid corners are not available in the grid data file and therefore have to be calculated automatically by OASIS3. For second-order remapping, only LR is supported because the gradient of the coupling field used in the transformation has to be calculated automatically by OASIS3.

- \* `$CFTYP`, `$REST`, `$NBIN`, `$ASSCMP`, and `$PROJCART` are as for `DISTWGT`. Note that for `CONSERV` the restriction does not influence the result.
- \* `$NORM` is the NORMlization option:
  - `FRACAREA`: The sum of the source cell intersected areas is used to NORMlize each target cell field value: the flux is not locally conserved, but the flux value itself is reasonable.
  - `DESTAREA`: The total target cell area is used to NORMlize each target cell field value even if it only partly intersects the source grid cells: local flux conservation is ensured, but unreasonable flux values may result.
  - `FRACNNEI`: as `FRACAREA`, except that the source nearest neighbour is used for target cells that do not intersect any unmasked source cells.
- \* `$ORDER`: `FIRST` or `SECOND`<sup>5</sup> for first or second order remapping respectively (see `SCRIP 1.4` documentation).

### Support of vector fields

SCRIPR supports 2D vector interpolation. The two vector components have to be identified by replacing `$CFTYP` by `VECTOR_I` or `VECTOR_J` and have to be associated by replacing `$ASSCMP`, for each component field, by the source symbolic name of the associated vector component in (see above). A proper example of vector interpolation is given in the interpolator-only mode example (see details in `prism/util/running/testinterp/README_testinterp`). The details of the vector treatment, performed by the routines `scriprmp_vector.F90` and `rotations.F90` in `prism/src/lib/scrpr/src` are the following:

- If the angles of the source grid local coordinate system are defined in the *grids.nc* data file (see section 7.2), an automatic rotation from the local to the geographic spherical coordinate system is performed.
- If the two source vector components are not defined on the same source grid, one component is automatically interpolated on the grid of the other component.
- If the user put the `PROJCART` keyword at the end of the `SCRIPR` configuring line (see above), projection of the two vector components in a Cartesian coordinate system, interpolation of the resulting 3 Cartesian components, and projection back in the spherical coordinate system are performed. In debug mode (compilation with `DEBUG` pre-compiling key), the resulting vertical component in the spherical coordinate system after interpolation is written to a file `projection.nc`; as the source vector is horizontal, this component should be very close to 0.
- If the user did not put the `PROJCART` keyword at the end of the `SCRIPR` configuring line, the two spherical coordinate system components are interpolated.
- If the angles of the target grid local coordinate system are defined in the *grids.nc* data file (see section 7.2), an automatic rotation from the geographic spherical to the local coordinate system is performed.
- The first and second components of the interpolated vector field are then present in the target fields associated respectively to the first and second source vector component. The target grids for the two vector components can be different.

---

<sup>5</sup>`CONSERV/SECOND` has not been tested in detail.

- **INTERP:**

INTERP gathers different techniques of interpolation controlled by routine `fiasco.f`. The following interpolations are available:

- BILINEAR performs a bilinear interpolation using 4 neighbours.
- BICUBIC performs a bicubic interpolation.
- NNEIBOR performs a nearest-neighbour interpolation.

These three interpolations are performed by routines in `/prism/src/lib/fscint` and support only A, B, G, L, Y, or Z grids (see annexe A). All sources grid points, masked or not, are used in the calculation. To avoid the ‘contamination’ by masked source grid points, transformations MASK and EXTRAP should be used. Values are calculated for all target grid points, masked or not.

The configuring line is as follows:

- ```
# BILINEAR or BICUBIC or NNEIBOR interpolation
  $CMETH $CGRS $CFTYP
* $CMETH = BILINEAR, BICUBIC or NNEIBOR
* $CGRS is the source grid type (A, B, G, L, Y, or Z, see annexe A)
* $CFTYP the field type (SCALAR or VECTOR). VECTOR has an effect for target grid
  points located near the pole: the sign of a source value located on the other side of the
  pole will be reversed.
```
- SURFMESH (routines in `/prism/src/lib/anaism`) is a first-order conservative remapping from a fine to a coarse grid (the source grid must be finer over the whole domain) and supports only Lat-Lon grids. For a target grid cell, all the underlying not masked source grid cells are found and the target grid field value is the sum of the source grid field values weighted by the overlapped surfaces. No value is assigned to masked cells. Note that it is not recommended to use this interpolation anymore, as the more general SCRIPR/CONSERV remapping is now available. The configuring line is as follows:


```
# SURFMESH remapping
  $CMETH $CGRS $CFTYP $NID $NV $NIO
* $CMETH = SURFMESH
* $CGRS and $CFTYP are as for BILINEAR
* $NID is the identifier for the weight-address dataset in all the different INTERP/SURFMESH
  datasets in the present coupling. This dataset will be calculated by OASIS3 if $NIO= 1,
  or only read if $NIO= 0.
* $NV is the maximum number of source grid meshes used in the remapping.
```
 - GAUSSIAN (routines in `/prism/src/lib/anaisg`) is a gaussian weighted nearest-neighbour interpolation technique. The user can choose the variance of the function and the number of neighbours considered. The masked source grid points are not used and no value are calculated for masked target grid points.

The configuring line is:

- ```
GAUSSIAN interpolation
 $CMETH $CGRS $CFTYP $NID $NV $VAR $NIO
* $CMETH = GAUSSIAN
* $CGRS is the source grid type (LR, D or U) and $CFTYP is as for the DISTWGT
* $NID is the identifier for the weight-address dataset in all the different INTERP/GAUSSIAN
 datasets in the present coupling. This weight-address dataset will be calculated by OA-
 SIS3 if $NIO= 1, or only read if $NIO= 0.
* $NV is the number of neighbours used in the interpolation.
```



\* \$VAR is as for SCRIPR/GAUSWGT (see above).

- **MOZAIC:**

MOZAIC performs the mapping of a field from a source to a target grid. The grid-mapping dataset, i.e. the weights and addresses of the source grid points used to calculate the value of each target grid point are defined by the user in a file (see section 7.5). The configuring line is:

```
MOZAIC operation
```

```
 $CFILE $NUMLU $NID $NV
```

- \$CFILE and \$NUMLU are the grid-mapping file name and associated logical unit on which the grid-mapping dataset is going to be read),
- \$NID the identifier for this grid-mapping dataset in all MOZAIC grid-mapping datasets in the present coupling
- \$NV is the maximum number of target grid points use in the mapping.

- **NOINTERP:**

NOINTERP is the analysis that has to be chosen when no other transformation from the interpolation class is chosen. There is no configuring line.

- **FILLING:**

FILLING (routine /prism/src/mod/oasis3/src/filling.f) performs the blending of a regional data set with a climatological global one for a Sea Surface Temperature (SST) or a Sea Ice Extent field. This occurs when coupling a non-global ocean model with a global atmospheric model. FILLING can only handle fields on Logically Rectangular grid (LR, but also A, B, G, L, Y, and Z grids, see section A.

The global data set has to be a set of SST given in Celsius degrees (for the filling of a Sea Ice Extent field, the presence or absence of ice is deduced from the value of the SST). The frequency of the global set can be interannual monthly, climatological monthly or yearly.

The blending can be smooth or abrupt. If the blending is abrupt, only model values are used within the model domain, and only the global data set values are used outside. If the blending is smooth, a linear interpolation is performed between the two fields within the model domain over narrow bands along the boundaries. The linear interpolation can also be performed giving a different weight to the regional or and global fields.

The smoothing is defined by parameters in /prism/src/mod/oasis3/src/mod\_smooth.F90.

The lower smoothing band in the global model second dimension is defined by *nsltb* (outermost point) and *nslte* (innermost point); the upper smoothing band in the global model second dimension is defined by *nnltb* (outermost point) and *nnlte* (innermost point). The parameter *qalfa* controls the weights given to the regional and to the global fields in the linear interpolation. *qalfa* has to be  $1/(nslte - nsltb)$  or  $1/(nnlte - nnltb)$ . For the outermost points (*nsltb* or *nnltb*) in the smoothing band, the weight given to the regional and global fields will respectively be 0 and 1; for the innermost points (*nslte* or *nnlte*) in the smoothing band, the weight given to the regional and global fields will respectively be 1 and 0; within the smoothing band, the weights will be a linear interpolation of the outermost and innermost weights.

The smoothing band in the global model first dimension will be a band of *nliss* points following the coastline. To calculate this band, OASIS3 needs *nwlgm*, the greater first dimension index of the lower coastline and *nelgm*, the smaller first dimension index on the upper coastline. The parameter *qbeta* controls the weights given to the regional and to the global fields in the linear interpolation. *qbeta* has to be  $1/(nliss - 1)$ . The weights given to the regional and global fields in the global model first dimension smoothing bands will be calculated as for the second dimension.

The user must provide the climatological data file with a specific format described in 7.5. When one uses FILLING for SST with smooth blending, thermodynamics consistency requires to modify the heat fluxes over the blending regions. The correction term is proportional to the difference between

the blended SST and the original SST interpolated on the atmospheric grid and can be written out on a file to be read later, for analysis CORRECT for example. In that case, the symbolic name of the flux correction term read through the input file *namcouple* must correspond in FILLING and CORRECT analyses.

In case the regional ocean model includes a coastal part or islands, a sea-land mask mismatch may occur and a coastal point correction can be performed if the field has been previously interpolated with INTER/SURFMESH. In fact, the mismatch could result in the atmosphere undesirably “seeing” climatological SST’s directly adjacent to ocean model SST’s. Where this situation arises, the coastal correction consists in identifying the suitable ocean model grid points that can be used to extrapolate the field, excluding climatological grid points.

This analysis requires one configuring line with 3, 4 or 6 arguments.

1. If FILLING performs the blending of a regional data set with a global one for the Sea Ice Extent, the 3-argument input line is:

```
Sea Ice Extent FILLING operation
$CFILE $NUMLU $CMETH
```

the file name for the global data set, \$NUMLU the associated logical unit. \$CMETH, the FILLING technique, is a CHARACTER\*8 variable: the first 3 characters are either SMO, smooth filling, or RAW, no smoothing ; the next three characters must be SIE for a Sea Ice Extent filling operation; the last two define the time characteristics of the global data file, respectively MO, SE and AN for interannual monthly, climatological monthly and yearly. Note that in all cases, the global data file has to be a Sea Surface Temperature field in Celsius degrees.

2. If FILLING performs the blending of a regional data set with a global one for the Sea Surface Temperature without any smoothing, the 4-argument input line is:

```
#Sea Surface Temperature FILLING operation without smoothing
$CFILE $NUMLU $CMETH $NFCOAST
```

\$CFILE, \$NUMLU are as for the SIE filling. In this case however, \$CMETH(1:3) = RAW, \$CMETH(4:6) = SST, and the last two characters define the time characteristics of the global data file, as for the SIE filling. \$NFCOAST is the flag for the calculation of the coastal correction ( 0 no, 1 yes).

3. If FILLING performs the blending of a regional data set with a global one for the Sea Surface Temperature with smoothing, the 6-argument input line is:

```
#Sea Surface Temperature FILLING operation with smoothing
$CFILE $NUMLU $CMETH $NFCOAST $CNAME $NUNIT
```

where \$CFILE, \$NUMLU and \$NFCOAST are as for the SST filling without smoothing. In this case, \$CMETH(1:3) = SMO, \$CMETH(4:6) = SST, and the last two characters define the time characteristics of the global data file, as for the SIE filling. \$CNAME is the symbolic name for the correction term that is calculated by OASIS3 and \$NUNIT the logical unit on which it is going to be written.

## 6.5 The “cooking” stage

The following analyses are available in the “cooking” part of OASIS3, controlled by *cookart.f*.

- **CONSERV:**

CONSERV(routine /prism/src/mod/oasis3/src/conserv.f) performs global flux conservation. The flux is integrated on both source and target grids, without considering values of masked points, and the residual (target - source) is calculated. Then all flux values on the target grid

are uniformly modified, according to their corresponding surface. This analysis requires one input line with one argument:

```
CONSERV operation
 $CMETH
```

version, only global flux conservation can be performed. Therefore \$CMETH must be GLOBAL.

- **SUBGRID:**

SUBGRID can be used to interpolate a field from a coarse grid to a finer target grid (the target grid must be finer over the whole domain). Two types of subgrid interpolation can be performed, depending on the type of the field.

For solar type of flux field (\$SUBTYPE = SOLAR), the operation performed is:

$$\Phi_i = \frac{1 - \alpha_i}{1 - \alpha} F$$

where  $\Phi_i$  ( $F$ ) is the flux on the fine (coarse) grid,  $\alpha_i$  ( $\alpha$ ) an auxiliary field on the fine (coarse) grid (e.g. the albedo). The whole operation is interpolated from the coarse grid with a grid-mapping type of interpolation; the dataset of weights and addresses has to be given by the user.

For non-solar type of field (\$SUBTYPE = NONSOLAR), a first-order Taylor expansion of the field on the fine grid relatively to a state variable is performed (for instance, an expansion of the total heat flux relatively to the SST):

$$\Phi_i = F + \frac{\partial F}{\partial T}(T_i - T)$$

where  $\Phi_i$  ( $F$ ) is the heat flux on the fine (coarse) grid,  $T_i$  ( $T$ ) an auxiliary field on the fine (coarse) grid (e.g. the SST) and  $\frac{\partial F}{\partial T}$  the derivative of the flux versus the auxiliary field on the coarse grid. This operation is interpolated from the coarse grid with a grid-mapping type of interpolation; the dataset of weights and addresses has to be given by the user.

This analysis requires one input line with 7 or 8 arguments depending on the type of subgrid interpolation.

1. If the the SUBGRID operation is performed on a solar flux, the 7-argument input line is:

```
SUBGRID operation with $SUBTYPE=SOLAR
 $CFILE $NUMLU $NID $NV $SUBTYPE $CCOARSE $CFINE
```

\$CFILE and \$NUMLU are the subgrid-mapping file name and associated logical unit (see section 7.5 for the structure of this file); \$NID the identifier for this subgrid-mapping dataset within the file build by OASIS based on all the different SUBGRID analyses in the present coupling; \$NV is the maximum number of target grid points use in the subgrid-mapping; \$SUBTYPE = SOLAR is the type of subgrid interpolation; \$CCOARSE is the auxiliary field name on the coarse grid (corresponding to  $\alpha$ ) and \$CFINE is the auxiliary field name on fine grid (corresponding to  $\alpha_i$ ). These two fields needs to be exchanged between their original model and OASIS3 main process, at least as AUXILARY fields. This analysis is performed from the coarse grid with a grid-mapping type of interpolation based on the \$CFILE file.

2. If the the SUBGRID operation is performed on a nonsolar flux, the 8-argument input line is:

```
SUBGRID operation with $SUBTYPE=NONSOLAR
 $CFILE $NUMLU $NID $NV $SUBTYPE $CCOARSE $CFINE $CDQDT
```

\$NV are as for a solar subgrid interpolation; \$SUBTYPE = NONSOLAR; \$CCOARSE is the auxiliary field name on the coarse grid (corresponding to  $T$ ) and \$CFINE is the auxiliary field name on fine grid (corresponding to  $T_i$ ); the additional argument \$CDQDT is the coupling ratio on the coarse grid (corresponding to  $\frac{\partial F}{\partial T}$ ) These three fields need to be exchanged between their original model and OASIS3 main process as AUXILARY fields. This operation is performed from the coarse grid with a grid-mapping type of interpolation based on the \$CFILE file.

- **BLASNEW:**

BLASNEW (routine `/prism/src/mod/oasis3/src/blasnew.f`) performs a linear combination of the current coupling field with any other fields after the interpolation. These can be other coupling fields or constant fields.

This analysis requires the same input line as BLASOLD.

- **MASKP:**

A new analysis MASKP can be used to mask the fields after interpolation. MASKP has the same generic input line as MASK.

## 6.6 The post-processing

The following analyses are available in the post-processing part of OASIS3, controlled by `/prism/src/mod/oasis3/src`

- **REVERSE:**

REVERSE (routine `/prism/src/mod/oasis3/src/reverse.f`) reorders a field.

This analysis requires the same input line as INVERT, with `$CORLON` and `$CORLAT` being now the resulting orientation. REVERSE does not work for U and D grids (see annexe A).

- **CHECKOUT:**

CHECKOUT (routine `/prism/src/mod/oasis3/src/chkfld.f`) calculates the mean and extremum values of an output field and prints them to the coupler output *cplout*.

The generic input line is as for CHECKIN.

- **GLORED** (not recommended as coupling fields can be directly interpolated to a target Reduced grid, if needed):

GLORED performs a linear interpolation of field from a full Gaussian grid to a Reduced grid. When present, GLORED must be the last analysis performed.

Before doing the interpolation, non-masked values are automatically extrapolated to masked points with EXTRAP/NINENN method (see above); to do so, the masked grid points are first replaced with a predefined value. The required global grid mask must be present in data file `masks` or `masks.nc` (see section 7.2).

The generic input line is as follows:

```
GLORED operation
$NNBRLAT $NV $NIO $NID
```

is as for REDGLO (see REDGLO description above). The next 3 parameters refer to the EXTRAP/NINENN extrapolation (see EXTRAP/NINENN description above). The value assigned to all land points before interpolation is given by `amskred` in `/prism/src/mod/oasis3/src/blkdata.f`; as for the `$VALMASK` in MASK analysis, it has to be chosen well outside the range of your field values but not too large to avoid any representation problem.

## Chapter 7

# OASIS3 auxiliary data files

OASIS3 needs auxiliary data files describing coupling and I/O field names and units, defining the grids of the models being coupled, containing the field coupling restart values or input data values, as well as a number of other auxiliary data files used in specific transformations. For coupled models distributed in the PRISM Standard Running Environment (SCE), all those files are either automatically provided or generated.

### 7.1 Field names and units

The text file `cf_name_table.txt`, that can be found in directory `prism/util/running/adjunct_files/oasis3` directory, contains a list of CF standard names and associated units identified with an index. The appropriate index has to be given by the user for each coupling or I/O field as the third entry on the field first line (see 5.3). This information will be used by OASIS3 for its log messages to *cplout* file and by the PSMILe to produce CF compliant NetCDF files.

### 7.2 Grid data files

The grids of the models being coupled can be given by the user or directly by the model through PSMILe specific calls (see section 4.2) in grid data files. These files can be all binary or all NetCDF. In `/prism/data/toyclim/input/toyclim_standard_standard_prism_2-2.tar.gz`, NetCDF examples can be found.

The arrays containing the grid information are dimensioned  $(nx, ny)$ , where  $nx$  and  $ny$  are the grid first and second dimension, except for Unstructured (U) and Reduced (D) grid, for which the arrays are dimensioned  $(nbr\_pts, 1)$ , where  $nbr\_pts$  is the total number of grid points.

1. *grids* or *grids.nc*: contains the component model grid longitudes, latitudes, and local angles (if any) in single or double precision REAL arrays (depending on OASIS3 compilation options). The array names must be composed of a prefix (4 characters), given by the user in the *namcouple* on the second line of each field (see section 5.3), and of a suffix (4 characters); this suffix is “.lon” or “.lat” for respectively the grid point longitudes or latitudes (see `/prism/src/mod/oasis3/src/mod_label.F90`.)

If the SCRIPR/CONSERV interpolation is used for a grid, the grid data file may contain longitudes and latitudes for model mesh corners as arrays dimensioned  $(nx, ny, 4)$  or  $(nbr\_pts, 1, 4)$  where 4 is the number of corners; in this case, it must necessarily be a NetCDF file (*grids.nc*). For Logically Rectangular LR grids, the grid corners will be automatically calculated approximately if they are not given in *grids.nc*. The names of the arrays must be composed of the grid prefix and the suffix “.clo” or “.cla” for respectively the grid corner longitudes or latitudes.

If vector fields are defined on a grid which has a local coordinate system not oriented in the usual zonal and meridional directions, the local angle of the grid coordinate system must be given in *grids.nc* file in an array which name must be composed of the grid prefix and the suffix “.ang”. The angle is defined as the angle between the first component and the zonal direction (which is also the angle between the second component and the meridional direction). In the grid file in */prism/data/toyclim/input/toyclim\_standard\_standard\_prism\_2-2.tar.gz*, the angles of the *torc* grid are given in array *torc.ang*. If one of the SCRIPR interpolations is requested for a vector field, OASIS3 automatically performs the rotation from the local coordinate system to the geographic spherical coordinate system for a source grid, or vice-versa for a target grid.

File *grids* or *grids.nc* must be present with at least the grid point longitudes and latitudes for all component model.

2. *masks* or *masks.nc*: contains the masks for all component model grids in INTEGER arrays (0 -not masked- or 1 -masked- for each grid point). The array names must be composed of the grid prefix and the suffix “.msk”. This file, *masks* or *masks.nc*, is mandatory.
3. *areas* or *areas.nc*: this file contains mesh surfaces for the component model grids in single or double precision REAL arrays (depending on OASIS3 compilation options). The array names must be composed of the grid prefix and the suffix “.srf”. The surfaces may be given in any units but they must be all the same (in INTERP/GAUSSIAN, it is assumed that the units are  $m^2$  but they are used for statistics calculations only.) This file *areas* or *areas.nc* is mandatory for CHECKIN, CHECKOUT or CONSERV, and used for statistic calculations in INTERP/GAUSSIAN; it is not required otherwise.
4. *maskr* or *maskr.nc*: this file contains Reduced (D) grid mask in INTEGER arrays dimensioned `array(nbr_pts)` where `nbr_pts` is the total number of the Reduced grid points (0 -not masked- or 1 -masked- for each grid point). This file is required only for grids to which the REDGLO or GLORED transformation is applied. As mentionned above, these transformations should not be used anymore as interpolations are now available for Reduced grids directly. If used, the mask array name must be “MSKRDxxx” where “xxx” is half the number of latitude circles of the reduced grid (032 for a T42 for example).

If the binary format is used, *grids*, *masks*, *areas*, and *maskr* must have the following structure. The array name is first written to the file to locate a data set corresponding to a given grid. The data set is then written sequentially after its name. Let us call “brick” the name and its associated data set. The order in which the bricks are written doesn’t matter. All the bricks are written in the grid data file in the following way:

```
...
WRITE(LU) array_name
WRITE(LU) auxildata
...
```

- LU is the associated unit,
- `array_name` is the name of the array (CHARACTER\*8),
- `auxildata` is the REAL or INTEGER array dimensioned `(nx, ny)` or `(nbr_pts, 1)` containing the grid data.

## 7.3 Coupling restart files

At the beginning of a coupled run, some coupling fields may have to be initially read from their coupling restart file (see section 4.8). If needed, these files are also automatically updated by the last `prism.put_proto` call of the run (see section 4.6.1) . To force the writing of the field in its cou-

pling restart file, one can use the routine `prism_put_restart_proto` (see section 4.6.3). The name of the coupling restart file is given by the 6th character string on the first configuring line for each field in the *namcouple* (see section 5.3). Coupling fields coming from different models cannot be in the same coupling restart files, but for each model, there can be an arbitrary number of fields written in one coupling restart file. Note that in the NONE techniques, output files with the same format are also created for writing the resulting field after transformation.

In the coupling restart files, the fields must be single or double precision REAL arrays (depending on PSMILe and OASIS3 compilation options) and, as the grid data files, must be dimensioned  $(nx, ny)$ , where  $nx$  and  $ny$  are the grid first and second dimension, except for fields given on Unstructured ('U') and Reduced ('D') grid, for which the arrays are dimensioned  $(nbr\_pts, 1)$ , where  $nbr\_pts$  is the total number of grid points. The shape and orientation of each restart field (and of the corresponding coupling fields exchanged during the simulation) must be coherent with the shape of its grid data arrays. The exceptions are for A, B, G, L, Z, or Y grids for which the field may be oriented from North to South and/or from East to West, in which case, INVERT transformation will have to be used - see section 6.3.

Both binary and NetCDF formats are supported; for NetCDF file the suffix `.nc` is not mandatory. If the coupling restart file for the first field is in NetCDF format, OASIS3 will assume that all coupling restart files (and output files for NONE communication techniques) are NetCDF<sup>1</sup>.

In the NetCDF restart files, the field arrays must have the source symbolic name indicated in the *namcouple* (see section 5.3).

In binary restart file, each field is written in the following way:

```
...
WRITE(LU) array_name
WRITE(LU) restartdata
...
```

- LU is the associated unit,
- array\_name is the source symbolic name of the field (CHARACTER\*8),
- restartdata is the restart field REAL array dimensioned  $(nx, ny)$  or  $(nbr\_pts, 1)$ <sup>2</sup>

## 7.4 Input data files

Fields with status INPUT in the *namcouple* will, at runtime, simply be read in from a NetCDF input file by the target model PSMILe below the `prism_get_proto` call, at appropriate times corresponding to the input period indicated by the user in the *namcouple*.

The name of the file must be the one given on the field first configuring line in the *namcouple* (see section 5.3.3). There must be one input file per INPUT field, containing a time sequence of the field in a single or double precision REAL array (depending on PSMILe compilation options), named with the field symbolic name in the *namcouple* and dimensioned  $(nx, ny, time)$  or  $(nbr\_pts, 1, time)$ . The time variable has to be an array `time(time)` expressed in "seconds since beginning of run". The "time" dimension has to be the unlimited dimension. For a practical example, see the file `SOALBEDO.nc` in `/prism/data/toyclim/input/toyclim_standard_standard.prism.2-2.tar.gz`.

<sup>1</sup>Note that even if the grid auxiliary data files are in NetCDF format, the restart coupling files may be in binary format, or vice-versa.

<sup>2</sup>If REDGLO is the first transformation applied on a Reduced grid field, the Reduced field must be given as an array `restartdata(nx*ny)` where  $nx$  and  $ny$  are the global Gaussian grid dimensions and the Reduced field is completed by trailing zeros.

## 7.5 Transformation auxiliary data files

Many transformation need auxiliary data files, such as the grid-mapping files used for an interpolation. Some of them are created automatically by OASIS3, others have to be generated by the user before starting the coupled run.

### 7.5.1 Auxiliary data files for EXTRAP/NINENN, EXTRAP/WEIGHT, INTERP/SURFMESH, INTERP/GAUSSIAN, MOZAIC, and SUBGRID

The auxiliary data files containing the weights and addresses used in these transformations have a similar structure; their names are given in Table 7.1.

| File name       | Description                                                             |
|-----------------|-------------------------------------------------------------------------|
| <i>nweights</i> | weights, addresses and iteration number for EXTRAP/NINENN interpolation |
| any name        | weights and addresses for EXTRAP/WEIGHT extrapolation                   |
| <i>mweights</i> | weights and addresses for INTERP/SURFMESH interpolation                 |
| <i>gweights</i> | weights and addresses for INTERP/GAUSSIAN interpolation                 |
| any name        | weights and addresses for MOZAIC interpolation                          |
| any name        | weights and addresses for SUBGRID interpolation                         |

**Table 7.1:** Analysis auxiliary data files

The files *nweights*, *mweights* and *gweights* can be created by OASIS3 if their corresponding  $\$NIO = 1$  (see EXTRAP/NINENN, INTERP/SURFMESH, INTERP/GAUSSIAN in sections 6.3 and 6.4).

The name of the (sub)grid-mapping files for MOZAIC, EXTRAP/WEIGHT and SUBGRID analyses can be chosen by the user and have to be indicated in the *namcouple* (see respectively sections 6.3 and 6.4 and 6.5). These files have to be generated by the user before starting the coupled run.

The structure of these files is as follows:

```

...
CHARACTER*8 claddress,clweight
INTEGER iaddress(jpnb,jpo)
REAL weight(jpnb,jpo)
OPEN(unit=90, file='at31topa', form='unformatted')
WRITE(clweight,('(WEIGHTS',I1)) knumb
WRITE(claddress,('(ADRESSE',I1)) knumb
WRITE (90) claddress
WRITE (90) iaddress
WRITE (90) clweight
WRITE (90) weight

```

where

- *jpnb* is the maximum number of neighbors used in the transformation ( $\$NVOISIN$  in the *namcouple*)
- *jpo* is the total dimension of the target grid
- *at31topa* is the name of the grid-mapping data file ( $\$CFIL$  in *namcouple*)
- *knumb* is the identifier of the data set ( $\$NID$  in *namcouple*)
- *claddress* is the locator of the address dataset
- *clweight* is the locator of the weight dataset
- *iaddress* (*i*, *j*) is the address on the source grid of the  $i^e$  neighbor used for the mapping of the  $j^e$  target grid point. The address is the index of a grid point within the total number of grid points.



- `weight(i, j)` is the weight affected to the  $i^e$  neighbor used for the transformation of the  $j^e$  target grid point

For file *nweights*, there is an additional brick composed of a CHARACTER\*8 variable (formed by the characters INCREME and by the data set identifier) and of an INTEGER array(N) which is the iteration number within EXTRAP/NINENN at which the extrapolation of the  $n^e$  grid point is effectively performed.

### 7.5.2 Auxiliary data files for FILLING

For the FILLING analysis, the global data set used can be either interannual monthly, climatological monthly or yearly (see 6.4). The name of the global data file can be chosen by the user and has to be indicated in the *namcouple* have to be given to OASIS through the input file *namcouple*. In case of monthly data, the file must be written in the following way:

```

...
REAL field_january_year_01(jpi, jpj)
...
WRITE(NLU_fil) field_january_year_01
WRITE(NLU_fil) field_february_year_01
WRITE(NLU_fil) field_march_year_01
etc...
WRITE(NLU_fil) field_december_year_01
C
C if climatology, one stops here
C
 WRITE(NLU_fil) field_january_year_02
 etc...
```

where

- `field_...` is the global dataset
- `jpi` and `jpj` are the dimensions of the grid on which FILLING is performed
- `NLU_fil` is the logical unit associated to the global data file and is defined in the input file *namcouple*

Note that the first month needs not to be a january. This is the only file within OASIS in which the fields are not read using a locator.

### 7.5.3 Auxiliary data files for SCRIPR

The NetCDF files containing the weights and addresses for the SCRIPR remappings (see section 6.4) are automatically generated at runtime by OASIS3. Their structure is described in detail in section 2.2.3 of the SCRIP documentation available in `prism/src/mod/oasis3/doc/SCRIPusers.pdf`.

## Chapter 8

# Compiling and running with OASIS3

OASIS3 and its TOYCLIM coupled model has been successfully compiled and run on Fujitsu VPP5000, NEC SX5 and SX6, SGI IRIX64, SGI Origin 3800, Linux Opteron, IBM Power4, and Cray X1.

### 8.1 Compiling OASIS3 and the TOYCLIM coupled model

OASIS3 and the TOYCLIM coupled model use the PRISM standard directory structure (see also (4)) and Standard Compiling Environment (see also (5)). To compile OASIS3 and toyatm, toyoce and toyche component models, one should go through the following steps:

1. Go in the directory `prism/util/compile/frames`.
2. Create the include files for your platform if they do not already exist in directory `prism/util/compile/frames/include_<node>` where `<node>` is the name of the platform.
3. Generate a compile script for the libraries using the script `Create_COMP_libs.frm`:

`Create_COMP_libs.frm " " " " " "`

The first parameter can be either `" "` or `" - "` to direct the standard output to a file or the screen.

The second parameter can be either `" "`, `" - "` or `" + "` to direct the standard error to a file, the screen or the standard output.

If the compile scripts shall be created for another platform than the one where the `Create_COMP_libs.frm` script is launched, the third parameter has to contain the abbreviated node name "node".

The compile script for the libraries `COMP_libs.<node>` should then be created in the directory `prism/util`.

4. Generate a compile script for OASIS3 and for each of the component models using the script Cre-

ate\_COMP\_models.frm:

```
Create_COMP_models.frm oasis3 "mp" "" "" ""
Create_COMP_models.frm toyoce "mp" "" "" "" "ID" "toyatm toyoce
toyche"
Create_COMP_models.frm toyatm "mp" "" "" "" "ID" "toyatm toyoce
toyche"
Create_COMP_models.frm toyche "mp" "" "" "" "ID" "toyatm toyoce
toyche"
```

The second parameter “mp” specifies the message passing used, which determines how the models are launched (see also section 4.1). If the default ‘MPI2’ is chosen, the string has to be empty (specification of MPI2 results in an error); otherwise, MPI1 has to be given, or NONE for the interpolator only mode -see section 6.1. The OASIS3 executable will have the string MPI1 or MPI2 appended to its name. The 3 toy models can also be compiled with either the MPI1 option or the default MPI2 option (empty string).

The third parameter can be either “ ” or “ - ” to direct the standard output to a file or the screen.

The fourth parameter can be either “ ”, “ - ” or “ + ” to direct the standard error to a file, the screen or the standard output.

If the compile scripts shall be created for another platform than the one where the Create\_COMP\_models.frm script is launched, the fifth parameter has to contain the abbreviated node name “node”.

The sixth parameter “ID” is version acronym for differentiation of executables (not relevant for OASIS3 and TOYCLIM toy models).

Finally the last parameter gives the name of all the component models in the coupled constellation. This list is not relevant for OASIS3, but it has to be given for the toy models. The specified partner models are checked against allowed partners and no default is set.

The scripts to compile OASIS3 and the 3 toy coupled models, COMP\_oasis3\_<mp>.<node> COMP\_toyatm\_<ID>.<node>, COMP\_toyoce\_<ID>.<node>, COMP\_toyche\_<ID>.<node> should then be created, respectively in directories prism/src/mod/oasis3, /toyatm, /toyoce, /toyche.

5. The compilation scripts created can now be used to compile OASIS3 and the 3 toy models. All four compile scripts have then to be launched explicitly by the user in their respective directory.

```
COMP_oasis3_<mp>.<node>
COMP_toyatm_<ID>.<node>
COMP_toyoce_<ID>.<node>
COMP_toyche_<ID>.<node>
```

The scripts compile the models with the MPI library specified during their generation. The script that triggers the update of the libraries, COMP\_libs.<node>, is automatically called by the model compilation scripts for the libraries they need. Libraries needed by OASIS3 are anaism, anaism, scrip, fscint, and clim for MPI1 and MPI2 mode (clim is not compiled in NONE mode). The toy models need psmile and mpp\_io.

6. The result should be executables oasis3.<mp>.x, toyatm.<mp>.x, toyoce.<mp>.x, and toyche.<mp>.x in the \$BLDROOT/bin directory defined by the compile scripts, where <mp> is either MPI1 or MPI2.

## 8.2 Configuring the TOYCLIM coupled model using OASIS3

The TOYCLIM coupled model performs a coupling between an “empty” ocean model, *toyoce*, an “empty” atmospheric model, *toyatm*, and an “empty” atmospheric chemistry model, *toyche*. There is no real physics or dynamics within the models. However, the coupling fields have a realistic size, the operations performed within OASIS3 on the coupling fields are realistic, and the coupling using the PRISM System model interface (PSMILe) is also realistic. The TOYCLIM atmosphere and chemistry models have the same grid and the same parallel partitioning on 3 processes. There is no need of interpolation and the coupling fields are directly exchanged between these two models without going through OASIS3 interpolation process. More details on the TOYCLIM coupled model can be found in (6).

The TOYCLIM coupled model uses PRISM standard running environment (SRE). To run it, one has to go through the following steps:

1. Go to the directory `prism/util/running/frames`
2. Create the include files for your platform if they do not already exist in directory `prism/util/running/frames/include_<node>` where `<node>` is the name of the platform.
3. Run the script `Create_TASKS.frm` to generate a setup file for your TOYCLIM experiment:

**Create\_TASKS.frm toyclim <expid>**

where `<expid>` is your experiment name.

4. To change the configuration of your experiment, modify the values of the configurable entries in the setup file `prism/util/running/frames/setup/setup_toyclim_<expid>`, which contains default values for these entries. Some of these configurable entries directly enter the OASIS3 configuration file *namcouple*, other affect the running script only<sup>1</sup>. The *namcouple* file is created from the *namcouple* base file (see *namcouple\_toyclim* in `prism/util/running/adjunct_files/oasis3`) by replacing the configurable entries (which begin with “#”) by the value defined in the setup file. The *namcouple* will be read by OASIS3 at runtime. The variables that can be defined in the set-up file and correspond to configurable *namcouple* entries are the following:
  - (a) *jobname*: Experiment identifier; it is composed of three digits; (*#Jobname*).
  - (b) *nlogprt*: Integer controlling the amount of information written to the OASIS output file *cplout*. 0: minimum output, 1: medium output, 2: maximum output; (*#Nlogprt*).
  - (c) *extrapwr*: Flag to provoke the calculation of weights and addresses for nearest neighbour extrapolation (EXTRAP/NINENN) within OASIS3 (1) or to read them from file (0); (*#Extrapwr*).
  - (d) *stat\_fieldxx*, where *xx* is the number of the field in the *namcouple*: The status of the *xx* coupling/IO field can be either ‘EXPOUT’ or ‘EXPORTED’, except for *Field<sub>3</sub>* for which it is ‘INPUT’, for *Field<sub>5</sub>* for which it is ‘OUTPUT’ and for *Field<sub>10</sub>* and *Field<sub>11</sub>* for which it is either ‘IGNOUT’ or ‘IGNORED’ (see section 5.3); (*#Stat\_fieldxx*).
  - (e) *dtFxx*, where *xx* is the number of the field in the *namcouple*: The coupling or I/O period of the *xx* coupling/IO field, which must be a multiple of 14400, except for *Field<sub>3</sub>* for which it must be a multiple of 43200, and for *Field<sub>5</sub>*, *Field<sub>10</sub>* and *Field<sub>11</sub>* for which it must be a multiple of 3600; (*#Dtxx*).
  - (f) *iniyear*, *inimonth* and *iniday*: the initial date of the experiment, respectively as YYYY, MM and DD (*#Inidate*).
  - (g) *message\_passing*: Message passing method, either MPI2 or MPI1 (for more details, see section 4.1); (in *#Channel*)

---

<sup>1</sup>Additional *namcouple* entries are also configurable by editing directly the *namcouple* base file. Refer to chapter 5 for more details.

- (h) *bSEND*: either 'yes' or 'no', indicates whether the buffered *MPI\_BSEND* or the standard blocking send *MPI\_SEND* will be used to send the coupling fields (for more details, see section 5.2) (in *#Channel*)

The variables that can be additionally defined in the setup file but do not correspond to any configurable *namcouple* entries are the following:

- (a) *ncplvers*: the *namcouple* version. Put " " to use the *namcouple* base file completed with the values defined in the setup file. To use another *namcouple*, a particular value has to be given to *ncplvers*, and a *namcouple* named *namcouple\_toyclim\_<ncplvers>* has to be available in *prism/util/running/adjunct\_files/oasis3*.
  - (b) *gridswr*: either '0' if you want the models to use the grid description files if they exist, or '1' if you want the models to unconditionally (re)generate those grid description files (for more details, see section 4.2).
5. Type 'Create\_TASKS.frm toyclim <expid>' a second time. The script will check the parameters you specified in *setup\_toyclim\_<expid>*. If a parameter is not supported or a combination of parameters does not make sense *Create\_TASKS.frm* writes an error message and stops.
  6. Correct the experimental setup file if necessary and run *Create\_TASKS.frm* again until the setup check is passed successfully.

Once the setup is done, all appropriate files and the script to start the experiment are available in the directory *<home>/<expid>*, where *<home>* and *<expid>* are defined in the setup file.

### 8.3 Running the TOYCLIM coupled model using OASIS3

After the setup and configuration phase, the experiment is ready to be started with the running script *RUN\_toyclim\_<expid>* in directory *<work>/<expid>/scripts*, where *<work>* and *<expid>* are as defined in the setup file *setup\_toyclim\_<expid>*.

To run a TOYCLIM experiment, one has to go through the following steps:

1. Login on the compute server (if different from the compile server).
2. Change to the directory *<work>/<expid>/scripts*.
3. Submit the runscript *RUN\_toyclim\_<expid>*.

Running TOYCLIM with the default parameters will result in a 30-day experiment executed as five 6-day runs. The final results obtained the directory *<work>/<expid>/work* should match the ones in *prism/data/toyclim/outdata*. Intermediate results are also saved in different sub-directories :

- the OASIS3 log files of each run in *<data>/<expid>/log* or *<archive>/<expid>/log*
- the output netCDF files containing the EXPOUT fields in *<data>/<expid>/outdata/oasis3* or *<archive>/<expid>/outdata/oasis3*
- the coupling restart files in *<data>/<expid>/restart* or *<archive>/<expid>/restart*.

where *<data>* and *<archive>* are defined in the runscript *RUN\_toyclim\_<expid>*.

### 8.4 Running the TOYCLIM coupled model manually

If you want to run the TOYCLIM manually, you need to copy the following files in your working directory:

- OASIS3, *toyatm*, *toyoce*, *toyche* executables
- OASIS3 grid, restart, and auxiliary files: *grids.nc*, *masks.nc*, *areas.nc*, *SOALBEDO.nc*, *flda1.nc*, *flda2.nc*, *flda3.nc*, *flda4.nc*, *fldo1.nc*, *at31topa*, *runoff31*, which are in *prism/data/toyclim/input\_toyclim\_standard\_standard\_prism2-2.tar.gz*

- OASIS3 adjunct files ‘cf\_name\_table.txt’ and ‘namcouple’ which can be found under names ‘cf\_name\_table.txt’ and ‘namcouple\_toyclim\_use’ in `prism/util/running/adjunct_files/oasis3`

Then you need to start the coupled model, setting up MPI parameters properly. For examples, refer to files `config_site_<node>.h` and `launching_toyclim_<node>.h` in `prism/util/running/frames/include_<node>` (where <node> is the name of the platform).

## 8.5 Running OASIS3 in interpolator-only mode

To run OASIS3 in interpolator-only mode, one has to go through the following steps (the following specific files can be retrieved from CERFACS CVS only):

- Compile OASIS3 following the procedure described in section 8.1 specifying NONE as <mp>.
- Compile the programs that will calculate the interpolation error fields, i.e. `gen_error.f90` and `gen_error_vector.f90` in directory `prism/util/running/testinterp/error`.
- Execute the running script `prism/util/running/testinterp/scrun_testinterp`.
- The results obtained after running the TOYCLIM with the defaults parameters should match the ones in `prism/data/testinterp/outdata`.

For more details, please read the `prism/util/running/testinterp/README_testinterp`.

# Appendix A

## The grid types for the transformations

As described in section 6, the different transformations in OASIS3 support different types of grids. The characteristics of these grids are detailed here.

### 1. Grids supported for the INTERP interpolations (see section 6.4)

- 'A' grid: this is a regular Lat-Lon grid covering either the whole globe or an hemisphere, going from South to North and from West to East. There is no grid point at the pole and at the equator, and the first latitude has an offset of 0.5 grid interval. The first longitude is  $0^\circ$  (the Greenwich meridian) and is not repeated at the end of the grid ( $\$C_{PER} = P$  and  $\$N_{PER} = 0$ ). The latitudinal grid length is  $180/NJ$  for a global grid,  $90/NJ$  otherwise. The longitudinal grid length is  $360/NI$ .
- 'B' grid: this is a regular Lat-Lon grid covering either an hemisphere or the whole globe, going from South to North and from West to East. There is a grid point at the pole and at the equator (if the grid is hemispheric or global with  $NJ$  odd). The first longitude is  $0^\circ$  (the Greenwich meridian), and is repeated at the end of the grid ( $\$C_{PER} = P$  and  $\$N_{PER} = 1$ ). The latitudinal grid length is  $180/(NJ-1)$  for a global grid,  $90/(NJ-1)$  otherwise. The longitudinal grid length is  $360/(NI-1)$ .
- 'G' grid: this is a irregular Lat-Lon Gaussian grid covering either an hemisphere or the whole globe, going from South to North and from West to East. This grid is used in spectral models. It is very much alike the A grid, except that the latitudes are not equidistant. There is no grid point at the pole and at the equator. The first longitude is  $0^\circ$  (the Greenwich meridian) and is not repeated at the end of the grid ( $\$C_{PER} = P$  and  $\$N_{PER} = 0$ ). The longitudinal grid length is  $360/NI$ .
- 'L' grid: this type covers regular Lat-Lon grids in general, going from South to North and from West to East.. The grid can be described by the latitude and the longitude of the southwest corner of the grid, and by the latitudinal and longitudinal grid mesh sizes in degrees.
- 'Z' grid: this is a Lat-Lon grid with non-constant latitudinal and longitudinal grid mesh sizes, going from South to North and from West to East. The deformation of the mesh can be described with the help of 1-dimensional positional records in each direction. This grid is periodical ( $\$C_{PER} = P$ ) with  $\$N_{PER}$  overlapping grid points.
- 'Y' grid: this grid is like 'Z' grid except that it is regional ( $\$C_{PER} = R$  and  $\$N_{PER} = 0$ ).

### 2. Grids supported for the SCRIPR interpolations

- 'LR' grid: The longitudes and the latitudes of 2D Logically-Rectangular (LR) grid points can be described by two arrays `longitude(i,j)` and `latitude(i,j)`, where  $i$  and  $j$  are respectively the first and second index dimensions. Stretched or/and rotated grids are LR grids. Note that A, B, G, L, Y, or Z grids are all particular cases of LR grids.

- ‘U’ grid: Unstructured (U) grids do not have any particular structure. The longitudes and the latitudes of 2D Unstructured grid points must be described by two arrays `longitude(nbr_pts,1)` and `latitude(nbr_pts,1)`, where `nbr_pts` is the total grid size.
- ‘D’ grid The Reduced (D) grid is composed of a certain number of latitude circles, each one being divided into a varying number of longitudinal segments. In OASIS3, the grid data (longitudes, latitudes, etc.) must be described by arrays dimensioned `(nbr_pts,1)`, where `nbr_pts` is the total number of grid points. There is no overlap of the grid, and no grid point at the equator nor at the poles. There are grid points on the Greenwich meridian.



## Appendix B

# Changes between versions

Here is a list of changes between the different official OASIS3 versions.

### B.1 Changes between `prism_2_4` and `oasis3_prism_2_3`

The changes between versions tagged `prism_2_4` and `oasis3_prism_2_3` delivered in July 2004 are the following:

- Update of compiling and running environments with version `prism_2-4` of PRISM Standard Compiling Environment (SCE) and PRISM Standard Running Environment (SRE), which among other improvements include the environments to compile and run on the CRAY X1 (see the directories with `<node>=baltic1`), thanks to Charles Henriet from CRAY France, and on a Linux station from Recherche en Prévision Numérique (Environnement Canada, Dorval, Canada) (see the directories with `<node>=armc28`).
- `prism/src/mod/oasis3/src/iniiof.F`: the opening of the coupling restart files is done only if the corresponding field has a lag greater than 0; note that this implies that all fields in mode NONE must now have a lag greater than 0 (e.g. `LAG=+1`) (thanks to Veronika Gayler from M&D).
- `prism/src/lib/psmile/src/prismdef_var_proto.F`: contrary to what was previously described in the documentation, `PRISM_Double` is not supported as 7<sup>th</sup> argument to describe the field type; `PRISM_Real` must be given for single or double precision real arrays.
- `prism/src/mod/oasis3/src/inipar.F90`: For upward compatibility of SCRIPR interpolation, “VECTOR” is still accepted in the `namcouple` as the field type and leads to the same behaviour as before (i.e. each vector component is treated as an independent scalar field). To have a real vector treatment, one has to indicate “VECTOR\_I” or “VECTOR\_J” (see section 6.4).
- Bug corrections in:
  - `prism/src/lib/scrip/src/scriprmp_vector.F90`: In some cases, some local variables were not deallocated and variable `dimid` was declared twice.
  - `prism/src/lib/psmile/src/mod_psmile_io.F90`: correct allocation of array hosting the longitudes (thanks to Reiner Vogelsang from SGI Germany).
  - `prism/src/lib/psmile/src/write_file.F90`: to remove a deadlock on some architecture (thanks to Luis Kornblueh from MPI).
  - `prism/src/lib/psmile/src/prism_enddef_proto.F`: the error handler is now explicitly set to `MPI_ERRORS_RETURN` before the call to `MPI_Buffer_Detach` to avoid abort on some architecture when the component model is not previously attached to any buffer (thanks to Luis Kornblueh from MPI).
  - `prism/src/lib/scrip/src/remap_conserv.f` (thanks to Veronika Gayler from M&D).

- `prism/src/mod/oasis3/src/inicmc.F`
- `prism/src/lib/scrip/src/remap_distwgt.f`

## B.2 Changes between `oasis3_prism_2_3` and `oasis3_prism_2_2`

The changes between versions tagged `oasis3_prism_2_3` delivered in July 2004 and `oasis3_prism_2_2` delivered in June 2004 are the following:

- Bug correction of the previous bug fix regarding ordering of grid and data information contained in I/O files when INVERT or REVERSE transformations are used: the re-ordering now occurs only for source field if INVERT is used, and only for target field if REVERSE is used.
- LGPL license: OASIS3 is now officially released under a Lesser GNU General Public License (LGPL) as published by the Free Software Foundation (see `prism/src/mod/oasis3/COPYRIGHT` and `prism/src/mod/oasis3/src/couple.f`)
- Upgrade of compiling and running environments: The compiling and running environments have been upgraded to the PRISM Standard Compiling and Running Environment version dated August 5th 2004, that should be very close to “prism\_2-3”.
- Treatment of vector fields: The interpolation algorithms using the SCRIP library now support vector fields, including automatic rotation from local to geographic coordinate system, projection in Cartesian coordinate system and interpolation of 3 Cartesian components, and support of vector components given on different grids. New routines have been added in `prism/src/lib/scrip/src:scriprmp_vector.F90` and `rotations.F90`. For more detail, see SCRIPR in section 6.4.
- All include of `mpif.h` are now written ‘`#include <mpif.h>`’.
- The output format of CHECKIN and CHECKOUT results is now E22.7

## B.3 Changes between `oasis3_prism_2_2` and `oasis3_prism_2_1`

The changes between versions tagged `oasis3_prism_2_2` delivered in June 2004 and `oasis3_prism_2_1` delivered to PRISM in April 2004 are the following:

- Bug corrections
  - `INTERP/GAUSSIAN` and `SCRIPR/GAUSWGT` transformations work for ‘U’ grids.
  - The grid and data information contained in I/O files output by the PSMILe library have now a coherent ordering even if INVERT or REVERSE transformations are used.
- OASIS3 and the TOYCLIM coupled model are ported to IBM Power4 and Linux Opteron, which are now included in the Standard Compiling and Running Environments (SCE and SRE).
- SIPC technique communication is re-validated.
- `Clim_MaxSegments = 338` in `prism/src/lib/clim/src/mod_clim.F90` and in `prism/src/lib/psmil`: 338 is presently the largest value needed by a PRISM model.
- `MPI_BSend`: below the call to `prism_enddef_proto`, the PSMILe tests whether or not the model has already attached to an MPI buffer. If it is the case, the PSMILe detaches from the buffer, adds the size of the pre-attached buffer to the size needed for the coupling exchanges, and reattaches to an MPI buffer. The model own call to `MPI_Buffer_Attach` must therefore be done before the call to `prism_enddef_proto`. Furthermore, the model is not allowed to call `MPI_BSend` after the call to `prism_terminate_proto`, as the PSMILe definitively detaches from the MPI buffer in this routine. See the example in the toyatm model in `prism/src/mod/toyatm/src`.

## B.4 Changes between oasis3\_prism\_2\_1 and oasis3\_prism\_1\_2

The changes between versions tagged oasis3\_prism\_1\_2 delivered in September 2003 and oasis3\_prism\_2\_1 delivered to PRISM in April 2004 are the following:

- Bug corrections
  - Thanks to Eric Maisonnave, a bug was found and corrected in `/prism/src/lib/scrip/src/scriprmp.f`: “sou\_mask” and “tgt\_mask” were not properly initialised if weights and addresses were not calculated but read from file.
  - Some deallocation were missing in `prism_terminate_proto.F` (“ig\_def\_part”, “ig\_length\_part”, “cg\_ignout\_field”).
  - Thanks to Arnaud Caubel, a bug was found and corrected in `/prism/src/lib/psmile/src/write_file.F90`. In case of parallel communication between a model and OASIS3 main process, the binary coupling restart files were not written properly (NetCDF coupling restart files are OK).

- Routines renamed

The routines `preproc.f`, `extrap.f`, `iniiof.f` in `prism/src/mod/oasis3/src` were renamed to `preproc.F`, `extrap.F`, `iniiof.F`, as a CPP key ‘key\_openmp’ was added. Please note that this key, allowing openMP parallelisation, is not fully tested yet.

- Modifications in the `namcouple`

- The third entry on the field first line now corresponds to an index in the new auxiliary file `cf_name_table.txt` (see sections 5.3 and 7.1).
- For IGNORED, IGNOUT and OUTPUT fields, the source and target grid locator prefixes must now be given on the field second line (see section 5.3.2)

- A new auxiliary file `cf_name_table.txt`

For each field, the CF standard name used in the OASIS3 log file, `cplout`, is now defined in an additional auxiliary file `cf_name_table.txt` not in `inipar.F` anymore. This auxiliary file must be copied to the working directory at the beginning of the run. The user may edit and modify this file at her own risk. In `cf_name_table.txt`, an index is given for each field standard name and associated units. The appropriate index has to be indicated for each field in the `namcouple` (third entry on the field first line, see section 5.3).

This standard name and the associated units are also used to define the field attributes “long\_name” and “units” in the NetCDF output files written by the PSMILe for fields with status EXPOUT, IGNOUT and OUTPUT.

For more details on this auxiliary file, see section 7.1.

- Many timesteps for mode NONE

In mode NONE, OASIS3 can now interpolate at once all time occurrences of a field contained in an input NetCDF file. The time variable in the input file is recognized by its attribute “units”. The acceptable units for time are listed in the `udunits.dat` file (3). This follows the CF convention.

The keyword \$RUNTIME in the `namcouple` has to be the number of time occurrences of the field to interpolate from the input file. The “coupling” period of the field (4th entry on the field first line) must be always “1”. Note that if \$RUNTIME is smaller than the total number of time occurrences in the input file, the first \$RUNTIME occurrences will be interpolated.

For more details, see section 6.1.

- Model grid data file writing

The grid data files `grids.nc`, `masks.nc` and `areas.nc` can now be written directly at run time by the component models, if they call the new routines `prism_start_grids_writing`, `prism_write_grid`, `prism_write_corner`, `prism_write_mask`, `prism_write_area`, `prism_terminate_grids_writing`.

The writing of those grid files by the models is driven by the coupler. It first checks whether the binary file *grids* or the netCDF file *grids.nc* exists (in that case, it is assumed that *areas* or *areas.nc* and *masks* or *masks.nc* files exist too) or if writing is needed. If *grids* or *grids.nc* exists, it must contain all grid information from all models; if it does not exist, each model must write its grid informations in the grid data files.

See section 4.2 for more details.

- Output of CF compliant files

The NetCDF output files written by the PSMILe for fields with status `EXPOUT`, `IGNOUT` and `OUTPUT` are now fully CF compliant.

In the NetCDF file, the field attributes “long\_name” and “units” are the ones corresponding to the field index in *cf\_name\_table.txt* (see above and section 7.1). The field index must be given by the user as the third entry on the field first line in the namcouple.

Also, the latitudes and the longitudes of the fields are now automatically read from the grid auxiliary data file *grids.nc* and written to the output files. If the latitudes and the longitudes of the mesh corners are present in *grids.nc*, they are also written to the output files as associated “bounds” variable. This works whether the *grids.nc* is given initially by the user or written at run time by the component models (see above). However, this does not work if the user gives the grid definition in a binary file *grids*.

- Removal of pre-compiling key “key\_BSend”

The pre\_compiling key “key\_BSend” has been removed. The default has changed: by default, the buffered `MPI_BSend` is used, unless `NOBSEND` is specified in the namcouple after `MPI1` or `MPI2`, in which case the standard blocking send `MPI_Send` is used to send the coupling fields.

# Appendix C

## Copyright statements

### C.1 OASIS3 copyright statement

Copyright 2004 Centre Européen de Recherche et Formation Avancée en Calcul Scientifique (CERFACS). This software and ancillary information called OASIS3 is free software. CERFACS has rights to use, reproduce, and distribute OASIS3. The public may copy, distribute, use, prepare derivative works and publicly display OASIS3 under the terms of the Lesser GNU General Public License (LGPL) as published by the Free Software Foundation, provided that this notice and any statement of authorship are reproduced on all copies. If OASIS3 is modified to produce derivative works, such modified software should be clearly marked, so as not to confuse it with the OASIS3 version available from CERFACS.

The developers of the OASIS3 software attempt to build a modular and user-friendly coupler for to the climate modelling community. The software is provided for free; in return, the user assumes full responsibility for use of the software. The OASIS3 software comes without any warranties (implied or expressed) and is not guaranteed to work for you or on your computer. Specifically, CERFACS and the various individuals involved in development and maintenance of the OASIS3 software are not responsible for any damage that may result from correct or incorrect use of this software.

If you feel that your research has benefited from the use of the OASIS3 software, we will greatly appreciate your reference to the following report:

Valcke, S., A. Caubel, R. Vogelsang, D. Declat, 2004. OASIS3 User Guide (oasis3\_prism\_2-4). PRISM Report Series No 2, 5th Ed., 60 pp.

### C.2 The SCRIP 1.4 copyright statement

The SCRIP 1.4 copyright statement reads as follows:

“Copyright 1997, 1998 the Regents of the University of California. This software and ancillary information (herein called SOFTWARE) called SCRIP is made available under the terms described here. The SOFTWARE has been approved for release with associated LA-CC Number 98-45. Unless otherwise indicated, this SOFTWARE has been authored by an employee or employees of the University of California, operator of Los Alamos National Laboratory under Contract No. W-7405-ENG-36 with the United States Department of Energy. The United States Government has rights to use, reproduce, and distribute this SOFTWARE. The public may copy, distribute, prepare derivative works and publicly display this SOFTWARE without charge, provided that this Notice and any statement of authorship are reproduced on all copies. Neither the Government nor the University makes any warranty, express or implied, or assumes any liability or responsibility for the use of this SOFTWARE. If SOFTWARE is modified to produce derivative works, such modified SOFTWARE should be clearly marked, so as not to confuse it with the version available from Los Alamos National Laboratory.”

## Appendix D

# The coupled models realized with OASIS

Here is a list of (some of) the coupled models realized with OASIS within the past 5 years or so in Europe and in other institutions in the world:

| Lab               | Cnt           | Vrs        | Atm                 | Oce                      | Comp                     |
|-------------------|---------------|------------|---------------------|--------------------------|--------------------------|
| IRI               | USA           | 2.4        | ECHAM4              | MOM3                     | SGI Origin<br>IBM Power3 |
| JPL(NASA)         | USA           | 2.4        | QTCM                | Trident                  | SGI                      |
| JAMSTEC           | Jp            | 2.4        | ECHAM4              | OPA 8.2                  | ES SX5                   |
| U. of<br>Tasmania | Aus-<br>tral. | 3.0        | Data atm. model     | MOM4                     | SGI O3400<br>Compaq      |
| BMRC              | Aus-<br>tral. | 3.0<br>2.4 | BAM4<br>BAM3 T47L34 | MOM4<br>ACOM2 180X194X25 |                          |
| CAS-IIT           | India         | 3.0        | MM5                 | POM                      |                          |

**Table D.1:** List of couplings realized with OASIS within the past 5 years in institutions outside Europe . The columns list the institution, the country, the OASIS version used, the atmospheric model, the ocean model, and the computing platform used for the coupled model run.

| Lab        | Cnt               | Vrs | Atm                              | Oce                       | Comp        |
|------------|-------------------|-----|----------------------------------|---------------------------|-------------|
| IPSL       | Fr                | 3.0 | LMDz 96x71x19<br>+ ORCH/INCA     | ORCA2 182x149x31<br>+ LIM | SX6         |
|            |                   | 2.4 | LMDz 96x71x19                    | ORCA2 182x149x31          | VPP5000     |
|            |                   | 2.4 | LMDz 72x45x19                    | ORCA4 92x76x31            | VPP5000     |
|            |                   | 2.4 | LMDZ 120X90X1                    | OPA ATL3 1/3 deg          |             |
|            |                   | 2.4 | LMDZ 120X90X1                    | OPA ATL1 1 deg            |             |
| Lodyc      | Fr                | 2.2 | IFS TI95 L31                     | OPA 8.1                   |             |
| Lodyc-ISA0 | Fr,It             | 2.3 | ECHAM4 T30/T42 L14               | ORCA2 182x149x31          | SX4,SX5     |
| Météo-Fr   | Fr                | 3.0 | ARPEGE 4                         | ORCA2                     | VPP5000     |
|            |                   | 2.4 | ARPEGE medias                    | OPA med 1/8e              | VPP5000     |
|            |                   | 2.2 | ARPEGE 3                         | OPA 8.1 + Gelato          | VPP5000     |
|            |                   | 2.1 | ARPEGE 2 T31L19                  | OPA8 TDH                  | CRAY J90    |
| Mercator   | Fr                | 3.0 | interp. mode                     | PAM (OPA)                 |             |
| CERFACS    | Fr                | 2.4 | ARPEGE 3                         | ORCA2-LIM                 | VPP5000     |
|            |                   | 2.2 | ARPEGE 3                         | OPA 8.1                   | VPP700      |
|            |                   | 2.1 | ARPEGE 2                         | OPAICE                    | CRAY C90    |
| ECMWF      | UK                | 2.2 | IFS T63/T255                     | E-HOPE 2deg/1deg          | IBM Power 4 |
|            |                   | 2.2 | IFS Cy23r4 T159L40               | E-HOPE 256L29             | VPP700      |
|            |                   | 2.2 | IFS Cy23r4 T95L40                | E-HOPE 256L29             | VPP700      |
|            |                   | 2.0 | IFS Cy15r8 T63L31                | E-HOPE 128L20             | VPP300      |
| MPI        | Ger-<br>ma-<br>ny | 3.0 | ECHAM5                           | MPI-OM                    | IBM Power4  |
|            |                   | 2.4 | ECHAM5 T42/L19                   | C-HOPE T42+L20            | NEC-SX      |
|            |                   | 2.4 | PUMAT42/L19                      | C-HOPE 2deg GIN           | NEC-SX      |
|            |                   | 2.4 | EMAD                             | E-HOPE T42+L20            | CRAY C-90   |
|            |                   | 2.4 | ECHAM5 T42/L19                   | E-HOPE T42+L20            | NEC-SX      |
|            |                   | 2.2 | ECHAM4 T30/L19                   | E-HOPE T42+L20            | CRAY T90    |
| CGAM       | UK                | 3.0 | HadAM3 2.5x3.75 L20              | ORCA2 182x149x31          | NEC SX6     |
|            |                   | 2.4 | HadAM3 2.5x3.75 L20              | ORCA 182x149x31           | T3E         |
| SMHI       | Sw                | 3.0 | ECHAM-RCA(reg.)                  |                           | SGI O3800   |
|            |                   | 2.3 | RCA-HIRLAM (reg.)                | RCO-OCCAM (reg.)          |             |
| INGV       | It                | 3.0 | ECHAM5                           | MPIOM                     | NEC SX6     |
| KNMI       | Nl                | 3.0 | ECHAM5                           | MPIOM                     | SGI IRIX64  |
| DMI        | Dk                | 3.0 | ECHAM (glob.)<br>- HIRLAM (reg.) |                           | NEC SX6     |
| U.Bergen   | Nw                | 3.0 | MM5                              | ROMS                      |             |
| SOC        | UK                | 2.2 | Interm. Atm. GCM                 | OCCAM-Lite                |             |

**Table D.2:** List of couplings realized with OASIS within the past 5 years in Europe. The columns list the institution, the country, the OASIS version used, the atmospheric model, the ocean model, and the computing platform used for the coupled model run.

# Bibliography

- [1] <http://climate.lanl.gov/Software/SCRIP/index.htm>
- [2] [http://www.gfdl.gov/~vb/mpp\\_io.html](http://www.gfdl.gov/~vb/mpp_io.html)
- [3] <http://www.unidata.ucar.edu/packages/udunits/udunits.dat>
- [4] Legutke, S. and V.Gayler, 2004: The PRISM Standard Compilation Environment. PRISM Report Series No 4.
- [5] Gayler, V. and S. Legutke, 2004: The PRISM Standard Running Environment. PRISM Report Series, No 5.
- [6] Valcke, S., 2004: The PRISM TOYCLIM Coupled Model Adaptation Guide. PRISM Report Series, No 7, 70 pp.
- [7] Carril, A., R. Budich, and S. Valcke, 2004: The TOYCLIM Demonstration Run Report. PRISM Report Series No 13.
- [8] C. Cassou, P. Noyret, E. Sevault, O. Thual, L. Terray, D. Beaucourt, and M. Imbard. Distributed Ocean-Atmosphere Modelling and Sensitivity to the Coupling Flux Precision: the CATHODE Project. *Monthly Weather Review*, 126, No 4: 1035-1053, 1998.
- [9] L. Terray and O. Thual. Oasis: le couplage océan-atmosphère. *La Météorologie*, 10:50–61, 1995.
- [10] M. Pontaud, L. Terray, E. Guilyardi, E. Sevault, D. B. Stephenson, and O. Thual. Coupled ocean-atmosphere modelling - computing and scientific aspects. In *2nd UNAM-CRAY supercomputing conference, Numerical simulations in the environmental and earth sciences* Mexico-city, Mexico, 1995.
- [11] E. Sevault, P. Noyret, and L. Terray. Clim 1.2 user guide and reference manual. *Technical Report TR/CGMC/95-47*, CERFACS, 1995.
- [12] P. Noyret, E. Sevault, L. Terray and O. Thual. Ocean-atmosphere coupling. *Proceedings of the Fall Cray User Group (CUG) meeting*, 1994.
- [13] L. Terray, and O. Thual. Coupled ocean-atmosphere simulations. In *High Performance Computing in the Geosciences, proceedings of the Les Houches Workshop* F.X. Le Dimet Ed., Kluwer Academic Publishers B.V, 1993.