

## IPSLCM6\_LR - (IPSLCM6\_rc1) configuration

---

### Table of Content


<b>IPSLCM6_LR - (IPSLCM6_rc1) configuration</b>	<b>1</b>
<b>1. IPSLCM6 model</b>	<b>2</b>
<b>2. Resolutions and configurations</b>	<b>2</b>
<b>2.1. IPSLCM6-LR_rc1</b>	<b>2</b>
<b>2.1.1. How to use it</b>	<b>3</b>
<b>2.1.2. Restart files</b>	<b>3</b>
<b>2.1.3. Output level</b>	<b>3</b>
<b>2.1.4. Lengths, frequencies</b>	<b>3</b>
<b>2.1.4.1. Period length</b>	<b>3</b>
<b>2.1.4.2. Pack Frequency</b>	<b>3</b>
<b>2.1.4.3. Rebuild frequency</b>	<b>3</b>
<b>2.1.4.4. How to add a parameter in NEMO's namelist?</b>	<b>3</b>
<b>2.1.4.5. What is the maximum length for a simulation name?</b>	<b>4</b>
<b>2.1.5. Computing centres</b>	<b>4</b>
<b>2.1.5.1. TGCC Bull Curie thin nodes</b>	<b>4</b>

Person in charge: Olivier Marti

## 1. IPSLCM6 model

You can find [here](#) a description for IPSLCM6 model

The version rc1 (IPSLCM6\_rc1) runs on **Curie-TGCC thin nodes**.



## 2. Resolutions and configurations

IPSLCM6 model will be available at different resolutions/configurations :

- **IPSLCM6A-VLR\_rc0** : LMDZ(Old Physics) 96x95x39-ORCHIDEE (Choisnel) - NEMO-LIM2-PISCES ORCA2. You can find [here](#) informations for the VLR (IPSLCM6\_rc0) configuration.
- **IPSLCM6-LR** (under development, **not available**) : LMDZ 144x144x79-ORCHIDEE (CWRR) - NEMO-LIM3-PISCES eORCA1xL75

### 2.1. IPSLCM6-LR\_rc1

The resolution of LMDZ is 144x142 (2.5° in longitude and 1.5° in latitude) with 79 vertical levels. The ocean configuration is eORCA1L75 : global ocean with a tripolar grid with one South pole, one North pole above Siberia and one North pole above northern America. The resolution is 1°. In the tropical region, the latitudinal resolution decreases to 1/2°. There are 76 vertical levels, with 1m resolution near the surface, and 200m in the abyss.

For LMDZ, the new physics is used. Current test (Sept. 2015) is NP 5.17h.

**IPSLCM6-LR\_rc1** is composed of following components and tools (Sept. 2015) :

```

#--H- IPSLCM6_rc1  IPSLCM6_rc1 coupled configuration
#--H- IPSLCM6_rc1  Working configuration started 27/03/2015
#--H- IPSLCM6_rc1  NEMOGCM branches/v3_6_STABLE/NEMOGCM revision 5618
#--H- IPSLCM6_rc1  XIOS branch xios-1.0 revision 592
#--H- IPSLCM6_rc1  IOIPSL/src svn tags/v2_2_2
#--H- IPSLCM6_rc1  LMDZ5 trunk revision 2327
#--H- IPSLCM6_rc1  ORCHIDEE version trunk rev 2724
#--H- IPSLCM6_rc1  OASIS3-MCT 2.0_branch rev 1129
#--H- IPSLCM6_rc1  IPSLCM6 svn
#--H- IPSLCM6_rc1  libIGCM trunk 1174
#--M- IPSLCM6_rc1  arnaud.caubel@lsce.ipsl.fr
#--C- IPSLCM6_rc1  IOIPSL/tags/v2_2_2/src
#--C- IPSLCM6_rc1  trunk/ORCHIDEE

```

	HEAD	8 IOIPSL/src modeles
	2848	14 ORCHIDEE modeles

#-C- IPSLCM6_rc1 branches/OASIS3-MCT_2.0_branch/oasis3-mct	1129	15	oasis3-mct	.
#-C- IPSLCM6_rc1 LMDZ5/trunk	2327	11	LMDZ	modeles
#-C- IPSLCM6_rc1 CONFIG/UNIFORM/v6/IPSLCM6	HEAD	8	IPSLCM6	config
#-C- IPSLCM6_rc1 trunk/libIGCM	1174	10	libIGCM	.
#-C- IPSLCM6_rc1 branches/2015/nemo_v3_6_STABLE/NEMOGCM	5618	7	.	modeles
#-C- IPSLCM6_rc1 trunk/ORCA1_LIM3_PISCES	HEAD	17	.	modeles/NEMOGCM/CONFIG
#-C- IPSLCM6_rc1 XIOS/branches/xios-1.0	604	12	XIOS	modeles

**Caution :** this is subject to quick changes !

### 2.1.1. How to use it

Here are the commands you need to know if you want to retrieve and compile the IPSLCM6 model and if you want to setup and run a piControl experiment (only piControl experiment is available):

```
mkdir YOUR_DIRECTORY ; cd YOUR_DIRECTORY
svn_ano # svn co http://forge.ipsl.jussieu.fr/igcmg/svn/modips1/trunk modips1
cd modips1/util
./model IPSLCM6_rc1
cd ../config/IPSLCM6
gmake IPSLCM6-LR
cp EXPERIMENTS/IPSLCM6/EXP00/config.card .
vi config.card # modify JobName (at least) : MYJOBNAME, restarts
.../util/ins_job # Check and complete job's header
# .../util/ins_job -m Intel # on ada after a compilation with Intel 2016.2
cd MYJOBNAME
vi Job_MYJOBNAME # modify PeriodNb, adjust the time, headers ...
llsubmit Job_MYJOBNAME # IDRIS
ccc_msub Job_MYJOBNAME # TGCC
```

### 2.1.2. Restart files

Not available yet. Waiting for reference simulations.

### 2.1.3. Output level

By default, only **monthly outputs** and **low output levels** are activated.

### 2.1.4. Lengths, frequencies

#### 2.1.4.1. Period length

Default period length is 1Y, i.e in config.card :

```
PeriodLength=1Y
```

Note that clean\_PeriodLength.job will remove last period files, i.e last simulated year files.

#### 2.1.4.2. Pack Frequency

Default pack frequency is 1Y, i.e in config.card :

```
PackFrequency=1Y
```

#### 2.1.4.3. Rebuild frequency

Since we run with XIOS (server mode) as output library, **the rebuild step is not needed anymore**.

#### 2.1.4.4. How to add a parameter in NEMO's namelist?

- let find the parameter in namelist\_ref. For example in modeles/NEMOGCM/CONFIG/SHARED/namelist\_ice\_lim3\_ref

- let find the namelist's name : for example &namicdyn
- let add a line with the new of the parameter in the file PARAM/namelist\_lim3\_ORCA1\_cfg in the &namicdyn section

#### 2.1.4.5. What is the maximum length for a simulation name?

Due to limitation in NEMO, a simulation should have **less than 39 characters**.

#### 2.1.5. Computing centres

##### 2.1.5.1. TGCC Bull Curie thin nodes

Default configuration on **598 cores** allows you to run **3 simulated years per day**. Because of load-balancing (difference between ocean computing time and atmosphere computing time), not all configurations (in terms of number of process/threads) are efficient. If you want to run a configuration with less cores, ask Arnaud Caubel what would be the optimum configuration.