

SIREN
NEMO 3.6

Generated by Doxygen 1.8.5

Fri Nov 25 2016 17:16:10

Contents

1	About	1
2	Download	3
3	How To Use (Quick Start)	5
3.1	Create coordinates file	6
3.2	Create bathymetry file	9
3.3	Merge bathymetry file	10
3.4	Create meshmask (ocean domain informations)	11
3.5	Create initial state	13
3.6	Create boundaries conditions	15
3.7	Create and run NEMO configuration	16
4	Support	19
5	Coding Rules	21
5.1	Fortran Standard	21
5.2	Free Form Source	21
5.3	Indentation	21
5.4	Naming conventions : variable	21
5.5	Naming conventions : structure	22
5.6	Naming conventions : function-subroutine	22
5.7	Precision	23
5.8	Declaration for global variable and constants	23
5.9	Implicit none	23
5.10	Header	23
6	Change log	25
7	NEMO periodicity	27
8	Todo List	29
9	Class Index	31

9.1 Class List	31
10 File Index	35
10.1 File List	35
11 Class Documentation	37
11.1 att Module Reference	37
11.1.1 Detailed Description	37
11.1.2 Member Function/Subroutine Documentation	39
11.1.2.1 att_get_dummy	39
11.1.2.2 att_get_id	39
11.1.2.3 att_get_index	40
11.1.2.4 att_is_dummy	40
11.2 att::att_clean Interface Reference	41
11.2.1 Member Function/Subroutine Documentation	41
11.2.1.1 att__clean_arr	41
11.2.1.2 att__clean_unit	41
11.3 att::att_copy Interface Reference	41
11.3.1 Member Function/Subroutine Documentation	42
11.3.1.1 att__copy_arr	42
11.3.1.2 att__copy_unit	42
11.4 att::att_init Interface Reference	43
11.4.1 Member Function/Subroutine Documentation	43
11.4.1.1 att__init_c	43
11.4.1.2 att__init_dp	44
11.4.1.3 att__init_dp_0d	44
11.4.1.4 att__init_i1	45
11.4.1.5 att__init_i1_0d	45
11.4.1.6 att__init_i2	46
11.4.1.7 att__init_i2_0d	46
11.4.1.8 att__init_i4	47
11.4.1.9 att__init_i4_0d	47
11.4.1.10 att__init_i8	47
11.4.1.11 att__init_i8_0d	48
11.4.1.12 att__init_sp	48
11.4.1.13 att__init_sp_0d	49
11.5 att::att_print Interface Reference	49
11.5.1 Member Function/Subroutine Documentation	49
11.5.1.1 att__print_arr	49
11.5.1.2 att__print_unit	50
11.6 boundary Module Reference	50

11.6.1 Detailed Description	51
11.6.2 Member Function/Subroutine Documentation	53
11.6.2.1 boundary_check	53
11.6.2.2 boundary_check_corner	54
11.6.2.3 boundary_get_indices	54
11.6.2.4 boundary_set_filename	55
11.6.2.5 boundary_swap	55
11.7 boundary::boundary_clean Interface Reference	56
11.7.1 Member Function/Subroutine Documentation	56
11.7.1.1 boundary__clean_arr	56
11.7.1.2 boundary__clean_unit	56
11.8 boundary::boundary_copy Interface Reference	56
11.8.1 Member Function/Subroutine Documentation	57
11.8.1.1 boundary__copy_arr	57
11.8.1.2 boundary__copy_unit	57
11.9 boundary::boundary_init Interface Reference	58
11.9.1 Member Function/Subroutine Documentation	58
11.9.1.1 boundary__init_wrapper	58
11.10 boundary::boundary_print Interface Reference	59
11.10.1 Member Function/Subroutine Documentation	59
11.10.1.1 boundary__print_arr	59
11.10.1.2 boundary__print_unit	59
11.11 date Module Reference	60
11.11.1 Detailed Description	60
11.11.2 Member Function/Subroutine Documentation	62
11.11.2.1 date_leapyear	62
11.11.2.2 date_now	63
11.11.2.3 date_print	63
11.11.2.4 date_today	63
11.12 date::date_init Interface Reference	64
11.12.1 Member Function/Subroutine Documentation	64
11.12.1.1 date__init_fmtdate	64
11.12.1.2 date__init_jd	65
11.12.1.3 date__init_nsec	65
11.12.1.4 date__init_ymd	65
11.13 dim Module Reference	66
11.13.1 Detailed Description	67
11.13.2 Member Function/Subroutine Documentation	70
11.13.2.1 dim_def_extra	70
11.13.2.2 dim_disorder	70

11.13.2.3	dim_fill_unused	70
11.13.2.4	dim_get_dummy	71
11.13.2.5	dim_get_id	71
11.13.2.6	dim_get_index	72
11.13.2.7	dim_init	72
11.13.2.8	dim_is_dummy	73
11.13.2.9	dim_reorder	73
11.14	dim::dim_clean Interface Reference	74
11.14.1	Member Function/Subroutine Documentation	74
11.14.1.1	dim__clean_arr	74
11.14.1.2	dim__clean_unit	74
11.15	dim::dim_copy Interface Reference	75
11.15.1	Member Function/Subroutine Documentation	75
11.15.1.1	dim__copy_arr	75
11.15.1.2	dim__copy_unit	75
11.16	dim::dim_print Interface Reference	76
11.16.1	Member Function/Subroutine Documentation	76
11.16.1.1	dim__print_arr	76
11.16.1.2	dim__print_unit	77
11.17	dim::dim_reorder_2xyzt Interface Reference	77
11.17.1	Member Function/Subroutine Documentation	77
11.17.1.1	dim__reorder_2xyzt_c	77
11.17.1.2	dim__reorder_2xyzt_i4	78
11.17.1.3	dim__reorder_2xyzt_l	78
11.18	dim::dim_reorder_xyz2 Interface Reference	79
11.18.1	Member Function/Subroutine Documentation	79
11.18.1.1	dim__reorder_xyz2_c	79
11.18.1.2	dim__reorder_xyz2_i4	80
11.18.1.3	dim__reorder_xyz2_l	80
11.19	dim::dim_reshape_2xyzt Interface Reference	81
11.19.1	Member Function/Subroutine Documentation	81
11.19.1.1	dim__reshape_2xyzt_dp	81
11.20	dim::dim_reshape_xyz2 Interface Reference	81
11.20.1	Member Function/Subroutine Documentation	82
11.20.1.1	dim__reshape_xyz2_dp	82
11.21	dom Module Reference	82
11.21.1	Detailed Description	83
11.21.2	Member Function/Subroutine Documentation	86
11.21.2.1	dom__init_file	86
11.21.2.2	dom__add_extra	86

11.21.2.3 dom_clean	87
11.21.2.4 dom_clean_extra	87
11.21.2.5 dom_del_extra	87
11.21.2.6 dom_print	88
11.22dom::dom_copy Interface Reference	88
11.22.1 Member Function/Subroutine Documentation	88
11.22.1.1 dom__copy_unit	88
11.23dom::dom_init Interface Reference	89
11.23.1 Member Function/Subroutine Documentation	89
11.23.1.1 dom__init_file	89
11.23.1.2 dom__init_mpp	90
11.24extrap Module Reference	90
11.24.1 Detailed Description	91
11.24.2 Member Function/Subroutine Documentation	92
11.24.2.1 extrap_add_extrabands	92
11.24.2.2 extrap_del_extrabands	93
11.25extrap::extrap_detect Interface Reference	93
11.25.1 Member Function/Subroutine Documentation	93
11.25.1.1 extrap__detect_wrapper	93
11.26extrap::extrap_fill_value Interface Reference	94
11.26.1 Member Function/Subroutine Documentation	94
11.26.1.1 extrap__fill_value_wrapper	94
11.27fct Module Reference	95
11.27.1 Detailed Description	96
11.27.2 Member Function/Subroutine Documentation	97
11.27.2.1 fct_basename	97
11.27.2.2 fct_concat	98
11.27.2.3 fct_dirname	98
11.27.2.4 fct_err	99
11.27.2.5 fct_getunit	99
11.27.2.6 fct_is_num	99
11.27.2.7 fct_is_real	100
11.27.2.8 fct_lower	100
11.27.2.9 fct_pause	101
11.27.2.10fct_split	101
11.27.2.11fct_upper	101
11.28fct::fct_str Interface Reference	102
11.28.1 Member Function/Subroutine Documentation	102
11.28.1.1 fct__i1_str	102
11.28.1.2 fct__i2_str	103

11.28.1.3	fct__i4_str	103
11.28.1.4	fct__i8_str	103
11.28.1.5	fct__l_str	104
11.28.1.6	fct__r4_str	104
11.28.1.7	fct__r8_str	104
11.29	file Module Reference	105
11.29.1	Detailed Description	106
11.29.2	Member Function/Subroutine Documentation	108
11.29.2.1	file_add_att	108
11.29.2.2	file_add_dim	109
11.29.2.3	file_add_suffix	109
11.29.2.4	file_add_var	109
11.29.2.5	file_check_var_dim	110
11.29.2.6	file_del_dim	110
11.29.2.7	file_get_id	111
11.29.2.8	file_get_type	111
11.29.2.9	file_get_unit	111
11.29.2.10	file_init	112
11.29.2.11	file_move_att	112
11.29.2.12	file_move_dim	113
11.29.2.13	file_move_var	113
11.29.2.14	file_print	113
11.30	file::file_clean Interface Reference	114
11.30.1	Member Function/Subroutine Documentation	114
11.30.1.1	file__clean_arr	114
11.30.1.2	file__clean_unit	114
11.31	file::file_copy Interface Reference	115
11.31.1	Member Function/Subroutine Documentation	115
11.31.1.1	file__copy_arr	115
11.31.1.2	file__copy_unit	115
11.32	file::file_del_att Interface Reference	116
11.32.1	Member Function/Subroutine Documentation	116
11.32.1.1	file__del_att_name	116
11.32.1.2	file__del_att_str	117
11.33	file::file_del_var Interface Reference	117
11.33.1	Member Function/Subroutine Documentation	117
11.33.1.1	file__del_var_name	117
11.33.1.2	file__del_var_str	118
11.34	file::file_rename Interface Reference	118
11.34.1	Member Function/Subroutine Documentation	118

11.34.1.1 file__rename_char	118
11.34.1.2 file__rename_str	119
11.35filter Module Reference	119
11.35.1 Detailed Description	119
11.36filter::filter_fill_value Interface Reference	121
11.36.1 Member Function/Subroutine Documentation	121
11.36.1.1 filter__fill_value_wrapper	121
11.37global Module Reference	121
11.37.1 Detailed Description	123
11.38grid Module Reference	123
11.38.1 Detailed Description	124
11.38.2 Member Function/Subroutine Documentation	128
11.38.2.1 grid_add_ghost	128
11.38.2.2 grid_check_coincidence	128
11.38.2.3 grid_check_dom	129
11.38.2.4 grid_del_ghost	129
11.38.2.5 grid_distance	130
11.38.2.6 grid_fill_small_dom	130
11.38.2.7 grid_fill_small_msk	131
11.38.2.8 grid_is_global	131
11.38.2.9 grid_is_north_fold	131
11.38.2.10grid_split_domain	132
11.39grid::grid_get_closest Interface Reference	132
11.39.1 Member Function/Subroutine Documentation	132
11.39.1.1 grid__get_closest_arr	132
11.39.1.2 grid__get_closest_str	133
11.40grid::grid_get_coarse_index Interface Reference	134
11.40.1 Member Function/Subroutine Documentation	135
11.40.1.1 grid__get_coarse_index_cc	135
11.40.1.2 grid__get_coarse_index_cf	136
11.40.1.3 grid__get_coarse_index_fc	136
11.40.1.4 grid__get_coarse_index_ff	137
11.41grid::grid_get_ew_overlap Interface Reference	137
11.41.1 Member Function/Subroutine Documentation	138
11.41.1.1 grid__get_ew_overlap_file	138
11.41.1.2 grid__get_ew_overlap_mpp	138
11.41.1.3 grid__get_ew_overlap_var	139
11.42grid::grid_get_fine_offset Interface Reference	139
11.42.1 Member Function/Subroutine Documentation	140
11.42.1.1 grid__get_fine_offset_cc	140

11.42.1.2 grid__get_fine_offset_cf	141
11.42.1.3 grid__get_fine_offset_fc	141
11.42.1.4 grid__get_fine_offset_ff	142
11.43grid::grid_get_ghost Interface Reference	143
11.43.1 Member Function/Subroutine Documentation	143
11.43.1.1 grid__get_ghost_mpp	143
11.43.1.2 grid__get_ghost_var	143
11.44grid::grid_get_info Interface Reference	144
11.44.1 Member Function/Subroutine Documentation	144
11.44.1.1 grid__get_info_file	144
11.44.1.2 grid__get_info_mpp	145
11.45grid::grid_get_perio Interface Reference	145
11.45.1 Member Function/Subroutine Documentation	145
11.45.1.1 grid__get_perio_file	145
11.45.1.2 grid__get_perio_mpp	146
11.45.1.3 grid__get_perio_var	146
11.46grid::grid_get_pivot Interface Reference	147
11.46.1 Member Function/Subroutine Documentation	147
11.46.1.1 grid__get_pivot_file	147
11.46.1.2 grid__get_pivot_mpp	148
11.46.1.3 grid__get_pivot_var	148
11.47grid_hgr Module Reference	149
11.47.1 Detailed Description	150
11.47.2 Member Function/Subroutine Documentation	152
11.47.2.1 grid_hgr_clean	152
11.47.2.2 grid_hgr_fill	152
11.47.2.3 grid_hgr_init	153
11.47.2.4 grid_hgr_nam	153
11.48grid_zgr Module Reference	153
11.48.1 Detailed Description	155
11.48.2 Member Function/Subroutine Documentation	156
11.48.2.1 grid_zgr_clean	156
11.48.2.2 grid_zgr_fill	156
11.48.2.3 grid_zgr_init	157
11.48.2.4 grid_zgr_nam	157
11.48.2.5 grid_zgr_sco_clean	158
11.48.2.6 grid_zgr_sco_init	158
11.48.2.7 grid_zgr_sco_stiff	158
11.48.2.8 grid_zgr_zps_clean	159
11.48.2.9 grid_zgr_zps_init	159

11.49interp Module Reference	159
11.49.1 Detailed Description	160
11.49.2 Member Function/Subroutine Documentation	161
11.49.2.1 interp_clean_mixed_grid	161
11.49.2.2 interp_create_mixed_grid	162
11.50interp_cubic Module Reference	162
11.50.1 Detailed Description	162
11.50.2 Member Function/Subroutine Documentation	163
11.50.2.1 interp_cubic_fill	163
11.51interp::interp_detect Interface Reference	163
11.51.1 Member Function/Subroutine Documentation	164
11.51.1.1 interp__detect_wrapper	164
11.52interp::interp_fill_value Interface Reference	164
11.52.1 Member Function/Subroutine Documentation	164
11.52.1.1 interp__fill_value_wrapper	164
11.53interp_linear Module Reference	165
11.53.1 Detailed Description	165
11.53.2 Member Function/Subroutine Documentation	166
11.53.2.1 interp_linear_fill	166
11.54interp_nearest Module Reference	166
11.54.1 Detailed Description	166
11.54.2 Member Function/Subroutine Documentation	167
11.54.2.1 interp_nearest_fill	167
11.55iom Module Reference	167
11.55.1 Detailed Description	168
11.55.2 Member Function/Subroutine Documentation	169
11.55.2.1 iom_close	169
11.55.2.2 iom_create	169
11.55.2.3 iom_open	170
11.55.2.4 iom_write_file	170
11.56iom_cdf Module Reference	171
11.56.1 Detailed Description	171
11.56.2 Member Function/Subroutine Documentation	172
11.56.2.1 iom_cdf_close	172
11.56.2.2 iom_cdf_open	173
11.56.2.3 iom_cdf_write_file	173
11.57iom_cdf::iom_cdf_fill_var Interface Reference	174
11.57.1 Member Function/Subroutine Documentation	174
11.57.1.1 iom_cdf__fill_var_all	174
11.57.1.2 iom_cdf__fill_var_id	174

11.57.1.3 iom_cdf__fill_var_name	175
11.58iom_cdf::iom_cdf_read_att Interface Reference	175
11.58.1 Member Function/Subroutine Documentation	175
11.58.1.1 iom_cdf__read_att_id	175
11.58.1.2 iom_cdf__read_att_name	176
11.59iom_cdf::iom_cdf_read_dim Interface Reference	176
11.59.1 Member Function/Subroutine Documentation	176
11.59.1.1 iom_cdf__read_dim_id	176
11.59.1.2 iom_cdf__read_dim_name	177
11.60iom_cdf::iom_cdf_read_var Interface Reference	177
11.60.1 Member Function/Subroutine Documentation	178
11.60.1.1 iom_cdf__read_var_id	178
11.60.1.2 iom_cdf__read_var_name	178
11.61iom_dom Module Reference	179
11.61.1 Detailed Description	179
11.61.2 Member Function/Subroutine Documentation	180
11.61.2.1 iom_dom_close	180
11.61.2.2 iom_dom_open	180
11.62iom_dom::iom_dom_read_var Interface Reference	180
11.62.1 Member Function/Subroutine Documentation	180
11.62.1.1 iom_dom__read_var_id	180
11.62.1.2 iom_dom__read_var_name	181
11.63iom_mpp Module Reference	181
11.63.1 Detailed Description	182
11.63.2 Member Function/Subroutine Documentation	183
11.63.2.1 iom_mpp_close	183
11.63.2.2 iom_mpp_create	184
11.63.2.3 iom_mpp_open	184
11.63.2.4 iom_mpp_write_file	184
11.64iom_mpp::iom_mpp_read_var Interface Reference	185
11.64.1 Member Function/Subroutine Documentation	185
11.64.1.1 iom_mpp__read_var_id	185
11.64.1.2 iom_mpp__read_var_name	186
11.65iom::iom_read_att Interface Reference	186
11.65.1 Member Function/Subroutine Documentation	187
11.65.1.1 iom__read_att_varid_id	187
11.65.1.2 iom__read_att_varid_name	188
11.65.1.3 iom__read_att_varname_id	188
11.65.1.4 iom__read_att_varname_name	189
11.66iom::iom_read_dim Interface Reference	189

11.66.1 Member Function/Subroutine Documentation	189
11.66.1.1 iom__read_dim_id	189
11.66.1.2 iom__read_dim_name	190
11.67iom::iom_read_var Interface Reference	190
11.67.1 Member Function/Subroutine Documentation	190
11.67.1.1 iom__read_var_id	190
11.67.1.2 iom__read_var_name	191
11.68iom_rstdimg Module Reference	191
11.68.1 Detailed Description	192
11.68.2 Member Function/Subroutine Documentation	193
11.68.2.1 iom_rstdimg_close	193
11.68.2.2 iom_rstdimg_get_mpp	193
11.68.2.3 iom_rstdimg_open	194
11.68.2.4 iom_rstdimg_write_file	194
11.69iom_rstdimg::iom_rstdimg_read_dim Interface Reference	195
11.69.1 Member Function/Subroutine Documentation	195
11.69.1.1 iom_rstdimg__read_dim_id	195
11.69.1.2 iom_rstdimg__read_dim_name	195
11.70iom_rstdimg::iom_rstdimg_read_var Interface Reference	196
11.70.1 Member Function/Subroutine Documentation	196
11.70.1.1 iom_rstdimg__read_var_id	196
11.70.1.2 iom_rstdimg__read_var_name	196
11.71kind Module Reference	197
11.71.1 Detailed Description	197
11.72lbc Module Reference	198
11.72.1 Detailed Description	198
11.73lbc::lbc_hide_nfd Interface Reference	199
11.73.1 Member Function/Subroutine Documentation	199
11.73.1.1 lbc__hide_nfd_2d	199
11.74lbc::lbc_hide Interface Reference	199
11.74.1 Member Function/Subroutine Documentation	199
11.74.1.1 lbc__hide_ink_2d	199
11.75lbc::lbc_ink Interface Reference	200
11.75.1 Member Function/Subroutine Documentation	200
11.75.1.1 lbc__ink_2d	200
11.75.1.2 lbc__ink_3d	201
11.76lbc::lbc_nfd Interface Reference	201
11.76.1 Member Function/Subroutine Documentation	201
11.76.1.1 lbc__nfd_2d	201
11.76.1.2 lbc__nfd_3d	202

11.77	logger Module Reference	202
11.77.1	Detailed Description	203
11.77.2	Member Function/Subroutine Documentation	205
11.77.2.1	logger_clean	205
11.77.2.2	logger_close	206
11.77.2.3	logger_debug	206
11.77.2.4	logger_error	206
11.77.2.5	logger_fatal	206
11.77.2.6	logger_flush	207
11.77.2.7	logger_footer	207
11.77.2.8	logger_header	207
11.77.2.9	logger_info	208
11.77.2.10	logger_open	208
11.77.2.11	logger_trace	208
11.77.2.12	logger_warn	209
11.78	math Module Reference	209
11.78.1	Detailed Description	210
11.78.2	Member Function/Subroutine Documentation	212
11.78.2.1	math_compute	212
11.78.2.2	math_deriv_1d	212
11.78.2.3	math_deriv_2d	212
11.78.2.4	math_deriv_3d	213
11.78.2.5	math_qsortc	213
11.78.2.6	math_unwrap	214
11.79	math::math_mean Interface Reference	214
11.79.1	Member Function/Subroutine Documentation	214
11.79.1.1	math__mean_1d	214
11.79.1.2	math__mean_2d	215
11.80	math::math_median Interface Reference	215
11.80.1	Member Function/Subroutine Documentation	216
11.80.1.1	math__median_1d	216
11.80.1.2	math__median_2d	216
11.81	math::math_mwe Interface Reference	216
11.81.1	Member Function/Subroutine Documentation	217
11.81.1.1	math__mwe_1d	217
11.81.1.2	math__mwe_2d	217
11.82	mpp Module Reference	217
11.82.1	Detailed Description	219
11.82.2	Member Function/Subroutine Documentation	223
11.82.2.1	mpp_add_att	223

11.82.2.2 mpp_add_dim	223
11.82.2.3 mpp_add_var	223
11.82.2.4 mpp_del_dim	224
11.82.2.5 mpp_get_contour	224
11.82.2.6 mpp_get_dom	224
11.82.2.7 mpp_get_index	225
11.82.2.8 mpp_get_proc_index	225
11.82.2.9 mpp_get_proc_size	225
11.82.2.10 mpp_move_att	226
11.82.2.11 mpp_move_dim	226
11.82.2.12 mpp_move_var	226
11.82.2.13 mpp_print	227
11.82.2.14 mpp_recombine_var	227
11.83 mpp::mpp_add_proc Interface Reference	227
11.83.1 Member Function/Subroutine Documentation	228
11.83.1.1 mpp__add_proc_unit	228
11.84 mpp::mpp_check_dim Interface Reference	228
11.84.1 Member Function/Subroutine Documentation	229
11.84.1.1 mpp__check_proc_dim	229
11.84.1.2 mpp__check_var_dim	229
11.85 mpp::mpp_del_proc Interface Reference	229
11.85.1 Member Function/Subroutine Documentation	230
11.85.1.1 mpp__del_proc_id	230
11.85.1.2 mpp__del_proc_str	230
11.86 mpp::mpp_clean Interface Reference	230
11.86.1 Member Function/Subroutine Documentation	231
11.86.1.1 mpp__clean_arr	231
11.86.1.2 mpp__clean_unit	231
11.87 mpp::mpp_copy Interface Reference	231
11.87.1 Member Function/Subroutine Documentation	231
11.87.1.1 mpp__copy_arr	231
11.87.1.2 mpp__copy_unit	232
11.88 mpp::mpp_del_att Interface Reference	233
11.88.1 Member Function/Subroutine Documentation	233
11.88.1.1 mpp__del_att_name	233
11.88.1.2 mpp__del_att_str	233
11.89 mpp::mpp_del_var Interface Reference	234
11.89.1 Member Function/Subroutine Documentation	234
11.89.1.1 mpp__del_var_mpp	234
11.89.1.2 mpp__del_var_name	234

11.89.1.3 mpp__del_var_str	234
11.90 mpp::mpp_get_use Interface Reference	235
11.90.1 Member Function/Subroutine Documentation	235
11.90.1.1 mpp__get_use_unit	235
11.91 mpp::mpp_init Interface Reference	235
11.91.1 Member Function/Subroutine Documentation	236
11.91.1.1 mpp__init_file	236
11.91.1.2 mpp__init_mask	237
11.91.1.3 mpp__init_var	237
11.92 multi Module Reference	238
11.92.1 Detailed Description	238
11.92.2 Member Function/Subroutine Documentation	240
11.92.2.1 multi__add_mpp	240
11.92.2.2 multi_clean	240
11.92.2.3 multi_init	240
11.92.2.4 multi_print	241
11.93 multi::multi_copy Interface Reference	241
11.93.1 Member Function/Subroutine Documentation	241
11.93.1.1 multi__copy_unit	241
11.94 date::operator(+) Interface Reference	242
11.94.1 Member Function/Subroutine Documentation	242
11.94.1.1 date__addnday	242
11.95 date::operator(-) Interface Reference	243
11.95.1 Member Function/Subroutine Documentation	243
11.95.1.1 date__diffdate	243
11.95.1.2 date__subnday	243
11.96 fct::operator(/) Interface Reference	244
11.96.1 Member Function/Subroutine Documentation	244
11.96.1.1 fct__i1_cat	244
11.96.1.2 fct__i2_cat	245
11.96.1.3 fct__i4_cat	245
11.96.1.4 fct__i8_cat	246
11.96.1.5 fct__l_cat	246
11.96.1.6 fct__r4_cat	246
11.96.1.7 fct__r8_cat	247
11.97 phycst Module Reference	247
11.97.1 Detailed Description	248
11.98 boundary::seg_clean Interface Reference	248
11.98.1 Member Function/Subroutine Documentation	248
11.98.1.1 seg_clean_arr	248

11.98.1.2 seg__clean_unit	249
11.99boundary::seg__copy Interface Reference	249
11.99.1 Member Function/Subroutine Documentation	249
11.99.1.1 seg__copy_arr	249
11.99.1.2 seg__copy_unit	250
11.100att::tatt Type Reference	250
11.100boundary::tbody Type Reference	251
11.101.Detailed Description	251
11.100date::tdate Type Reference	251
11.100dim::tdim Type Reference	252
11.100dom::tdom Type Reference	252
11.100file::tfile Type Reference	253
11.100interp::tinterp Type Reference	255
11.100hpp::tlay Type Reference	255
11.107.Detailed Description	256
11.100logger::tlogger Type Reference	256
11.100hpp::tmpp Type Reference	257
11.110multi::tmulti Type Reference	257
11.110grid_hgr::tnamh Type Reference	258
11.110grid_zgr::tnamz Type Reference	258
11.110boundary::tseg Type Reference	259
11.110var::tvar Type Reference	259
11.110var Module Reference	261
11.115.Detailed Description	262
11.115.2Member Function/Subroutine Documentation	268
11.115.2.1var_check_dim	268
11.115.2.2var_chg_extra	268
11.115.2.3var_chg_fillvalue	269
11.115.2.4var_chg_unit	269
11.115.2.5var_clean_extra	270
11.115.2.6var_concat	270
11.115.2.7var_def_extra	270
11.115.2.8var_del_dim	271
11.115.2.9var_del_value	271
11.115.2.10var_get_dummy	271
11.115.2.11var_get_id	272
11.115.2.12var_get_index	272
11.115.2.13var_get_mask	273
11.115.2.14var_get_unit	273
11.115.2.15var_is_dummy	273

11.115.2.1	var_limit_value	274
11.115.2.1	var_max_dim	274
11.115.2.1	var_move_att	274
11.115.2.1	var_move_dim	275
11.115.2.2	var_read_matrix	275
11.115.2.2	var_reorder	276
11.115.2.2	var_to_date	276
11.116	var::var_add_att Interface Reference	276
11.116.1	Member Function/Subroutine Documentation	277
11.116.1.1	var__add_att_arr	277
11.116.1.2	var__add_att_unit	277
11.117	var::var_add_dim Interface Reference	277
11.117.1	Member Function/Subroutine Documentation	278
11.117.1.1	var__add_dim_arr	278
11.117.1.2	var__add_dim_unit	278
11.118	var::var_add_value Interface Reference	278
11.118.1	Member Function/Subroutine Documentation	279
11.118.1.1	var__add_value_dp	279
11.118.1.2	var__add_value_i1	279
11.118.1.3	var__add_value_i2	280
11.118.1.4	var__add_value_i4	280
11.118.1.5	var__add_value_i8	281
11.118.1.6	var__add_value_rp	281
11.119	var::var_clean Interface Reference	282
11.119.1	Member Function/Subroutine Documentation	282
11.119.1.1	var__clean_arr_1d	282
11.119.1.2	var__clean_arr_2d	283
11.119.1.3	var__clean_arr_3d	283
11.119.1.4	var__clean_unit	283
11.120	var::var_copy Interface Reference	284
11.120.1	Member Function/Subroutine Documentation	284
11.120.1.1	var__copy_arr	284
11.120.1.2	var__copy_unit	284
11.121	var::var_del_att Interface Reference	285
11.121.1	Member Function/Subroutine Documentation	285
11.121.1.1	var__del_att_name	285
11.121.1.2	var__del_att_str	286
11.122	var::var_init Interface Reference	286
11.122.1	Member Function/Subroutine Documentation	288
11.122.1.1	var__init	288

11.122.1.2	<code>var__init_1d_dp</code>	290
11.122.1.3	<code>var__init_1d_i1</code>	292
11.122.1.4	<code>var__init_1d_i2</code>	293
11.122.1.5	<code>var__init_1d_i4</code>	295
11.122.1.6	<code>var__init_1d_i8</code>	296
11.122.1.7	<code>var__init_1d_sp</code>	298
11.122.1.8	<code>var__init_2d_dp</code>	299
11.122.1.9	<code>var__init_2d_i1</code>	301
11.122.1.10	<code>var__init_2d_i2</code>	302
11.122.1.11	<code>var__init_2d_i4</code>	304
11.122.1.12	<code>var__init_2d_i8</code>	305
11.122.1.13	<code>var__init_2d_sp</code>	307
11.122.1.14	<code>var__init_3d_dp</code>	308
11.122.1.15	<code>var__init_3d_i1</code>	310
11.122.1.16	<code>var__init_3d_i2</code>	311
11.122.1.17	<code>var__init_3d_i4</code>	313
11.122.1.18	<code>var__init_3d_i8</code>	314
11.122.1.19	<code>var__init_3d_sp</code>	316
11.122.1.20	<code>var__init_dp</code>	317
11.122.1.21	<code>var__init_i1</code>	319
11.122.1.22	<code>var__init_i2</code>	320
11.122.1.23	<code>var__init_i4</code>	322
11.122.1.24	<code>var__init_i8</code>	323
11.122.1.25	<code>var__init_sp</code>	325
11.123	<code>var::var_print</code> Interface Reference	326
11.123.1	Member Function/Subroutine Documentation	326
11.123.1.1	<code>var__print_arr</code>	326
11.123.1.2	<code>var__print_unit</code>	327
11.124	<code>grid</code> Module Reference	327
11.124.1	Detailed Description	328
11.124.2	Member Function/Subroutine Documentation	329
11.124.2.1	<code>grid_get_level</code>	329
11.124.2.2	<code>grid_zgr_bat</code>	330
11.124.2.3	<code>grid_zgr_bat_ctl</code>	330
11.124.2.4	<code>grid_zgr_z</code>	331
11.124.2.5	<code>grid_zgr_zps</code>	331
12	File Documentation	335
12.1	<code>src/create_bathy.f90</code> File Reference	335
12.1.1	Detailed Description	335

12.1.2	method	335
12.1.3	how to	335
12.1.4	Function/Subroutine Documentation	338
12.1.4.1	create_bathy	338
12.1.4.2	create_bathy_check_depth	338
12.1.4.3	create_bathy_check_time	339
12.1.4.4	create_bathy_extract	339
12.1.4.5	create_bathy_get_var	339
12.1.4.6	create_bathy_interp	340
12.1.4.7	create_bathy_matrix	340
12.2	src/create_boundary.F90 File Reference	341
12.2.1	Detailed Description	341
12.2.2	method	341
12.2.3	how to	342
12.2.4	Function/Subroutine Documentation	346
12.2.4.1	create__boundary	346
12.2.4.2	create_boundary	346
12.2.4.3	create_boundary_check_depth	347
12.2.4.4	create_boundary_check_time	347
12.2.4.5	create_boundary_get_coord	347
12.2.4.6	create_boundary_get_dom	348
12.2.4.7	create_boundary_get_level	348
12.2.4.8	create_boundary_interp	349
12.2.4.9	create_boundary_matrix	349
12.2.4.10	create_boundary_use_mask	349
12.3	src/create_coord.f90 File Reference	350
12.3.1	Detailed Description	350
12.3.2	method	350
12.3.3	how to	350
12.3.4	Function/Subroutine Documentation	352
12.3.4.1	create_coord	352
12.3.4.2	create_coord_get_offset	353
12.3.4.3	create_coord_interp	353
12.4	src/create_meshmask.f90 File Reference	353
12.4.1	Detailed Description	354
12.4.2	method	354
12.4.3	how to	354
12.4.4	Function/Subroutine Documentation	358
12.4.4.1	create__gloatt	358
12.4.4.2	create__mask	358

12.4.4.3	create_meshmask	360
12.5	src/create_restart.f90 File Reference	360
12.5.1	Detailed Description	360
12.5.2	method	361
12.5.3	how to	361
12.5.4	Function/Subroutine Documentation	363
12.5.4.1	create_restart	363
12.5.4.2	create_restart_check_depth	364
12.5.4.3	create_restart_check_time	364
12.5.4.4	create_restart_interp	365
12.5.4.5	create_restart_mask	365
12.5.4.6	create_restart_matrix	365
12.6	src/merge_bathy.f90 File Reference	366
12.6.1	Detailed Description	366
12.6.2	method	366
12.6.3	how to	367
12.6.4	Function/Subroutine Documentation	367
12.6.4.1	merge_bathy	367
12.6.4.2	merge_bathy_get_boundary	369
12.6.4.3	merge_bathy_interp	369

Chapter 1

About

SIREN is a software to set up regional configuration with [NEMO](#).

Actually SIREN creates the input files you need to run a NEMO regional configuration.

SIREN allows you to create your own regional configuration embedded in a wider one.

To know how to install SIREN see [Download](#).

You could find a tutorial for a quick start with SIREN in [How To Use \(Quick Start\)](#).

For more information about how to use each component of SIREN

- see [create_coord.f90](#) to create fine grid coordinate file
- see [create_bathy.f90](#) to create fine grid bathymetry
- see [merge_bathy.f90](#) to merge fine grid bathymetry
- see [create_meshmask.f90](#) to create mesh mask or domain_cfg file.
- see [create_restart.f90](#) to create initial state file, or other fields.
- see [create_boundary.F90](#) to create boundary condition

- [Download](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Coding Rules](#)
- [Change log](#)
- [Todo List](#)

Chapter 2

Download

Download NEMO

to install SIREN, you should first download NEMO. see [NEMO quick start guide](#)

Compile SIREN

when NEMO is installed, you just have to compile SIREN codes:

1. go to `./NEMOGCM/TOOLS`
2. run maketools (ex: `./maketools -n SIREN -m ifort_mpi_beaufix`)

Note

to get help on maketools: `./maketools -h`

Fortran Compiler

SIREN codes were successfully tested with :

- ifort (version 15.0.1)
- gfortran (version 4.8.2 20140120)
- [About](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Coding Rules](#)
- [Change log](#)
- [Todo List](#)

Chapter 3

How To Use (Quick Start)

SIREN is a software to set up regional configuration with [NEMO](#).

Actually SIREN creates all the input files you need to run a NEMO regional configuration.

SIREN is composed of a set of 6 Fortran programs :

- [create_coord.f90](#) to create regional grid coordinates.
- [create_bathy.f90](#) to create regional grid bathymetry.
- [merge_bathy.f90](#) to merge regional grid bathymetry with wider grid bathymetry at boundaries.

Note

the goal of this step is to avoid break in Bathymetry. This break may cause inconsistency between forcing fields at boundary and regional fields.

- [create_meshmask.f90](#) to create meshmask or domain_cfg [file\(s\)](#) which contain(s) all the ocean domain informations.
- [create_restart.f90](#) to create initial state file from coarse grid restart or standard outputs.

Note

this program could also be used to refined other input fields from a wider configurations (as runoff, chlorophyll etc...)

- [create_boundary.F90](#) to create boundaries conditions from wider configurations output fields.

Warning

SIREN can not:

- create global configuration.
- create configuration around or close to North pole.
- change number of vertical level.

Here after we briefly describe how to use each programs, and so how to create your own regional configuration.

Note

As demonstrator for a first start a set of GLORYS files (global reanalysis on *ORCA025* grid), as well as examples of namelists are available [here](#).

3.1 Create coordinates file

To create your own configuration, you first have to create a coordinates file on your domain of study.

SIREN allows you to create this coordinates file from a wider coordinates file.

The coordinates file created could simply be an extraction, or a refinement of the wide grid.

To create this new coordinates file, you have to run :

```
./SIREN/create_coord.exe create_coord.nam
```

Here after is an example of namelist for *create_coord.exe*.

In this example, you create a coordinates file named *coord_fine.nc*.

This new coordinates file is refined from an extraction of *coordinates_ORCA025.nc*.

```
&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namcrs
  cn_coord0 = "PATH/coordinates_ORCA025.nc"
  in_perio0 = 4
/

&namvar
/

&namnst
  in_imin0 = 1070
  in_imax0 = 1072
  in_jmin0 = 607
  in_jmax0 = 609

  in_rhoi = 2
  in_rhoj = 3
/

&namout
  cn_fileout = "PATH/coord_fine.nc"
/
```

Let's get describe this namelist.

First we have the **namlog** sub-namelist. This sub-namelist set parameters of the log file.

All the parameters of this sub-namelist have default value, so you could let it empty, as done here.

This will create a log file named *create_coord.log*

The **namcfg** sub-namelist defines where found SIREN configuration files.

- The variable configuration file defines standard name, default interpolation method, axis,... to be used for some known variables.
Obviously, you could add other variables to those already list, in this file.
- The dimension configuration file defines dimensions allowed.

Note

You could find the generic version of those configuration files in the directory *NEMOGCM/TOOLS/SIREN/cfg*.

The **namcrs** sub-namelist set parameters of the wide coordinates file, as path to find it, and NEMO periodicity of the wide grid.

Note

the NEMO periodicity could be choose between 0 to 6:

in_perio=0 standard regional model

in_perio=1 east-west cyclic model

in_perio=2 model with symmetric boundary condition across the equator

in_perio=3 regional model with North fold boundary and T-point pivot

in_perio=4 global model with a T-point pivot.

example: ORCA2, ORCA025, ORCA12

in_perio=5 regional model with North fold boundary and F-point pivot

in_perio=6 global model with a F-point pivot

example: ORCA05

See Also

For more information see [NEMO periodicity](#)

The **namvar** sub-namelist lists variables to be used.

By default all the variables of the wider coordinates file are used to create the new coordinates file.

The interpolation methods to be used are defined in the configuration variables file (see below). So you do not need to fill this sub-namelist too.

The **namnst** sub-namelist defines the subdomain to be used as well as refinement factor.


Note

Subdomain is defined by indices of the coarse/wide grid.

- you can select area quite every where (excepted too close from the North pole), and use the refinement factor you want.

```
&namvar
  in_imin0 = 1070
  in_imax0 = 1072
  in_jmin0 = 607
  in_jmax0 = 609

  in_rhoi = 2
  in_rhoj = 3
/
```



- you can select area crossing the east-west overlap of the global ORCA grid.

```

&namvar
  in_imin0 = 1402
  in_imax0 = 62
  in_jmin0 = 490
  in_jmax0 = 570

  in_rhoi = 5
  in_rhoj = 5
/

```



- you can select east-west cyclic area.

```

&namvar
  in_imin0 = 0
  in_imax0 = 0
  in_jmin0 = 390
  in_jmax0 = 450

  in_rhoi = 1
  in_rhoj = 1
/

```



Finally the **namout** sub-namelist defines the output file.

Note

All the output files created by SIREN include information about NEMO periodicity, as well as source file, indices and refinement used.

See Also

For more information about how to create coordinates, see [create_coord.f90](#)

3.2 Create bathymetry file

Then you need a Bathymetry file.

SIREN allows you to create a Bathymetry extracted or refined from a wider Bathymetry grid.

To create this new bathymetry, you have to run :

```
./SIREN/create_bathy.exe create_bathy.nam
```

Here after is an example of namelist for *create_bathy.exe*.

In this example, you create a bathymetry file named *bathy_fine.nc*.

This new bathymetry file is refined from an extraction of *bathy_meter_ORCA025.nc*.

Moreover a minimum value of 5m is imposed to the output Bathymetry.

```
&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namcrs
  cn_coord0 = "PATH/coordinates_ORCA025.nc"
  in_perio0 = 4
/

&namfin
  cn_coord1 = "PATH/coord_fine.nc"
/

&namvar
  cn_varfile = "Bathymetry:PATH/bathy_meter_ORCA025.nc"
  cn_varinfo = "Bathymetry: min=5"
/

&namnst
  in_rhoi = 2
  in_rhoj = 3
/

&namout
  cn_fileout = "PATH/bathy_fine.nc"
/
```

Let's get describe this namelist.

First as previously, we have the **namlog** and **namcfg** sub-namelist (see above for more explanation).

Then the **namcrs** sub-namelist set parameters of the wide coordinates file.

Note

in all SIREN namelist:

0 referred to the coarse/wide grid.

1 referred to the fine grid.

In the same way, the **namfin** sub-namelist set parameters of the fine coordinates file.

Note

in this namelist example, there is no need to set the variable *in_perio1* to define the NEMO periodicity of the fine grid. Indeed, if this variable is not inform, SIREN tries to read it in the global attributes of the file. So if you created the fine coordinates with SIREN, you do not have to fill it. In other case, you should add it to the namelist.

The **namvar** sub-namelist lists variables to be used:

cn_varfile defines the variable name ("Bathymetry" here) and the input file associated with.

Warning

The domain of the input Bathymetry have to be larger than the output domain.

Note

- if the input file is at coarse grid resolution (same than *cn_coord0*), the ouptut Bathymetry will be refined on fine grid.
- if the input file is a wider bathymetry (already at fine grid resolution), the output Bathymetry will be extracted from this one.

cn_varinfo defines user's requests for a variable.

Note

Default interpolation method for the Bathymetry, is *cubic* interpolation.

So you may want to specify a minimum value to avoid negative value, or to change interpolation method.

example:

- `cn_varinfo="Bathymetry: min=1"`
- `cn_varinfo="Bathymetry: int=linear"`

The **namnst** sub-namelist defines the subdomain refinement factor.

Of course those refinement factors have to be convenient with refinement from coarse grid *cn_coord0* to fine grid *cn_coord1*.

Note

subdomain indices are automatically deduced from fine and coarse grid coordinates.

Finally, this **namout** sub-namelist defines the output file.

Note

All the output files create by SIREN include information about source file, indices, refinement and interpolation method used.

See Also

For more information about how to create bathymetry, see [create_bathy.f90](#)

3.3 Merge bathymetry file

The Bathymetry you build, may differ from the wider one.

To avoid issue with boundaries forcing fields, you should merge fine and coarse Bathymetry on boundaries.

SIREN allows you to do this.

To create this merged bathymetry, you have to run :

```
./SIREN/merge_bathy.exe merge_bathy.nam
```

Here after is an example of namelist for *merge_bathy.exe*.

```
&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namcrs
```



```

cn_bathy0 = "PATH/bathy_meter_ORCA025.nc"
in_perio0 = 4
/

&namfin
cn_bathy1 = "PATH/bathy_fine.nc"
/

&namnst
in_rhoi = 3
in_rhoj = 3
/

&nambdy
/

&namout
cn_fileout = "PATH/bathy_merged.nc"
/

```

In this namelist, you find again the **namlog**, **namcfg** describe above.

Then the **namcrs** sub-namelist sets parameters of the wider grid. However this time, this is the coarse/wide grid Bathymetry wich have to be informed.

The **namfin** sub-namelist defines parameters of the fine grid Bathymetry.

Note

here again you could add the *in_perio1* parameter if need be i.e. if your fine grid Bathymetry was not created by SIREN.

The **namnst** sub-namelist defines the subdomain refinement factor.

The **nambdy** sub-namelist defines the subdomain boundaries.

By default SIREN tries to create boundaries for each side. Boundary exist if there is at least one sea point on the second row of each side. So you could let this namelist empty.

See Also

For more information about boundaries, see [Create boundaries conditions](#)

Finally, this **namout** sub-namelist defines the output file.

See Also

For more information about how to merge bathymetry, see [merge_bathy.f90](#)

3.4 Create meshmask (ocean domain informations)

Depending on the vertical grid you choose to use, NEMO may not see the bathymetry exactly as you defined it just before. To get the ocean domain informations as seen by NEMO, SIREN allows you to create the meshmask [file\(s\)](#) which contain(s) all those informations.

Moreover SIREN allows you to create the *domain_cfg* file which is the new input file for NEMO (release 3.7 and upper).

To create the meshmask [file\(s\)](#), you have to run :

```
./SIREN/create_meshmask.exe create_meshmask.nam
```

Here after is an example of namelist for *create_meshmask.exe*.

In this example, you create one meshmask file named *mesh_mask.nc*.

It uses coordinates file *coord_fine.nc* to define horizontal grid. and defines z-coordinate with partial steps. The minimum depth of the final Bathymetry is 10m.

```

&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namin
  cn_bathy = "PATH/bathy_merged.nc"
  cn_coord = "PATH/coord_fine.nc"
  in_perio = 4
/

&namhgr
  in_mshhgr = 0
/

&namzgr
  ln_zps = .TRUE.
  in_nlevel= 75
/

&namdmin
  dn_hmin=10.
/

&namzco
  dn_ppsur = -3958.951371276829
  dn_ppa0 = 103.953009600000
  dn_ppa1 = 2.415951269000
  dn_ppkth = 15.351013700000
  dn_ppacr = 7.000000000000
  dn_ppdzmin = 6.
  dn_pphmax = 5750.
  ln_dbletanh= .TRUE.
  dn_ppa2 = 100.760928500000
  dn_ppkth2 = 48.029893720000
  dn_ppacr2 = 13.000000000000
/

&namzps
  dn_e3zps_min = 25.
  dn_e3zps_rat = 0.2
/

&namsco
/

&namlbc
/

&namwd
/

&namgrd
/

&namout
  in_msh = 1
/

```

Let's get describe this namelist more accurately.

As previously, we have the **namlog** and **namcfg** describe above.

The **namin** sub-namelist defines the Bathymetry to be used. Mainly SIREN need Bathymetry to create meshmask. Here we also read coordinates directly on a file.

Note

1. here again you could add the *in_perio* parameter if need be i.e. if your Bathymetry was not created by SIREN.
2. by default SIREN suppress closed sea/lake from the ORCA domain.

The **namhgr** sub-namelist defines the horizontal grid. the type of horizontal mesh is choose between :

- *in_mshhgr=0* : curvilinear coordinate on the sphere read in coordinate.nc
- *in_mshhgr=1* : geographical mesh on the sphere with regular grid-spacing

- `in_mshhgr=2` : f-plane with regular grid-spacing
- `in_mshhgr=3` : beta-plane with regular grid-spacing
- `in_mshhgr=4` : Mercator grid with T/U point at the equator
- `in_mshhgr=5` : beta-plane with regular grid-spacing and rotated domain (GYRE configuration)

The **namzgr** sub-namelist allows to choose the type of vertical grid (z-coordinate full steps, partial steps, sigma or hybrid coordinates) and the number of level.

The **namdmin** sub-namelist defines the minimum ocean depth. It could be defines in meter (>0) or in number of level (<0).

The **namzco** sub-namelist defines parameters to compute z-coordinate vertical grid (**needed for all type of vertical grid**)

The **namzps** sub-namelist defines extra parameters needed to define z-coordinates partial steps.

The **namSCO** sub-namelist defines extra parameters needed to define sigma or hybrid coordinates (not needed here).

The **namlbc** sub-namelist defines lateral boundary conditions at the coast. It is needed to modify the `fmask`.

The **namwd** sub-namelist defines the wetting and drying parameters if activated (see `namzgr` sub-namelist)

The **namgrd** sub-namelist allows to use configuration 1D or to choose vertical scale factors (`e3.=dk` or old definition).

Finally, this **namout** sub-namelist defines the number output [file\(s\)](#).

Note

To create the `domain_cfg` file, you should put **`in_msh=0`**.

See Also

For more information about how to create `meshmask`, see [create_meshmask.f90](#)

3.5 Create initial state

To run your configuration you need an initial state of the ocean.

You could start from a restart file (with all NEMO variables fields at one time step). Or you could start from "partial" information about ocean state (Temperature and Salinity for example).

SIREN allows you to create both of those initial state.

To create the initial state, you have to run:

```
./SIREN/create_restart.exe create_restart.nam
```

Here after is an example of namelist for `create_restart.exe`.

In this example, you create an initial state split on 81 "processors", and named `restart_out.nc`.

The initial state is composed of temperature and salinity refined from an extraction of GLORYS fields.

```
&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namcrs
  cn_coord0 = "PATH/coordinates_ORCA025.nc"
  in_perio0 = 4
```

```

/
&namfin
  cn_coord1 = "PATH/coord_fine.nc"
  cn_bathyl = "PATH/bathy_merged.nc"
/
&namzgr
/
&namzps
/
&namvar
  cn_varfile = "votemper:GLORYS_gridT.nc",
              "vosaline:GLORYS_gridS.nc"
/
&namnst
  in_rhoi = 3
  in_rhoj = 3
/
&namout
  cn_fileout = "PATH/restart_out.nc"
  in_nproc = 81
/

```

Let's get describe this namelist more accurately.

As previously, we have the **namlog** and **namcfg** sub-namelist, as well as the **namcrs** sub-namelist to set parameters of the wide coordinates file (see above for more explanation).

Then the **namfin** sub-namelist set parameters of the fine grid coordinates and bathymetry.

The **namzgr** and **namzps** sub-namelist define respectively parameters for vertical grid and partial step.

By default, those parameters are defined the same way than in GLORYS (i.e. 75 vertical levels).

So you could let it empty.

Note

If you use forcing fields other than GLORYS, you have to be sure it uses the same vertical grid. In other case, you need to get information about the parametrisation use, and to put it in those sub-namelist (see [create_restart.f90](#)).

the **namvar** sub-namelist lists variables to be used.

Here we use *votemper* (temperature) get from *GLORYS_gridT.nc* file, and *vosaline* (salinity) get from *GLORYS_gridS.nc* file.

Note

To get all variables of a restart file. You have to use:

```
cn_varfile = "all:PATH/restart.dimg"
```

The **namnst** sub-namelist defines the subdomain refinement factor, as seen previously.

Finally, this **namout** sub-namelist defines the output files.

Here we ask for output on 81 processors, with *restart_out.nc* as file "basename".

So SIREN computes the optimal layout for 81 processors available,

and split restart on output files named *restart_out_num.nc*, where *num* is the proc number.

Note

SIREN could also create the other fields you may need for your configuration.

To do so, you just have to run *create_restart.exe* with other variable(s) from other input [file\(s\)](#).

For example, to get runoff fields, you could use:

```
cn_varfile = "sorunoff:PATH/runoff_GLORYS.nc"
...
cn_fileout = "PATH/runoff_out.nc"
```

See Also

For more information about how to create initial state or other fields, see [create_restart.f90](#)

3.6 Create boundaries conditions

Finally to force your configuration, you may need boundaries conditions.

NEMO read physical boundaries conditions from temperature, salinity, currents, and sea surface height.

To create the boundaries condition with SIREN, you have to run:

```
./SIREN/create_boundary.exe create_boundary.nam
```

Here after is an example of namelist for *create_boundary.exe*.

In this example, you create boundaries conditions named *boundary_out.nc* on each side of the domain.

The boundaries contain information about temperature, salinity, currents and sea surface height refined from an extraction of GLORYS fields.

```
&namlog
/

&namcfg
  cn_varcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/variable.cfg"
  cn_dimcfg = "PATH/NEMOGCM/TOOLS/SIREN/cfg/dimension.cfg"
/

&namcrs
  cn_coord0 = "PATH/coordinates_ORCA025.nc"
  in_perio0 = 4
/

&namfin
  cn_coord1 = "PATH/coord_fine.nc"
  cn_bathyl = "PATH/bathy_fine.nc"
/

&namzgr
/

&namzps
/

&namvar
  cn_varfile="votemper:GLORYS_gridT.nc",
             "vosaline:GLORYS_gridS.nc",
             "vozocrtx:GLORYS_gridU.nc",
             "vomecrty:GLORYS_gridV.nc",
             "sossheig:GLORYS_grid2D.nc"
/

&namnst
  in_rhoi = 3
  in_rhoj = 3
/

&nambdy
/

&namout
  cn_fileout = "PATH/boundary_out.nc"
/
```

Let's get describe this namelist more accurately.

As previously, we have the **namlog** and **namcfg** sub-namelist, as well as the **namcrs** sub-namelist to set parameters of the wide coordinates file (see above for more explanation).

Then the **namfin** sub-namelist set parameters of the fine grid coordinates and bathymetry.

The **namzgr** and **namzps** sub-namelists define respectively parameters for vertical grid and partial step.

By default, those parameters are defined the same way than in GLORYS (i.e. 75 vertical levels).

So you could let it empty.

Note

If you use forcing fields other than GLORYS, you have to be sure it uses the same vertical grid. In other case, you need to get information about the parametrisation use, and to put it in those sub-namelist (see [create_boundary.F90](#)).

the **namvar** sub-namelist lists variables to be used.

Here we get *votemper* (temperature) from *GLORYS_gridT.nc* file, *vosaline* (salinity) from *GLORYS_gridS.nc* file, *vozocrtx* (zonal velocity) from *GLORYS_gridU.nc*, *vomecrtx* (meridional velocity) from *GLORYS_gridV.nc*, and *sossheig* (sea surface height) from *GLORYS_grid2D.nc*.

The **namnst** sub-namelist defines the subdomain refinement factor.

The **nambdy** sub-namelist defines the subdomain boundaries.

By default SIREN tries to create boundaries for each side (Boundary is created if sea point exist on the second row of each side).

So you could let this namelist empty.

Note

SIREN allows you to place boundaries away from the side of the domain. To do so you have to define your boundary.

That means you have to give on fine grid the index of the boundary (how far from the border your boundary is), the width of your boundary, and finally first and last point of your boundary (the length of your boundary).

So to define a north boundary, you have to add in the sub-namelist *nambdy*, the parameter:

```
cn_north="index,first:last (width) "
```

Finally, this **namout** sub-namelist defines the output files.

Here we ask for output with *boundary_out.nc* as file "basename".

So SIREN creates output files named *boundary_out_west.nc*, *boundary_out_east.nc*, *boundary_out_north.nc*, and *boundary_out_south.nc* depending if boundary exist or not.

See Also

For more information about how to create boundaries condition, see [create_boundary.F90](#)

3.7 Create and run NEMO configuration

So now you created all the input files you need for your physical configuration, you have to create the "NEMO configuration".

To do so, go to the directory *NEMOGCM/CONFIG/*, and run:

```
./makenemo -n MY_CONFIG -d "OPA_SRC"
```

This creates your configuration "MY_CONFIG" in the directory *NEMOGCM/CONFIG/*.

you could check the *cpp_keys* used in file *cpp_MY_CONFIG.fcm*, and re-run *makenemo* if need be.

Once *makenemo* has run successfully, the *opa* executable is available in directory *NEMOGCM/CONFIG/MY_CONFIG/EXP00*.

Then you just have to put all your input files in this directory, fill the namelist *namelist_cfg*, and run:

```
mpirun ./opa
```

Note

no surface forcing here. weighted function needed to do interpolation on the fly, could be created by WEIGHT tools already inside NEMO.

See Also

For more information about how to create NEMO configuration see [NEMO Quick Start Guide](#).

- [About](#)
- [Download](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Coding Rules](#)
- [Change log](#)
- [Todo List](#)

Chapter 4

Support

How to get support

If you have questions regarding the use of SIREN, please have a look at the [NEMO configuration manager forum](#).

If you don't find an answer in the archives, feel free to register and post your question.

How to Help

The development of SIREN highly depends on your input!

If you are trying SIREN let me know what you think of it (do you miss certain features?). Even if you decide not to use it, please let me know why.

How to report a bug

If you believe you have found a new bug, please report it.

Before submitting a new bug, first search through the database if the same bug has already been submitted by others

If you send only a (vague) description of a bug, you are usually not very helpful and it will cost much more time to figure out what you mean. In the worst-case your bug report may even be completely ignored.

- [About](#)
- [Download](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Coding Rules](#)
- [Change log](#)
- [Todo List](#)

Chapter 5

Coding Rules

The conventions used in SIREN coding are based on the NEMO coding rules (see [NEMO coding conventions](#)).

However some modifications were added to improve readability of the code.

Some of the NEMO coding rules are reminded here, and extensions are described.

5.1 Fortran Standard

SIREN software adhere to strict **FORTRAN 95** standard.

There is only one exception. The use of functions *COMMAND_ARGUMENT_COUNT* and *GET_COMMAND_ARGUMENT*.

There exist no equivalent for those Fortran 03 intrinsic functions in Fortran 95.

At least none convenient for compilers tested (see [Download](#)).

5.2 Free Form Source

Free Form Source will be used, however a self imposed limit of 80 should enhance readability.

5.3 Indentation

Code as well as comments lines will be indented 3 characters for readability.

Indentation should be write without hard tabs.

Example for vi :

```
:set expandtab tabstop=3 shiftwidth=3
```

5.4 Naming conventions : variable

All variables should be named as explicitly as possible.

The naming conventions concerns prefix letters of these name, in order to identify the variable type and status.

It must be composed of two letters defining type and status follow by an underscore.

table below list the starting letters to be used for variable naming, depending on their type and status.

Type / Status	byte (integer(1)) b	short (integer(2)) s	integer(4) i	integer(8) k	real(4) r	real(8) d	logical l	character c	complex y	structure t
global g	bg_	sg_	ig_	kg_	rg_	dg_	lg_	cg_	yg_	tg_
global parameter p	bp_	sp_	ip_	kp_	rp_	dp_	lp_	cp_	yp_	tp_
module m	bm_	sm_	im_	km_	rm_	dm_	lm_	cm_	ym_	tm_
namelist n	bn_	sn_	in_	kn_	rn_	dn_	ln_	cn_	yn_	tn_
dummy argument d	bd_	sd_	id_	kd_	rd_	dd_	ld_	cd_	yd_	td_
local l	bl_	sl_	il_	kl_	rl_	dl_	ll_	cl_	yl_	tl_
loop control			j?							

5.5 Naming conventions : structure

The structure name should be written in capital letter, and start with **T**

Example: TTRACER

Variables inside the structure should be named as explicitly as possible.

For those variables, the prefix naming conventions only concern the type of variable.

It must be composed of one letter defining type follows by an underscore.

see table of variable conventions.

Example: **tl_type%i_year**

year is an integer(4) variable in a local structure named *type*.

5.6 Naming conventions : function-subroutine

Functions or Subroutines are defined in a module.

Their name should start with the module name then with their "functional" name. So it will be easy to find it.

Example:

a function to realise addition written in a module **math** should be called **math_add**.

PUBLIC function or subroutine should used one underscore: *math_add*

PRIVATE function or subroutine should used two underscores: *math__add*

5.7 Precision

All variables should make use of kinds.

Numerical constant need to have a suffix of **kindvalue**

5.8 Declaration for global variable and constants

All global data must be accompanied with a comment field on the same line.

Note that using doxygen (see [header](#)), we will use symbol !< instead of !: as separator

5.9 Implicit none

All subroutines and functions will include an IMPLICIT NONE statement.

5.10 Header

SIREN use **doxygen auto documentation** tool.

Information could be find on [doxygen](#) web page.

Some basic tag are described [here](#).

- [About](#)
- [Download](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Change log](#)
- [Todo List](#)

Chapter 6

Change log

Release ()

New Features

- [create_meshmask.f90](#) program to create meshmask from coordinates and bathymetry files.
- [create_meshmask.f90](#) allows to write domain_cfg file.
- [merge_bathy.f90](#): allow to choose the number of boundary point with coarse grid value.
- [dimension.f90](#): dimension allowed read in configuration file.
- [variable.f90](#): allow to add scalar value.
- [create_meshmask.f90](#): choose vertical scale factors (e3.=dk[depth] or old definition).

Changes

- [create_coord.f90](#): allow to define sub domain with coarse grid indices or coordinates.
- [grid.f90:grid__get_closest_str](#): add function to get closest grid point using coarse grid coordinates structure.
- [iom_cdf.f90:iom_cdf__get_info](#): define cdf4 as cdf.
- [variable.f90](#): add subroutine to clean global array of extra information, and define logical for variable to be used.
- [create_coord.f90](#): dimension to be used select from configuration file.
- [create_bathy.f90](#): dimension to be used select from configuration file.
- [merge_bathy.f90](#): dimension to be used select from configuration file.
- [create_boundary.f90](#): dimension to be used select from configuration file.
- [create_restart.f90](#): dimension to be used select from configuration file.

Bug fixes

- [boundary.f90:boundary_check](#): take into account that boundaries are compute on T point, but expressed on U,V point.
- [grid.f90:grid__get_closest_str](#): use max of zero and east-west overlap instead of east-west overlap.
- [mpp.f90](#): compare index to td_lay number of proc instead of td_mpp (bug fix) .

Initial Release 2016-03-17


- [About](#)
- [Download](#)
- [How To Use \(Quick Start\)](#)
- [Support](#)
- [Coding Rules](#)
- [Todo List](#)

Chapter 7


NEMO periodicity

NEMO periodicity is defined as follow :


closed boundary (in_perio=0) ghost cells (solid walls) are imposed at all model boundaries.




cyclic east-west boundary (in_perio=1) first and last rows are closed, whilst the first column is set to the value of the last-but-one column and the last column to the value of the second one.




symmetric boundary condition across the equator. (in_perio=2) last row, and first and last columns are closed.




North fold boundary with a T-point pivot (in_perio=3) first row, and first and last columns are closed.




North fold boundary with a T -point pivot and cyclic east-west boundary (in_perio=4) first row is closed. The first column is set to the value of the last-but-one column and the last column to the value of the second one.



North fold boundary with a F -point pivot (in_perio=5) first row, and first and last columns are closed.



North fold boundary with a F -point pivot and cyclic east-west boundary (in_perio=6) first row is closed. The first column is set to the value of the last-but-one column and the last column to the value of the second one.



See Also

For more information about NEMO periodicity, see *Model Boundary Condition* chapter in [NEMO documentation](#))

Chapter 8

Todo List

Type **boundary**

add schematic to boundary structure description

Subprogram **create_bathy**

check tl_multi is not empty

Subprogram **create_boundary**

rewrite using meshmask instead of bathymetry and coordinates files.

Subprogram **create_coord_interp** (td_var, id_rho, id_offset, id_iext, id_jext)

check if mask is really needed

Subprogram **create_restart**

rewrite using meshmask instead of bathymetry and coordinates files

Type **date**

see calendar.f90 and select Gregorian, NoLeap, or D360 calendar

Type **extrap**

create module for each extrapolation method

- smooth extrapolated points

Subprogram **extrap::extrap_add_extrabands** (td_var, id_isize, id_jsize)

invalid special case for grid with north fold

Type **iom**

see lbc_ink

- see goup netcdf4

Type **kind**

check i8 max value

Subprogram **vgrid::vgrid_zgr_bat** (dd_bathy, dd_gdepw, dd_hmin, dd_fill)

add subroutine description

Chapter 9

Class Index

9.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

att		
	This module manage attribute of variable or file	37
att::att_clean	41
att::att_copy	41
att::att_init	43
att::att_print	49
boundary		
	This module manage boundary	50
boundary::boundary_clean	56
boundary::boundary_copy	56
boundary::boundary_init	58
boundary::boundary_print	59
date		
	This module provide the calculation of Julian dates, and do many manipulations with dates	60
date::date_init	64
dim		
	This module manage dimension and how to change order of those dimension	66
dim::dim_clean	74
dim::dim_copy	75
dim::dim_print	76
dim::dim_reorder_2xyzt	77
dim::dim_reorder_xyzt2	79
dim::dim_reshape_2xyzt	81
dim::dim_reshape_xyzt2	81
dom		
	This module manage domain computation	82
dom::dom_copy	88
dom::dom_init	89
extrap		
	This module manage extrapolation	90
extrap::extrap_detect	93
extrap::extrap_fill_value	94
fct		
	This module groups some basic useful function	95
fct::fct_str	102
file		
	This module manage file structure	105
file::file_clean	114

file::file_copy	115
file::file_del_att	116
file::file_del_var	117
file::file_rename	118
filter	
This module is filter manager	119
filter::filter_fill_value	121
global	
This module defines global variables and parameters	121
grid	
This module is grid manager	123
grid::grid_get_closest	132
grid::grid_get_coarse_index	134
grid::grid_get_ew_overlap	137
grid::grid_get_fine_offset	139
grid::grid_get_ghost	143
grid::grid_get_info	144
grid::grid_get_perio	145
grid::grid_get_pivot	147
grid_hgr	
This module manage Horizontal grid	149
grid_zgr	
This module manage Vertical grid	153
interp	
This module manage interpolation on regular grid	159
interp_cubic	
This module manage cubic interpolation on regular grid	162
interp::interp_detect	163
interp::interp_fill_value	164
interp_linear	
This module manage linear interpolation on regular grid	165
interp_nearest	
This module manage nearest interpolation on regular grid	166
iom	
Input/Output manager : Library to read input files	167
iom_cdf	
NETCDF Input/Output manager : Library to read Netcdf input files	171
iom_cdf::iom_cdf_fill_var	174
iom_cdf::iom_cdf_read_att	175
iom_cdf::iom_cdf_read_dim	176
iom_cdf::iom_cdf_read_var	177
iom_dom	
This module allow to read domain (defined as domain structure) in a mpp files	179
iom_dom::iom_dom_read_var	180
iom_mpp	
This module manage massively parallel processing Input/Output manager. Library to read/write mpp files	181
iom_mpp::iom_mpp_read_var	185
iom::iom_read_att	186
iom::iom_read_dim	189
iom::iom_read_var	190
iom_rstdimg	
This module is a library to read/write dimg file	191
iom_rstdimg::iom_rstdimg_read_dim	195
iom_rstdimg::iom_rstdimg_read_var	196
kind	
This module defines the F90 kind parameter for common data types	197

<code>lbc</code>		
	This module groups lateral boundary conditions subroutine	198
<code>lbc::lbc__hide_nfd</code>		199
<code>lbc::lbc_hide</code>		199
<code>lbc::lbc_lnk</code>		200
<code>lbc::lbc_nfd</code>		201
<code>logger</code>		
	This module manage log file	202
<code>math</code>		
	This module groups some useful mathematical function	209
<code>math::math_mean</code>		214
<code>math::math_median</code>		215
<code>math::math_mwe</code>		216
<code>mpp</code>		
	This module manage massively parallel processing	217
<code>mpp::mpp_add_proc</code>		227
<code>mpp::mpp_check_dim</code>		228
<code>mpp::mpp_del_proc</code>		229
<code>mpp::mpp_clean</code>		230
<code>mpp::mpp_copy</code>		231
<code>mpp::mpp_del_att</code>		233
<code>mpp::mpp_del_var</code>		234
<code>mpp::mpp_get_use</code>		235
<code>mpp::mpp_init</code>		235
<code>multi</code>		
	This module manage multi file structure	238
<code>multi::multi_copy</code>		241
<code>date::operator(+)</code>		242
<code>date::operator(-)</code>		243
<code>fct::operator(/)</code>		244
<code>phycst</code>		
	This module defines physical constant	247
<code>boundary::seg_clean</code>		248
<code>boundary::seg_copy</code>		249
<code>att::tatt</code>		250
<code>boundary::tbody</code>		
	Boundary structure	251
<code>date::tdate</code>		251
<code>dim::tdim</code>		252
<code>dom::tdom</code>		252
<code>file::tfile</code>		253
<code>interp::tinterp</code>		255
<code>mpp::tlay</code>		
	Domain layout structure	255
<code>logger::tlogger</code>		256
<code>mpp::tmpp</code>		257
<code>multi::tmulti</code>		257
<code>grid_hgr::tnamh</code>		258
<code>grid_zgr::tnamz</code>		258
<code>boundary::tseg</code>		259
<code>var::tvar</code>		259
<code>var</code>		
	This module manage variable structure	261
<code>var::var_add_att</code>		276
<code>var::var_add_dim</code>		277
<code>var::var_add_value</code>		278
<code>var::var_clean</code>		282
<code>var::var_copy</code>		284

var::var_del_att	285
var::var_init	286
var::var_print	326
vgrid	
This module manage vertical grid	327

Chapter 10

File Index

10.1 File List

Here is a list of all documented files with brief descriptions:

src/create_bathy.f90	This program creates fine grid bathymetry file	335
src/create_boundary.F90	This program creates boundary files	341
src/create_coord.f90	This program creates fine grid coordinate file	350
src/create_meshmask.f90	This program creates the NetCDF file(s) which contain(s) all the ocean domain informations. It allows to create the domain_cfg.nc file needed to run NEMO, or the mesh_mask file(s)	353
src/create_restart.f90	This program creates restart file	360
src/merge_bathy.f90	This program merges bathymetry file at boundaries	366

Chapter 11

Class Documentation

11.1 att Module Reference

This module manage attribute of variable or file.

Data Types

- interface [att_clean](#)
- interface [att_copy](#)
- interface [att_init](#)
- interface [att_print](#)
- type [tatt](#)

Public Member Functions

- INTEGER(i4) function, public [att_get_index](#) (td_att, cd_name)
This function return attribute index, in a array of attribute structure, given attribute name.
- INTEGER(i4) function, public [att_get_id](#) (td_att, cd_name)
This function return attribute id, read from a file.
- subroutine, public [att_get_dummy](#) (cd_dummy)
This subroutine fill dummy attribute array.
- logical function, public [att_is_dummy](#) (td_att)
This function check if attribute is defined as dummy attribute in configuraton file.

11.1.1 Detailed Description

This module manage attribute of variable or file.

```
define type TATT:<br/>
```

```
TYPE(tatt) :: tl_att
```

the attribute value inside attribute structure will be character or real(8) 1D array.

However the attribute value could be initialized with:

- character
- scalar (real(4), real(8), integer(4) or integer(8))

- array 1D (real(4), real(8), integer(4) or integer(8))

to initialize an attribute structure :

```
t1_att=att_init('attname',value)
```

- value is a character, scalar value or table of value

to print attribute information of one or array of attribute structure:

```
CALL att_print(td_att)
```

to clean attribute structure:

```
CALL att_clean(td_att)
```

to copy attribute structure in another one (using different memory cell):

```
t1_att2=att_copy(t1_att1)
```

Note

as we use pointer for the value array of the attribute structure, the use of the assignment operator (=) to copy attribute structure create a pointer on the same array. This is not the case with this copy function.

to get attribute index, in an array of attribute structure:

```
il_index=att_get_index( td_att, cd_name )
```

- td_att array of attribute structure
- cd_name attribute name

to get attribute id, read from a file:

```
il_id=att_get_id( td_att, cd_name )
```

- td_att array of attribute structure
- cd_name attribute name

to get attribute name

- t1_att%c_name

to get character length or the number of value store in attribute

- t1_att%i_len

to get attribute value:

- t1_att%c_value (for character attribute)
- t1_att%d_value(i) (otherwise)

to get the type number (based on NETCDF type constants) of the attribute:

- t1_att%i_type

to get attribute id (read from file):

- t1_att%i_id

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- Fix memory leaks bug

September, 2015

- manage useless (dummy) attributes

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.1.2 Member Function/Subroutine Documentation**11.1.2.1 subroutine, public att::att_get_dummy (character(len=*), intent(in) *cd_dummy*)**

This subroutine fill dummy attribute array.

Author

J.Paul

Date

September, 2015 - Initial Version

Marsh, 2016

- close file (bugfix)

Parameters

<i>in</i>	<i>cd_dummy</i>	dummy configuration file
-----------	-----------------	--------------------------

11.1.2.2 INTEGER(i4) function, public att::att_get_id (type(tatt), dimension(:), intent(in) *td_att*, character(len=*), intent(in) *cd_name*)

This function return attribute id, read from a file.

if attribute name do not exist, return 0.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- bug fix with use of id read from attribute structure

Parameters

in	<i>td_att</i>	array of attribute structure
in	<i>cd_name</i>	attribute name

Returns

attribute id

11.1.2.3 INTEGER(i4) function, public att::att_get_index (type(tatt), dimension(:), intent(in) *td_att*, character(len=*) , intent(in) *cd_name*)

This function return attribute index, in a array of attribute structure, given attribute name.

if attribute name do not exist, return 0.

Author

J.Paul

Date

Septempber, 2014 - Initial Version

Parameters

in	<i>td_att</i>	array of attribute structure
in	<i>cd_name</i>	attribute name

Returns

attribute index

11.1.2.4 logical function, public att::att_is_dummy (type(tatt), intent(in) *td_att*)

This function check if attribute is defined as dummy attribute in configuraton file.

Author

J.Paul

Date

September, 2015 - Initial Version

Parameters

in	<i>td_att</i>	attribute structure
----	---------------	---------------------

Returns

true if attribute is dummy attribute

The documentation for this module was generated from the following file:

- src/attribute.f90

11.2 att::att_clean Interface Reference

Public Member Functions

- subroutine [att_clean_unit](#) (td_att)
This subroutine clean attribute structure.
- subroutine [att_clean_arr](#) (td_att)
This subroutine clean array of attribute structure.

11.2.1 Member Function/Subroutine Documentation

11.2.1.1 subroutine att::att_clean::att_clean_arr (type(tatt), dimension(:), intent(inout) td_att)

This subroutine clean array of attribute structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in, out	td_att	attribute structure
---------	--------	---------------------

11.2.1.2 subroutine att::att_clean::att_clean_unit (type(tatt), intent(inout) td_att)

This subroutine clean attribute structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	td_att	attribute structure
---------	--------	---------------------

The documentation for this interface was generated from the following file:

- src/attribute.f90

11.3 att::att_copy Interface Reference

Public Member Functions

- type(tatt) function [att_copy_unit](#) (td_att)
This subroutine copy an attribute structure in another one.
- type(tatt) function, dimension(size(td_att(:))) [att_copy_arr](#) (td_att)
This subroutine copy a array of attribute structure in another one.

11.3.1 Member Function/Subroutine Documentation

11.3.1.1 `type(tatt)` function, `dimension(size(td_att(:)))` `att::att_copy::att__copy_arr (type(tatt), dimension(:), intent(in) td_att)`

This subroutine copy a array of attribute structure in another one.

see `att__copy_unit`

Warning

do not use on the output of a function who create or read an attribute (ex: `tl_att=att_copy(att_init())` is forbidden). This will create memory leaks.

to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_att</code>	array of attribute structure
-----------------	---------------------	------------------------------

Returns

copy of input array of attribute structure

11.3.1.2 `type(tatt)` function `att::att_copy::att__copy_unit (type(tatt), intent(in) td_att)`

This subroutine copy an attribute structure in another one.

attribute value are copied in a temporary array, so input and output attribute structure value do not point on the same "memory cell", and so on are independant.

Warning

do not use on the output of a function who create or read an attribute (ex: `tl_att=att_copy(att_init())` is forbidden). This will create memory leaks.

to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

in	<i>td_att</i>	attribute structure
----	---------------	---------------------

Returns

copy of input attribute structure

The documentation for this interface was generated from the following file:

- src/attribute.f90

11.4 att::att_init Interface Reference

Public Member Functions

- TYPE(TATT) function [att__init_c](#) (cd_name, cd_value)
This function initialize an attribute structure with character value.
- TYPE(TATT) function [att__init_dp](#) (cd_name, dd_value, id_type)
This function initialize an attribute structure with array of real(8) value.
- TYPE(TATT) function [att__init_dp_0d](#) (cd_name, dd_value, id_type)
This function initialize an attribute structure with real(8) value.
- TYPE(TATT) function [att__init_sp](#) (cd_name, rd_value, id_type)
This function initialize an attribute structure with array of real(4) value.
- TYPE(TATT) function [att__init_sp_0d](#) (cd_name, rd_value, id_type)
This function initialize an attribute structure with real(4) value.
- TYPE(TATT) function [att__init_i1](#) (cd_name, bd_value, id_type)
This function initialize an attribute structure with array of integer(1) value.
- TYPE(TATT) function [att__init_i1_0d](#) (cd_name, bd_value, id_type)
This function initialize an attribute structure with integer(1) value.
- TYPE(TATT) function [att__init_i2](#) (cd_name, sd_value, id_type)
This function initialize an attribute structure with array of integer(2) value.
- TYPE(TATT) function [att__init_i2_0d](#) (cd_name, sd_value, id_type)
This function initialize an attribute structure with integer(2) value.
- TYPE(TATT) function [att__init_i4](#) (cd_name, id_value, id_type)
This function initialize an attribute structure with array of integer(4) value.
- TYPE(TATT) function [att__init_i4_0d](#) (cd_name, id_value, id_type)
This function initialize an attribute structure with integer(4) value.
- TYPE(TATT) function [att__init_i8](#) (cd_name, kd_value, id_type)
This function initialize an attribute structure with array of integer(8) value.
- TYPE(TATT) function [att__init_i8_0d](#) (cd_name, kd_value, id_type)
This function initialize an attribute structure with integer(8) value.

11.4.1 Member Function/Subroutine Documentation

11.4.1.1 TYPE(TATT) function `att::att_init::att__init_c (character(len=*), intent(in) cd_name, character(len=*), intent(in) cd_value)`

This function initialize an attribute structure with character value.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>cd_value</i>	attribute value

Returns

attribute structure

11.4.1.2 **TYPE(TATT) function** `att::att_init::att__init_dp (character(len=*), intent(in) cd_name, real(dp), dimension(:), intent(in) dd_value, integer(i4), intent(in), optional id_type)`

This function initialize an attribute structure with array of real(8) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>dd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.3 **TYPE(TATT) function** `att::att_init::att__init_dp_0d (character(len=*), intent(in) cd_name, real(dp), intent(in) dd_value, integer(i4), intent(in), optional id_type)`

This function initialize an attribute structure with real(8) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>dd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.4 TYPE(TATT) function att::att_init::att_init_i1 (character(len=*), intent(in) *cd_name*, integer(i1), dimension(:), intent(in) *bd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with array of integer(1) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>bd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.5 TYPE(TATT) function att::att_init::att_init_i1_0d (character(len=*), intent(in) *cd_name*, integer(i1), intent(in) *bd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with integer(1) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
----	----------------	----------------

in	<i>bd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.6 **TYPE(TATT) function** `att::att_init::att__init_i2 (character(len=*), intent(in) cd_name, integer(i2), dimension(:), intent(in) sd_value, integer(i4), intent(in), optional id_type)`

This function initialize an attribute structure with array of integer(2) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>sd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.7 **TYPE(TATT) function** `att::att_init::att__init_i2_0d (character(len=*), intent(in) cd_name, integer(i2), intent(in) sd_value, integer(i4), intent(in), optional id_type)`

This function initialize an attribute structure with integer(2) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>sd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.8 TYPE(TATT) function att::att_init::att_init_i4 (character(len=*), intent(in) *cd_name*, integer(i4), dimension(:), intent(in) *id_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with array of integer(4) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>id_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.9 TYPE(TATT) function att::att_init::att_init_i4_0d (character(len=*), intent(in) *cd_name*, integer(i4), intent(in) *id_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with integer(4) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>id_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.10 TYPE(TATT) function att::att_init::att_init_i8 (character(len=*), intent(in) *cd_name*, integer(i8), dimension(:), intent(in) *kd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with array of integer(8) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>kd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.11 TYPE(TATT) function att::att_init::att_init_i8_0d (character(len=*), intent(in) *cd_name*, integer(i8), intent(in) *kd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with integer(8) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>kd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.12 TYPE(TATT) function att::att_init::att_init_sp (character(len=*), intent(in) *cd_name*, real(sp), dimension(:), intent(in) *rd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with array of real(4) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>rd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

11.4.1.13 **TYPE(TATT) function att::att_init::att_init_sp_0d** (character(len=*), intent(in) *cd_name*, real(sp), intent(in) *rd_value*, integer(i4), intent(in), optional *id_type*)

This function initialize an attribute structure with real(4) value.

Optionally you could specify the type of the variable to be saved.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_name</i>	attribute name
in	<i>rd_value</i>	attribute value
in	<i>id_type</i>	type of the variable to be saved

Returns

attribute structure

The documentation for this interface was generated from the following file:

- src/attribute.f90

11.5 att::att_print Interface Reference

Public Member Functions

- subroutine [att__print_unit](#) (td_att)
This subroutine print attribute information.
- subroutine [att__print_arr](#) (td_att)
This subroutine print informations of an array of attribute.

11.5.1 Member Function/Subroutine Documentation

11.5.1.1 subroutine [att::att_print::att__print_arr](#) (type(tatt), dimension(:), intent(in) *td_att*)

This subroutine print informations of an array of attribute.

Author

J.Paul

Date

June, 2014 - Initial Version

Parameters

in	<i>td_att</i>	array of attribute structure
----	---------------	------------------------------

11.5.1.2 subroutine att::att_print::att__print_unit (type(tatt), intent(in) *td_att*)

This subroutine print attribute information.

Author

J.Paul

Date

November, 2013 - Initial Version
September, 2014

- take into account type of attribute.

Parameters

in	<i>td_att</i>	attribute structure
----	---------------	---------------------

The documentation for this interface was generated from the following file:

- src/attribute.f90

11.6 boundary Module Reference

This module manage boundary.

Data Types

- interface [boundary_clean](#)
- interface [boundary_copy](#)
- interface [boundary_init](#)
- interface [boundary_print](#)
- interface [seg__clean](#)
- interface [seg__copy](#)
- type [tbody](#)
- *boundary structure*
- type [tseg](#)

Public Member Functions

- character(len=lc) function, public `boundary_set_filename` (cd_file, cd_card, id_seg, cd_date)
This function put cardinal name and date inside file name.
- subroutine, public `boundary_get_indices` (td_bdy, td_var, ld_oneseg)
This subroutine get indices of each segment for each boundary.
- subroutine, public `boundary_check_corner` (td_bdy, td_var)
This subroutine check if there is boundary at corner, and adjust boundary indices if necessary.
- subroutine, public `boundary_check` (td_bdy, td_var)
This subroutine check boundary.
- subroutine, public `boundary_swap` (td_var, td_bdy)
This subroutine swap array for east and north boundary.

11.6.1 Detailed Description

This module manage boundary.

```
define type TBDY:<br/>
```

```
TYPE(tbdy) :: tl_bdy<br/>
```

to initialise boundary structure:

```
tl_bdy=boundary_init(td_var, [ld_north,] [ld_south,] [ld_east,] [ld_west,]  
[cd_north,] [cd_south,] [cd_east,] [cd_west,] [ld_oneseg])
```

- td_var is variable structure
- ld_north is logical to force used of north boundary [optional]
- ld_south is logical to force used of north boundary [optional]
- ld_east is logical to force used of north boundary [optional]
- ld_west is logical to force used of north boundary [optional]
- cd_north is string character description of north boundary [optional]
- cd_south is string character description of south boundary [optional]
- cd_east is string character description of east boundary [optional]
- cd_west is string character description of west boundary [optional]
- ld_oneseg is logical to force to use only one segment for each boundary [optional]

to get boundary cardinal:

- tl_bdy%c_card

to know if boundary is use:

- tl_bdy%l_use

to know if boundary come from namelist (cn_north,..):

- tl_bdy%l_nam

to get the number of segment in boundary:

- `tl_bdy%i_nseg`

to get array of segment in boundary:

- `tl_bdy%t_seg(:)`

to get orthogonal segment index of north boundary:

- `tl_bdy%t_seg(jp_north)%`

to get segment width of south boundary:

- `tl_bdy%t_seg(jp_south)%`

to get segment first indice of east boundary:

- `tl_bdy%t_seg(jp_east)%`

to get segment last indice of west boundary:

- `tl_bdy%t_seg(jp_west)%`

to print information about boundary:

`CALL boundary_print(td_bdy)`

- `td_bdy` is boundary structure or a array of boundary structure

to clean boundary structure:

`CALL boundary_clean(td_bdy)`

to get indices of each semgent for each boundary:

`CALL boundary_get_indices(td_bdy, td_var, ld_oneseg)`

- `td_bdy` is boundary structure
- `td_var` is variable structure
- `ld_oneseg` is logical to force to use only one segment for each boundary [optional]

to check boundary indices and corner:

`CALL boundary_check(td_bdy, td_var)`

- `td_bdy` is boundary structure
- `td_var` is variable structure

to check boundary corner:

`CALL boundary_check_corner(td_bdy, td_var)`

- `td_bdy` is boundary structure
- `td_var` is variable structure

to create filename with cardinal name inside:

```
cl_filename=boundary_set_filename(cd_file, cd_card)
```

- `cd_file` = original file name
- `cd_card` = cardinal name

to swap array for east and north boundary:

```
CALL boundary_swap( td_var, td_bdy )
```

- `td_var` is variable structure
- `td_bdy` is boundary structure

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add boundary description

November, 2014

- Fix memory leaks bug

February, 2015

- Do not change indices read from namelist
- Change string character format of boundary read from namelist, see `boundary__get_info`

Todo add schematic to boundary structure description

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.6.2 Member Function/Subroutine Documentation

11.6.2.1 subroutine, public `boundary::boundary_check` (`type(tbdy)`, `dimension(ip_ncard)`, `intent(inout) td_bdy`, `type(tvar)`, `intent(in) td_var`)

This subroutine check boundary.

It checks that first and last indices as well as orthogonal index are inside domain, and check corner (see `boundary__check_corner`).

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2016

- Bug fix: take into account that boundaries are compute on T point, but expressed on U,V point

Parameters

<i>in, out</i>	<i>td_bdy</i>	boundary structure
<i>in</i>	<i>td_var</i>	variable structure

11.6.2.2 subroutine, public boundary::boundary_check_corner (type(*tbdy*), dimension(ip_ncard), intent(inout) *td_bdy*, type(*tvar*), intent(in) *td_var*)

This subroutine check if there is boundary at corner, and adjust boundary indices if necessary.

If there is a north west corner, first indices of north boundary should be the same as the west boundary indices. And the last indices of the west boundary should be the same as the north indices. More over the width of west and north boundary should be the same.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_bdy</i>	boundary structure
<i>in</i>	<i>td_var</i>	variable structure

11.6.2.3 subroutine, public boundary::boundary_get_indices (type(*tbdy*), dimension(ip_ncard), intent(inout) *td_bdy*, type(*tvar*), intent(in) *td_var*, logical, intent(in), optional *ld_oneseg*)

This subroutine get indices of each segment for each boundary.

indices are compute from variable value, actually variable fill value, which is assume to be land mask. Boundary structure should have been initialized before running this subroutine. Segment indices will be search between first and last indies, at this orthogonal index.

Optionnally you could forced to use only one segment for each boundary.

Warning

number of segment (*i_nseg*) will be change, before the number of segment structure

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_bdy</i>	boundary structure
----------------	---------------	--------------------

<code>in</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>ld_onseg</code>	use only one sgment for each boundary

11.6.2.4 `character(len=lc)` function, `public boundary::boundary_set_filename (character(len=*), intent(in) cd_file, character(len=*), intent(in) cd_card, integer(i4), intent(in), optional id_seg, character(len=*), intent(in), optional cd_date)`

This function put cardinal name and date inside file name.

Examples : `cd_file="boundary.nc"` `cd_card="west"` `id_seg =2` `cd_date=y2015m07d16`

function return "boundary_west_2_y2015m07d16.nc"

`cd_file="boundary.nc"` `cd_card="west"`

function return "boundary_west.nc"

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>cd_file</code>	file name
<code>in</code>	<code>cd_card</code>	cardinal name
<code>in</code>	<code>id_seg</code>	segment number
<code>in</code>	<code>cd_date</code>	file date (format: y????m??d??)

Returns

file name with cardinal name inside

11.6.2.5 `subroutine, public boundary::boundary_swap (type(tvar), intent(inout) td_var, type(tbdy), intent(in) td_bdy)`

This subroutine swap array for east and north boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable strucutre
<code>in</code>	<code>td_bdy</code>	boundary strucutre

The documentation for this module was generated from the following file:

- `src/boundary.f90`

11.7 boundary::boundary_clean Interface Reference

Public Member Functions

- subroutine [boundary__clean_unit](#) (td_bdy)
This subroutine clean boundary structure.
- subroutine [boundary__clean_arr](#) (td_bdy)
This subroutine clean array of boundary structure.

11.7.1 Member Function/Subroutine Documentation

11.7.1.1 subroutine boundary::boundary_clean::boundary__clean_arr (type(tbdy), dimension(:), intent(inout) td_bdy)

This subroutine clean array of boundary structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<i>in, out</i>	<i>td_bdy</i>	boundary strucutre
----------------	---------------	--------------------

11.7.1.2 subroutine boundary::boundary_clean::boundary__clean_unit (type(tbdy), intent(inout) td_bdy)

This subroutine clean boundary structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_bdy</i>	boundary strucutre
----------------	---------------	--------------------

The documentation for this interface was generated from the following file:

- src/boundary.f90

11.8 boundary::boundary_copy Interface Reference

Public Member Functions

- type(tbdy) function [boundary__copy_unit](#) (td_bdy)
This subroutine copy boundary structure in another one.
- type(tbdy) function, dimension(size(td_bdy(:))) [boundary__copy_arr](#) (td_bdy)
This subroutine copy a array of boundary structure in another one.

11.8.1 Member Function/Subroutine Documentation

11.8.1.1 `type(tbdy) function, dimension(size(td_bdy(:))) boundary::boundary_copy::boundary__copy_arr (type(tbdy), dimension(:), intent(in) td_bdy)`

This subroutine copy a array of boundary structure in another one.

Warning

do not use on the output of a function who create or read an attribute (ex: `tl_bdy=boundary_copy(boundary_-init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code><i>td_bdy</i></code>	array of boundary structure
-----------------	----------------------------	-----------------------------

Returns

copy of input array of boundary structure

11.8.1.2 `type(tbdy) function boundary::boundary_copy::boundary__copy_unit (type(tbdy), intent(in) td_bdy)`

This subroutine copy boundary structure in another one.

Warning

do not use on the output of a function who create or read an attribute (ex: `tl_bdy=boundary_copy(boundary_-init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_bdy</code>	boundary structure
-----------------	---------------------	--------------------

Returns

copy of input boundary structure

The documentation for this interface was generated from the following file:

- `src/boundary.f90`

11.9 boundary::boundary_init Interface Reference

Public Member Functions

- `type(tbdy)` function, `dimension(ip_ncard)` `boundary__init_wrapper` (`td_var`, `ld_north`, `ld_south`, `ld_east`, `ld_west`, `cd_north`, `cd_south`, `cd_east`, `cd_west`, `ld_oneseg`)

This function initialise a boundary structure.

11.9.1 Member Function/Subroutine Documentation

11.9.1.1 `type(tbdy)` function, `dimension(ip_ncard)` `boundary::boundary_init::boundary__init_wrapper` (`type(tvar)`, `intent(in) td_var`, `logical, intent(in), optional ld_north`, `logical, intent(in), optional ld_south`, `logical, intent(in), optional ld_east`, `logical, intent(in), optional ld_west`, `character(len=lc), intent(in), optional cd_north`, `character(len=lc), intent(in), optional cd_south`, `character(len=lc), intent(in), optional cd_east`, `character(len=lc), intent(in), optional cd_west`, `logical, intent(in), optional ld_oneseg`)

This function initialise a boundary structure.

Boundaries for each cardinal will be compute with variable structure. It means that orthogonal index, first and last indices of each sea segment will be compute automatically. However you could specify which boundary to use or not with arguments `ln_north`, `ln_south`, `ln_east`, `ln_west`. And boundary description could be specify with argument `cn_north`, `cn_south`, `cn_east`, `cn_west`. For each cardinal you could specify orthogonal index, first and last indices (in this order) and boundary width (between parentheses). ex : `cn_north='index,first,last(width)'` You could specify more than one segment for each boundary. However each segment will have the same width. So you do not need to specify it for each segment. ex : `cn_north='index1,first1,last1(width)|index2,first2,last2'`

Boundaries are compute on T point, but expressed on U,V point. change will be done to get data on other point when need be.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add boolean to use only one segment for each boundary
- check boundary width

Parameters

in	<i>td_var</i>	variable structure
in	<i>ld_north</i>	use north boundary or not
in	<i>ld_south</i>	use south boundary or not
in	<i>ld_east</i>	use east boundary or not
in	<i>ld_west</i>	use west boundary or not
in	<i>cd_north</i>	north boundary description
in	<i>cd_south</i>	south boundary description
in	<i>cd_east</i>	east boundary description
in	<i>cd_west</i>	west boundary description
in	<i>ld_oneseg</i>	force to use only one segment for each boundary

Returns

boundary structure

The documentation for this interface was generated from the following file:

- src/boundary.f90

11.10 boundary::boundary_print Interface Reference

Public Member Functions

- subroutine [boundary__print_unit](#) (td_bdy)
This subroutine print information about one boundary.
- subroutine [boundary__print_arr](#) (td_bdy)
This subroutine print information about a array of boundary.

11.10.1 Member Function/Subroutine Documentation

11.10.1.1 subroutine boundary::boundary_print::boundary__print_arr (type(tbdy), dimension(:), intent(in) td_bdy)

This subroutine print information about a array of boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_bdy</i>	boundary structure
----	---------------	--------------------

11.10.1.2 subroutine boundary::boundary_print::boundary__print_unit (type(tbdy), intent(in) td_bdy)

This subroutine print information about one boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_bdy</i>	boundary structure
----	---------------	--------------------

The documentation for this interface was generated from the following file:

- src/boundary.f90

11.11 date Module Reference

This module provide the calculation of Julian dates, and do many manipulations with dates.

Data Types

- interface [date_init](#)
- interface [operator\(+\)](#)
- interface [operator\(-\)](#)
- type [tdate](#)

Public Member Functions

- CHARACTER(LEN=lc) function, public [date_print](#) (td_date, cd_fmt)
This function print the date and time with format YYYY/MM/DD hh:mm:ss.
- LOGICAL function, public [date_leapyear](#) (td_date)
This function check if year is a leap year.
- TYPE(TDATE) function, public [date_now](#) ()
This function return the current date and time.
- TYPE(TDATE) function, public [date_today](#) ()
This function return the date of the day at 12:00:00.

11.11.1 Detailed Description

This module provide the calculation of Julian dates, and do many manipulations with dates.

Actually we use Modified Julian Dates, with 17 Nov 1858 at 00:00:00 as origin.

define type TDATE:

```
TYPE(tdate) :: t1_date1
```

default date is 17 Nov 1858 at 00:00:00

to initialise date :

- from date of the day at 12:00:00 :

```
t1_date1=date_today()
```

- from date and time of the day :

```
t1_date1=date_now()
```

- from julian day :

```
t1_date1=date_init(dd_jd)
```

- dd_jd julian day (double precision)

- from number of second since julian day origin :

```
t1_date1=date_init(kd_nsec)
```

- kd_nsec number of second (integer 8)

- from year month day :

```
t1_date1=date_init(2012,12,10)
```

- from string character formatted date :

```
t1_date1=date_init(cd_fmtdate)
```

- cd_fmtdate date in format YYYY-MM-DD hh:mm:ss

to print date in format YYYY-MM-DD hh:mm:ss

CHARACTER(LEN=l) :: cl_date

```
cl_date=date_print(t1_date1)
print *, trim(cl_date)
```

to print date in another format (only year, month, day):

```
cl_date=date_print(t1_date1, cd_fmt)
print *, trim(cl_date)
```

- cd_fmt output format (ex: cd_fmt="(y',i0.4,'m',i0.2,'d',i0.2)")

to print day of the week:

```
print *, "dow ", t1_date1%i_dow
```

to print last day of the month:

```
print *, "last day ", t1_date1%i_lday
```

to know if year is a leap year:

```
ll_isleap=date_leapyear(t1_date1)
```

- ll_isleap is logical

to compute number of days between two dates:

```
t1_date2=date_init(2010,12,10)
dl_diff=t1_date1-t1_date2
```

- dl_diff is the number of days between date1 and date2 (double precision)

to add or subtract nday to a date:

```
t1_date2=t1_date1+2.
t1_date2=t1_date1-2.6
```

- number of day (double precision)

to print julian day:

```
print *, " julian day",t1_date1\%r_jd
```

to print CNES julian day (origin 1950-01-01 00:00:00)

```
print *, " CNES julian day",t1_date1\%r_jc
```

to create pseudo julian day with origin date_now:

```
t1_date1=date_init (2012,12,10,td_dateo=date_now())
```

Note

you erase CNES julian day when doing so

to print julian day in seconds:

```
print *, t1_date1\%k_jdsec
```

to print CNES or new julian day in seconds:

```
print *, t1_date1\%k_jcsec
```

Author

J.Paul

Date

November, 2013 - Initial Version

Note

This module is based on Perderabo's date calculator (ksh)
Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

Todo • see calendar.f90 and select Gregorian, NoLeap, or D360 calendar

11.11.2 Member Function/Subroutine Documentation

11.11.2.1 LOGICAL function, public date::date_leapyear (type(tdate), intent(in) *td_date*)

This function check if year is a leap year.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_date</i>	date structcutre
-----------	----------------	------------------

Returns

true if year is leap year

11.11.2.2 TYPE(TDATE) function, public date::date_now ()

This function return the current date and time.

Author

J.Paul

Date

November, 2013 - Initial Version

Returns

current date and time in a date structure

11.11.2.3 CHARACTER(LEN=lc) function, public date::date_print (type(tdate), intent(in) *td_date*, character(len=*), intent(in), optional *cd_fmt*)

This function print the date and time with format YYYY/MM/DD hh:mm:ss.

Optionally, you could specify output format. However it will be only apply to year, month, day.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_date</i>	date structcutre
<i>in</i>	<i>cd_fmt</i>	ouput format (only for year,month,day)

Returns

date in format YYYY-MM-DD hh:mm:ss

11.11.2.4 TYPE(TDATE) function, public date::date_today ()

This function return the date of the day at 12:00:00.

Author

J.Paul

Date

November, 2013 - Initial Version

Returns

date of the day at 12:00:00 in a date structure

The documentation for this module was generated from the following file:

- src/date.f90

11.12 date::date_init Interface Reference**Public Member Functions**

- TYPE(TDATE) function [date__init_jd](#) (dd_jd, td_dateo)
This function initialized date structure from julian day.
- TYPE(TDATE) function [date__init_nsec](#) (kd_nsec, td_dateo)
This function initialized date structure from number of second since julian day origin.
- TYPE(TDATE) function [date__init_ymd](#) (id_year, id_month, id_day, id_hour, id_min, id_sec, td_dateo)
This function initialized date structure form year month day and optionnaly hour min sec.
- TYPE(TDATE) function [date__init_fmtdate](#) (cd_datetime, td_dateo)
This function initialized date structure from a character date with format YYYY-MM-DD hh:mm:ss.

11.12.1 Member Function/Subroutine Documentation

11.12.1.1 TYPE(TDATE) function `date::date_init::date__init_fmtdate (character(len=*), intent(in) cd_datetime, type(tdate), intent(in), optional td_dateo)`

This function initialized date structure from a character date with format YYYY-MM-DD hh:mm:ss.

Optionaly create pseudo julian day with new origin.

julian day origin is 17 Nov 1858 at 00:00:00

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_date</i>	date in format YYYY-MM-DD hh:mm:ss
in	<i>td_dateo</i>	new date origin for pseudo julian day

Returns

date structure

11.12.1.2 TYPE(TDATE) function date::date_init::date__init_jd (real(dp), intent(in) *dd_jd*, type(tdate), intent(in), optional *td_dateo*)

This function initialized date structure from julian day.

Optionally create pseudo julian day with new origin.

julian day origin is 17 Nov 1858 at 00:00:00

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>dd_jd</i>	julian day
in	<i>td_dateo</i>	new date origin for pseudo julian day

Returns

date structure of julian day

11.12.1.3 TYPE(TDATE) function date::date_init::date__init_nsec (integer(i8), intent(in) *kd_nsec*, type(tdate), intent(in), optional *td_dateo*)

This function initialized date structure from number of second since julian day origin.

Optionally create pseudo julian day with new origin.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>kd_nsec</i>	number of second since julian day origin
in	<i>td_dateo</i>	new date origin for pseudo julian day

Returns

date structure of julian day

11.12.1.4 TYPE(TDATE) function date::date_init::date__init_ymd (integer(i4), intent(in) *id_year*, integer(i4), intent(in) *id_month*, integer(i4), intent(in) *id_day*, integer(i4), intent(in), optional *id_hour*, integer(i4), intent(in), optional *id_min*, integer(i4), intent(in), optional *id_sec*, type(tdate), intent(in), optional *td_dateo*)

This function initialized date structure form year month day and optionnaly hour min sec.

Optionally create pseudo julian day with new origin.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>id_year</i>	
in	<i>id_month</i>	
in	<i>id_day</i>	
in	<i>id_hour</i>	
in	<i>id_min</i>	
in	<i>id_sec</i>	
in	<i>td_dateo</i>	new date origin for pseudo julian day

Returns

date structure of year month day

The documentation for this interface was generated from the following file:

- src/date.f90

11.13 dim Module Reference

This module manage dimension and how to change order of those dimension.

Data Types

- interface [dim_clean](#)
- interface [dim_copy](#)
- interface [dim_print](#)
- interface [dim_reorder_2xyzt](#)
- interface [dim_reorder_xyzt2](#)
- interface [dim_reshape_2xyzt](#)
- interface [dim_reshape_xyzt2](#)
- type [tdim](#)

Public Member Functions

- INTEGER(i4) function, public [dim_get_index](#) (td_dim, cd_name, cd_sname)
This function returns dimension index, given dimension name or short name.
- INTEGER(i4) function, public [dim_get_id](#) (td_dim, cd_name, cd_sname)
This function returns dimension id, in a array of dimension structure, given dimension name, or short name.
- TYPE(TDIM) function, public [dim_init](#) (cd_name, id_len, ld_uld, cd_sname, ld_use)
This function initialize a dimension structure with given name.
- type([tdim](#)) function, dimension(ip_maxdim),
public [dim_fill_unused](#) (td_dim)
This function fill unused dimension of an array of dimension and return a 4 elts array of dimension structure.
- subroutine, public [dim_reorder](#) (td_dim, cd_dimorder)

This subroutine switch element of an array (4 elts) of dimension structure from disordered dimension to ordered dimension

- subroutine, public `dim_disorder` (td_dim)

This subroutine switch dimension array from ordered dimension ('x','y','z','t') to disordered dimension.

- subroutine, public `dim_get_dummy` (cd_dummy)

This subroutine fill dummy dimension array.

- logical function, public `dim_is_dummy` (td_dim)

This function check if dimension is defined as dummy dimension in configuraton file.

- subroutine, public `dim_def_extra` (cd_file)

This subroutine read dimension configuration file, and fill array of dimension allowed.

11.13.1 Detailed Description

This module manage dimension and how to change order of those dimension.

```
define type TDIM:<br/>
```

```
TYPE (tdim) :: t1_dim
```

to initialize a dimension structure:

```
t1_dim=dim_init( cd_name, [id_len,] [ld_uld,] [cd_sname])
```

- `cd_name` is the dimension name
- `id_len` is the dimension size [optional]
- `ld_uld` is true if this dimension is the unlimited one [optional]
- `cd_sname` is the dimension short name ('x','y','z','t') [optional]

to clean dimension structure:

```
CALL dim_clean(t1_dim)
```

- `t1_dim` : dimension strucutre or array of dimension structure

to print information about dimension structure:

```
CALL dim_print(t1_dim)
```

to copy dimension structure in another one (using different memory cell):

```
t1_dim2=dim_copy(t1_dim1)
```

to get dimension name:

- `t1_dim%c_name`

to get dimension short name:

- `t1_dim%c_sname`

to get dimension length:

- `tl_dim%i_len`

to know if dimension is the unlimited one:

- `tl_dim%i_uld`

to get dimension id (for variable or file dimension):

- `tl_dim%i_id`

to know if dimension is used (for variable or file dimension):

- `tl_dim%i_use`

Former function or information concern only one dimension. However variables as well as files use usually 4 dimensions.

To easily work with variable we want they will be all 4D and ordered as following: ('x','y','z','t').

Functions and subroutines below, allow to reorder dimension of variable.

Suppose we defined the array of dimension structure below:

```
TYPE (tdim), DIMENSION(4) :: tl_dim
tl_dim(1)=dim_init( 'X', id_len=10)
tl_dim(2)=dim_init( 'T', id_len=3, ld_uld=.true.)
```

to reorder dimension (default order: ('x','y','z','t')):

```
CALL dim_reorder(tl_dim(:))
```

This subroutine filled dimension structure with unused dimension, then switch from "disordered" dimension to "ordered" dimension.

The dimension structure return will be:

```
tl_dim(1) => 'X', i_len=10, l_use=T, l_uld=F
tl_dim(2) => 'Y', i_len=1, l_use=F, l_uld=F
tl_dim(3) => 'Z', i_len=1, l_use=F, l_uld=F
tl_dim(4) => 'T', i_len=3, l_use=T, l_uld=T
```

After using subroutine `dim_reorder` you could use functions and subroutine below.

to use another dimension order.

```
CALL dim_reorder(tl(dim(:), cl_neworder)
```

- `cl_neworder` : character(len=4) (example: 'yxzt')

to switch dimension array from ordered dimension to disordered dimension:

```
CALL dim_disorder(tl_dim(:))
```

to fill unused dimension of an array of dimension structure.

```
tl_dimout(:)=dim_fill_unused(tl_dimin(:))
```

- `tl_dimout(:)` : 1D array (4elts) of dimension structure

- `tl_dimin(:)` : 1D array (≤ 4 elts) of dimension structure

to reshape array of value in "ordered" dimension:

```
CALL dim_reshape_2xyzt(tl_dim(:), value(:, :, :, :))
```

- value must be a 4D array of real(8) value "disordered"

to reshape array of value in "disordered" dimension:

```
CALL dim_reshape_xyz2(tl_dim(:), value(:, :, :, :))
```

- value must be a 4D array of real(8) value "ordered"

to reorder a 1D array of 4 elements in "ordered" dimension:

```
CALL dim_reorder_2xyzt(tl_dim(:), tab(:))
```

- `tab` must be a 1D array with 4 elements "disordered". It could be composed of character, integer(4), or logical

to reorder a 1D array of 4 elements in "disordered" dimension:

```
CALL dim_reorder_xyz2(tl_dim(:), tab(:))
```

- `tab` must be a 1D array with 4 elements "ordered". It could be composed of character, integer(4), or logical

to get dimension index from a array of dimension structure, given dimension name or short name :

```
index=dim_get_index( tl_dim(:), [cl_name, cl_sname] )
```

- `tl_dim(:)` : array of dimension structure
- `cl_name` : dimension name [optional]
- `cl_sname`: dimension short name [optional]

to get dimension id used in an array of dimension structure, given dimension name or short name :

```
id=dim_get_id( tl_dim(:), [cl_name, cl_sname] )
```

- `tl_dim(:)` : array of dimension structure
- `cl_name` : dimension name [optional]
- `cl_sname`: dimension short name [optional]

Author

J.Paul

Date

November, 2013 - Initial Version

Spetember, 2015

- manage useless (dummy) dimension

October, 2016

- dimension allowed read in configuration file

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.13.2 Member Function/Subroutine Documentation

11.13.2.1 subroutine, public dim::dim_def_extra (character(len=*), intent(in) *cd_file*)

This subroutine read dimension configuration file, and fill array of dimension allowed.

Author

J.Paul

Date

Ocotber, 2016 - Initial Version

Parameters

<i>in</i>	<i>cd_file</i>	input file (dimension configuration file)
-----------	----------------	---

11.13.2.2 subroutine, public dim::dim_disorder (type(tdim), dimension(:), intent(inout) *td_dim*)

This subroutine switch dimension array from ordered dimension ('x','y','z','t') to disordered dimension.

Example: ('x','y','z','t') => ('z','x','t','y')

Warning

this subroutine change dimension order

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_dim</i>	array of dimension structure
----------------	---------------	------------------------------

11.13.2.3 type(tdim) function, dimension(ip_maxdim), public dim::dim_fill_unused (type(tdim), dimension(:), intent(in), optional *td_dim*)

This function fill unused dimension of an array of dimension and return a 4 elts array of dimension structure.

output dimensions 'x','y','z' and 't' are all informed.

Note

without input array of dimension, return a 4 elts array of dimension structure all unused (case variable 0d)

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- Bug fix: use order to disorder table (see dim_init)

Parameters

<i>in</i>	<i>td_dim</i>	array of dimension structure
-----------	---------------	------------------------------

Returns

4elts array of dimension structure

11.13.2.4 subroutine, public dim::dim_get_dummy (character(len=*), intent(in) *cd_dummy*)

This subroutine fill dummy dimension array.

Author

J.Paul

Date

September, 2015 - Initial Version

Parameters

<i>in</i>	<i>cd_dummy</i>	dummy configuration file
-----------	-----------------	--------------------------

11.13.2.5 INTEGER(i4) function, public dim::dim_get_id (type(tdim), dimension(:), intent(in) *td_dim*, character(len=*), intent(in) *cd_name*, character(len=*), intent(in), optional *cd_sname*)

This function returns dimension id, in a array of dimension structure, given dimension name, or short name.

Note

only dimension used are checked.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_dim</i>	dimension structure
<i>in</i>	<i>cd_name</i>	dimension name or short name
<i>in</i>	<i>cd_sname</i>	dimension short name

Returns

dimension id

11.13.2.6 **INTEGER(i4) function, public dim::dim_get_index (type(tdim), dimension(:), intent(in) *td_dim*, character(len=*), intent(in) *cd_name*, character(len=*), intent(in), optional *cd_sname*)**

This function returns dimension index, given dimension name or short name.

the function check dimension name, in the array of dimension structure. dimension could be used or not.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- do not check if dimension used

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>cd_name</i>	dimension name
in	<i>cd_sname</i>	dimension short name

Returns

dimension index

11.13.2.7 **TYPE(TDIM) function, public dim::dim_init (character(len=*), intent(in) *cd_name*, integer(i4), intent(in), optional *id_len*, logical, intent(in), optional *id_uld*, character(len=*), intent(in), optional *cd_sname*, logical, intent(in), optional *id_use*)**

This function initialize a dimension structure with given name.

Optionally length could be inform, as well as short name and if dimension is unlimited or not.

By default, define dimension is supposed to be used. Optionally you could force a defined dimension to be unused.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- add optional argument to define dimension unused

July, 2015

- Bug fix: inform order to disorder table instead of disorder to order table

Parameters

in	<i>cd_name</i>	dimension name
in	<i>id_len</i>	dimension length

in	<i>ld_uld</i>	dimension unlimited
in	<i>cd_sname</i>	dimension short name
in	<i>ld_use</i>	dimension use or not

Returns

dimension structure

11.13.2.8 logical function, public dim::dim_is_dummy (type(tdim), intent(in) *td_dim*)

This function check if dimension is defined as dummy dimension in configuraton file.

Author

J.Paul

Date

September, 2015 - Initial Version

Parameters

in	<i>td_dim</i>	dimension structure
----	---------------	---------------------

Returns

true if dimension is dummy dimension

11.13.2.9 subroutine, public dim::dim_reorder (type(tdim), dimension(:), intent(inout) *td_dim*, character(len=ip_maxdim), intent(in), optional *cd_dimorder*)

This subroutine switch element of an array (4 elts) of dimension structure from disordered dimension to ordered dimension

Optionally you could specify dimension order to output (default 'xyzt') Example: (/z';x';t';y'/) => (/x';y';z';t'/)

Warning

this subroutine change dimension order

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- allow to choose ordered dimension to be output

Parameters

<code>in, out</code>	<code>td_dim</code>	array of dimension structure
<code>in</code>	<code>cd_dimorder</code>	dimension order to be output

The documentation for this module was generated from the following file:

- `src/dimension.f90`

11.14 dim::dim_clean Interface Reference

Public Member Functions

- subroutine `dim__clean_unit` (`td_dim`)
This subroutine clean dimension structure.
- subroutine `dim__clean_arr` (`td_dim`)
This subroutine clean array of dimension structure.

11.14.1 Member Function/Subroutine Documentation

11.14.1.1 subroutine `dim::dim_clean::dim__clean_arr` (`type(tdim)`, `dimension(:)`, `intent(inout) td_dim`)

This subroutine clean array of dimension structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_dim</code>	array of dimension strucutre
-----------------	---------------------	------------------------------

11.14.1.2 subroutine `dim::dim_clean::dim__clean_unit` (`type(tdim)`, `intent(inout) td_dim`)

This subroutine clean dimension structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_dim</code>	dimension structure
-----------------	---------------------	---------------------

The documentation for this interface was generated from the following file:

- src/dimension.f90

11.15 dim::dim_copy Interface Reference

Public Member Functions

- `type(tdim)` function `dim__copy_unit` (`td_dim`)
This subroutine copy an dimension structure in another one.
- `type(tdim)` function, `dimension(size(td_dim(:)))` `dim__copy_arr` (`td_dim`)
This subroutine copy a array of dimension structure in another one.

11.15.1 Member Function/Subroutine Documentation

11.15.1.1 `type(tdim)` function, `dimension(size(td_dim(:)))` `dim::dim_copy::dim__copy_arr` (`type(tdim)`, `dimension(:)`, `intent(in)` `td_dim`)

This subroutine copy a array of dimension structure in another one.

see `dim__copy_unit`

Warning

do not use on the output of a function who create or read an structure (ex: `tl_dim=dim_copy(dim_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_dim</code>	array of dimension structure
-----------------	---------------------	------------------------------

Returns

copy of input array of dimension structure

11.15.1.2 `type(tdim)` function `dim::dim_copy::dim__copy_unit` (`type(tdim)`, `intent(in)` `td_dim`)

This subroutine copy an dimension structure in another one.

dummy function to get the same use for all structure

Warning

do not use on the output of a function who create or read an structure (ex: `tl_dim=dim_copy(dim_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_dim</code>	dimension structure
-----------------	---------------------	---------------------

Returns

copy of input dimension structure

The documentation for this interface was generated from the following file:

- `src/dimension.f90`

11.16 dim::dim_print Interface Reference

Public Member Functions

- subroutine `dim__print_unit` (`td_dim`)
This subrtoutine print dimension information.
- subroutine `dim__print_arr` (`td_dim`)
This subroutine print informations of an array of dimension.

11.16.1 Member Function/Subroutine Documentation

11.16.1.1 subroutine `dim::dim_print::dim__print_arr` (`type(tdim)`, `dimension(:)`, `intent(in) td_dim`)

This subroutine print informations of an array of dimension.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
----	---------------	------------------------------

11.16.1.2 subroutine dim::dim_print::dim__print_unit (type(tdim), intent(in) *td_dim*)

This subrtoutine print dimension information.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	dimension structure
----	---------------	---------------------

The documentation for this interface was generated from the following file:

- src/dimension.f90

11.17 dim::dim_reorder_2xyzt Interface Reference

Public Member Functions

- integer(i4) function,
dimension(ip_maxdim) [dim__reorder_2xyzt_i4](#) (td_dim, id_arr)
This function reordered integer(4) 1D array to be suitable with dimension ordered as defined in dim_reorder.
- character(len=lc) function,
dimension(ip_maxdim) [dim__reorder_2xyzt_c](#) (td_dim, cd_arr)
This function reordered string 1D array to be suitable with dimension ordered as defined in dim_reorder.
- logical function, dimension(ip_maxdim) [dim__reorder_2xyzt_l](#) (td_dim, ld_arr)
This function reordered logical 1D array to be suitable with dimension ordered as defined in dim_reorder.

11.17.1 Member Function/Subroutine Documentation

11.17.1.1 character(len=lc) function, dimension(ip_maxdim) dim::dim_reorder_2xyzt::dim__reorder_2xyzt_c (type(tdim), dimension(:), intent(in) *td_dim*, character(len=*), dimension(:), intent(in) *cd_arr*)

This function reordered string 1D array to be suitable with dimension ordered as defined in dim_reorder.

Note

you must have run dim_reorder before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>cd_arr</i>	array of value to reordered

Returns

array of value reordered

11.17.1.2 integer(i4) function, dimension(ip_maxdim) dim::dim_reorder_2xyzt::dim__reorder_2xyzt_i4 (type(tdim), dimension(:), intent(in) *td_dim*, integer(i4), dimension(:), intent(in) *id_arr*)

This function reordered integer(4) 1D array to be suitable with dimension ordered as defined in dim_reorder.

Note

you must have run dim_reorder before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>id_arr</i>	array of value to reshape

Returns

array of value reshaped

11.17.1.3 logical function, dimension(ip_maxdim) dim::dim_reorder_2xyzt::dim__reorder_2xyzt_l (type(tdim), dimension(:), intent(in) *td_dim*, logical, dimension(:), intent(in) *ld_arr*)

This function reordered logical 1D array to be suitable with dimension ordered as defined in dim_reorder.

Note

you must have run dim_reorder before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>ld_arr</i>	array of value to reordered

Returns

array of value reordered

The documentation for this interface was generated from the following file:

- src/dimension.f90

11.18 dim::dim_reorder_xyzt2 Interface Reference

Public Member Functions

- integer(i4) function,
dimension(ip_maxdim) [dim__reorder_xyzt2_i4](#) (td_dim, id_arr)
This function disordered integer(4) 1D array to be suitable with initial dimension order (ex: dimension read in file).
- character(len=lc) function,
dimension(ip_maxdim) [dim__reorder_xyzt2_c](#) (td_dim, cd_arr)
This function disordered string 1D array to be suitable with initial dimension order (ex: dimension read in file).
- logical function, dimension(ip_maxdim) [dim__reorder_xyzt2_l](#) (td_dim, ld_arr)
This function disordered logical 1D array to be suitable with initial dimension order (ex: dimension read in file).

11.18.1 Member Function/Subroutine Documentation

11.18.1.1 **character(len=lc) function, dimension(ip_maxdim) dim::dim_reorder_xyzt2::dim_reorder_xyzt2_c (type(tdim), dimension(:), intent(in) *td_dim*, character(len=*) , dimension(:), intent(in) *cd_arr*)**

This function disordered string 1D array to be suitable with initial dimension order (ex: dimension read in file).

Note

you must have run `dim_reorder` before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>cd_arr</i>	array of value to reordered

Returns

array of value reordered

11.18.1.2 `integer(i4) function, dimension(ip_maxdim) dim::dim_reorder_xyz2::dim__reorder_xyz2_i4 (type(tdim), dimension(:), intent(in) td_dim, integer(i4), dimension(:), intent(in) id_arr)`

This function disordered integer(4) 1D array to be suitable with initial dimension order (ex: dimension read in file).

Note

you must have run `dim_reorder` before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code><i>td_dim</i></code>	array of dimension structure
<code>in</code>	<code><i>id_arr</i></code>	array of value to reshape

Returns

array of value reshaped

11.18.1.3 `logical function, dimension(ip_maxdim) dim::dim_reorder_xyz2::dim__reorder_xyz2_l (type(tdim), dimension(:), intent(in) td_dim, logical, dimension(:), intent(in) ld_arr)`

This function disordered logical 1D array to be suitable with initial dimension order (ex: dimension read in file).

Note

you must have run `dim_reorder` before use this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code><i>td_dim</i></code>	array of dimension structure
<code>in</code>	<code><i>ld_arr</i></code>	array of value to reordered

Returns

array of value reordered

The documentation for this interface was generated from the following file:

- `src/dimension.f90`

11.19 dim::dim_reshape_2xyzt Interface Reference

Public Member Functions

- `real(dp) function, dimension(td_dim(1)%i_len,td_dim(2)%i_len,td_dim(3)%i_len,td_dim(4)%i_len) dim__reshape_2xyzt_dp (td_dim, dd_value)`

This function reshape real(8) 4D array to an ordered array, as defined by dim_reorder.

11.19.1 Member Function/Subroutine Documentation

11.19.1.1 `real(dp) function, dimension(td_dim(1)%i_len, td_dim(2)%i_len, td_dim(3)%i_len, td_dim(4)%i_len) dim::dim_reshape_2xyzt::dim__reshape_2xyzt_dp (type(tdim), dimension(:), intent(in) td_dim, real(dp), dimension(:,:,:), intent(in) dd_value)`

This function reshape real(8) 4D array to an ordered array, as defined by dim_reorder.

Example: `(/'z','x','t','y'/) => (/'x','y','z','t'/)`

Note

you must have run dim_reorder before use this subroutine

Warning

output array dimension differ from input array dimension

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_dim</code>	array of dimension structure
<code>in</code>	<code>dd_value</code>	array of value to reshape

Returns

array of value reshaped

The documentation for this interface was generated from the following file:

- `src/dimension.f90`

11.20 dim::dim_reshape_xyzt2 Interface Reference

Public Member Functions

- `real(dp) function, dimension(td_dim(td_dim(1)%_xyzt2)%i_len,td_dim(td_dim(2)%_xyzt2)%i_len,td_dim(td_dim(3)%_xyzt2)%i_len,td_dim(td_dim(4)%_xyzt2)%i_len) dim__reshape_xyzt2_dp (td_dim, dd_value)`

This function reshape ordered real(8) 4D array with dimension (/'x','y','z','t'/) to an "disordered" array.

11.20.1 Member Function/Subroutine Documentation

11.20.1.1 `real(dp) function, dimension(td_dim(td_dim(1)%i_xyzt2)%i_len, td_dim(td_dim(2)%i_xyzt2)%i_len, td_dim(td_dim(3)%i_xyzt2)%i_len, td_dim(td_dim(4)%i_xyzt2)%i_len) dim::dim_reshape_xyzt2::dim_reshape_xyzt2_dp (type(tdim), dimension(:), intent(in) td_dim, real(dp), dimension(:,:,:), intent(in) dd_value)`

This function reshape ordered real(8) 4D array with dimension ('x','y','z','t') to an "disordered" array.

Example: ('x','y','z','t') => ('z','x','t','y')

Note

you must have run `dim_reorder` before use this subroutine

Warning

output array dimension differ from input array dimension

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_dim</i>	array of dimension structure
in	<i>dd_value</i>	array of value to reshape

Returns

array of value reshaped

The documentation for this interface was generated from the following file:

- `src/dimension.f90`

11.21 dom Module Reference

This module manage domain computation.

Data Types

- interface [dom_copy](#)
- interface [dom_init](#)
- type [tdom](#)

Public Member Functions

- subroutine, public [dom_print](#) (td_dom)
This subroutine print some information about domain strucutre.
- TYPE(TDOM) function [dom__init_file](#) (td_file, id_imin, id_imax, id_jmin, id_jmax, cd_card)

This function initialise domain structure, given open file structure, and sub domain indices.

- subroutine, public `dom_add_extra` (td_dom, id_iext, id_jext)

This subroutine add extra bands to coarse domain to get enough point for interpolation...

- subroutine, public `dom_clean_extra` (td_dom)

This subroutine clean coarse grid domain structure. it remove extra point added.

- subroutine, public `dom_del_extra` (td_var, td_dom, id_rho, ld_coord)

This subroutine delete extra band, from fine grid variable value, and dimension, taking into account refinement factor.

- subroutine, public `dom_clean` (td_dom)

This subroutine clean domain structure.

11.21.1 Detailed Description

This module manage domain computation.

```
define type TDOM:<br/>
```

```
TYPE (tdom) :: tl_dom
```

to initialize domain structure:

```
tl_dom=dom_init(td_mpp, [id_imin,] [id_imax,] [id_jmin,] [id_jmax],[cd_card])
```

- `td_mpp` is mpp structure of an opened file.
- `id_imin` is i-direction sub-domain lower left point indice
- `id_imax` is i-direction sub-domain upper right point indice
- `id_jmin` is j-direction sub-domain lower left point indice
- `id_jmax` is j-direction sub-domain upper right point indice
- `cd_card` is the cardinal name (for boundary case)

to get global domain dimension:

- `tl_dom%t_dim0`

to get NEMO periodicity index of global domain:

- `tl_dom%i_perio0`

to get NEMO pivot point index F(0),T(1):

- `tl_dom%i_pivot`

to get East-West overlap of global domain:

- `tl_dom%i_ew0`

to get selected sub domain dimension:

- `tl_dom%t_dim`

to get NEMO periodicity index of sub domain:

- `tl_dom%i_perio`

to get East-West overlap of sub domain:

- `tl_dom%i_ew`

to get i-direction sub-domain lower left point indice:

- `tl_dom%i_imin`

to get i-direction sub-domain upper right point indice:

- `tl_dom%i_imax`

to get j-direction sub-domain lower left point indice:

- `tl_dom%i_jmin`

to get j-direction sub-domain upper right point indice:

- `tl_dom%i_jmax`

to get size of i-direction extra band:

- `tl_dom%i_iextra`

to get size of j-direction extra band:

- `tl_dom%i_jextra`

to get i-direction ghost cell number:

- `tl_dom%i_ighost`

to get j-direction ghost cell number:

- `tl_dom%i_jghost`

to get boundary index:

- `tl_dom%i_bdy`
 - 0 = no boundary
 - 1 = north
 - 2 = south
 - 3 = east
 - 4 = west

to clean domain structure:

`CALL dom_clean(td_dom)`

- `td_dom` is domain structure

to print information about domain structure:

```
CALL dom_print(td_dom)
```

to get East-West overlap (if any):

```
il_ew=dom_get_ew_overlap(td_lon)
```

- `td_lon` : longitude variable structure

to add extra bands to coarse grid domain (for interpolation):

```
CALL dom_add_extra( td_dom, id_iext, id_jext )
```

- `td_dom` is domain structure
- `id_iext` is i-direction size of extra bands
- `id_jext` is j-direction size of extra bands

to remove extra bands from fine grid (after interpolation):

```
CALL dom_del_extra( td_var, td_dom, id_rho )
```

- `td_var` is variable structure to be changed
- `td_dom` is domain structure
- `id_rho` is a array of refinement factor following i- and j-direction

to reset coarse grid domain without extra bands:

```
CALL dom_clean_extra( td_dom )
```

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header
- use zero indice to defined cyclic or global domain

October, 2014

- use mpp file structure instead of file

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.21.2 Member Function/Subroutine Documentation

11.21.2.1 TYPE(TDOM) function `dom::dom__init_file (type(tfile), intent(in) td_file, integer(i4), intent(in), optional id_imin, integer(i4), intent(in), optional id_imax, integer(i4), intent(in), optional id_jmin, integer(i4), intent(in), optional id_jmax, character(len=*), intent(in), optional cd_card)`

This function initialise domain structure, given open file structure, and sub domain indices.

sub domain indices are computed, taking into account coarse grid periodicity, pivot point, and East-West overlap.

Author

J.Paul

Date

June, 2013 - Initial Version

September, 2014

- add boundary index
- add ghost cell factor

Parameters

<i>in</i>	<i>td_file</i>	file structure
<i>in</i>	<i>id_perio</i>	grid periodicity
<i>in</i>	<i>id_imin</i>	i-direction sub-domain lower left point indice
<i>in</i>	<i>id_imax</i>	i-direction sub-domain upper right point indice
<i>in</i>	<i>id_jmin</i>	j-direction sub-domain lower left point indice
<i>in</i>	<i>id_jmax</i>	j-direction sub-domain upper right point indice
<i>in</i>	<i>cd_card</i>	name of cardinal (for boundary)

Returns

domain structure

11.21.2.2 subroutine, public `dom::dom_add_extra (type(tdom), intent(inout) td_dom, integer(i4), intent(in), optional id_iext, integer(i4), intent(in), optional id_jext)`

This subroutine add extra bands to coarse domain to get enough point for interpolation...

- domain periodicity is take into account.
- domain indices are changed, and size of extra bands are saved.
- optionally, i- and j- direction size of extra bands could be specify (default=im_minext)

Author

J.Paul

Date

November, 2013 - Initial version

September, 2014

- take into account number of ghost cell

February, 2016

- number of extra point is the MAX (not the MIN) of zero and asess value.

Parameters

<i>in, out</i>	<i>td_dom</i>	domain structure
<i>in</i>	<i>id_jext</i>	i-direction size of extra bands (default=im_minext)
<i>in</i>	<i>id_jext</i>	j-direction size of extra bands (default=im_minext)

11.21.2.3 subroutine, public dom::dom_clean (type(tdom), intent(inout) *td_dom*)

This subroutine clean domain structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_dom</i>	domain structure
----------------	---------------	------------------

11.21.2.4 subroutine, public dom::dom_clean_extra (type(tdom), intent(inout) *td_dom*)

This subroutine clean coarse grid domain structure. it remove extra point added.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_dom</i>	domain structure
----------------	---------------	------------------

11.21.2.5 subroutine, public dom::dom_del_extra (type(tvar), intent(inout) *td_var*, type(tdom), intent(in) *td_dom*, integer(i4), dimension(:), intent(in), optional *id_rho*, logical, intent(in), optional *ld_coord*)

This subroutine delete extra band, from fine grid variable value, and dimension, taking into account refinement factor.

Note

This subroutine should be used before clean domain structure.

Warning

if work on coordinates grid, do not remove all extra point. save value on ghost cell.

Author

J.Paul

Date

November, 2013 - Initial version

September, 2014

- take into account boundary for one point size domain

December, 2014

- add special case for coordinates file.

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>td_dom</code>	domain structure
<code>in</code>	<code>id_rho</code>	array of refinement factor
<code>in</code>	<code>ld_coord</code>	work on coordinates file or not

11.21.2.6 subroutine, public `dom::dom_print (type(tdom), intent(in) td_dom)`

This subroutine print some information about domain structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_dom</code>	dom structure
----------------------	---------------------	---------------

The documentation for this module was generated from the following file:

- `src/domain.f90`

11.22 dom::dom_copy Interface Reference

Public Member Functions

- `type(tdom)` function `dom__copy_unit (td_dom)`
This subroutine copy an domain structure in another one.

11.22.1 Member Function/Subroutine Documentation

11.22.1.1 `type(tdom)` function `dom::dom_copy::dom__copy_unit (type(tdom), intent(in) td_dom)`

This subroutine copy an domain structure in another one.

dummy function to get the same use for all structure

Warning

do not use on the output of a function who create or read an structure (ex: `tl_dom=dom_copy(dom_init())` is forbidden). This will create memory leaks.

to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_dom</code>	domain structure
-----------------	---------------------	------------------

Returns

copy of input domain structure

The documentation for this interface was generated from the following file:

- src/domain.f90

11.23 dom::dom_init Interface Reference

Public Member Functions

- TYPE(TDOM) function [dom__init_file](#) (`td_file`, `id_imin`, `id_imax`, `id_jmin`, `id_jmax`, `cd_card`)
This function initialise domain structure, given open file structure, and sub domain indices.
- TYPE(TDOM) function [dom__init_mpp](#) (`td_mpp`, `id_imin`, `id_imax`, `id_jmin`, `id_jmax`, `cd_card`)
This function initialise domain structure, given open file structure, and sub domain indices.

11.23.1 Member Function/Subroutine Documentation

11.23.1.1 TYPE(TDOM) function `dom::dom_init::dom__init_file` (`type(tfile)`, `intent(in) td_file`, `integer(i4)`, `intent(in)`, optional `id_imin`, `integer(i4)`, `intent(in)`, optional `id_imax`, `integer(i4)`, `intent(in)`, optional `id_jmin`, `integer(i4)`, `intent(in)`, optional `id_jmax`, `character(len=*)`, `intent(in)`, optional `cd_card`)

This function initialise domain structure, given open file structure, and sub domain indices.

sub domain indices are computed, taking into account coarse grid periodicity, pivot point, and East-West overlap.

Author

J.Paul

Date

June, 2013 - Initial Version
September, 2014

- add boundary index
- add ghost cell factor

Parameters

in	<i>td_file</i>	file structure
in	<i>id_perio</i>	grid periodicity
in	<i>id_imin</i>	i-direction sub-domain lower left point indice
in	<i>id_imax</i>	i-direction sub-domain upper right point indice
in	<i>id_jmin</i>	j-direction sub-domain lower left point indice
in	<i>id_jmax</i>	j-direction sub-domain upper right point indice
in	<i>cd_card</i>	name of cardinal (for boundary)

Returns

domain structure

11.23.1.2 TYPE(TDOM) function dom::dom_init::dom__init_mpp (type(tmpp), intent(in) *td_mpp*, integer(i4), intent(in), optional *id_imin*, integer(i4), intent(in), optional *id_imax*, integer(i4), intent(in), optional *id_jmin*, integer(i4), intent(in), optional *id_jmax*, character(len=*) , intent(in), optional *cd_card*)

This function initialise domain structure, given open file structure, and sub domain indices.

sub domain indices are computed, taking into account coarse grid periodicity, pivot point, and East-West overlap.

Author

J.Paul

Date

June, 2013 - Initial Version

September, 2014

- add boundary index
- add ghost cell factor

October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>id_perio</i>	grid periodicity
in	<i>id_imin</i>	i-direction sub-domain lower left point indice
in	<i>id_imax</i>	i-direction sub-domain upper right point indice
in	<i>id_jmin</i>	j-direction sub-domain lower left point indice
in	<i>id_jmax</i>	j-direction sub-domain upper right point indice
in	<i>cd_card</i>	name of cardinal (for boundary)

Returns

domain structure

The documentation for this interface was generated from the following file:

- src/domain.f90

11.24 extrap Module Reference

This module manage extrapolation.

Data Types

- interface [extrap_detect](#)
- interface [extrap_fill_value](#)

Public Member Functions

- subroutine, public [extrap_add_extrabands](#) (td_var, id_ysize, id_jsize)
This subroutine add to the variable (to be extrapolated) an extraband of N points at north,south,east and west boundaries.
- subroutine, public [extrap_del_extrabands](#) (td_var, id_ysize, id_jsize)
This subroutine remove of the variable an extraband of N points at north,south,east and west boundaries.

11.24.1 Detailed Description

This module manage extrapolation.

Extrapolation method to be used is specify inside variable structure, as array of string character.


```
- td_var%c_extrap(1) string character is the interpolation name choose between:
  - 'dist_weight'
  - 'min_error'
```

@note Extrapolation method could be specify for each variable in namelist `_namvar_`, defining string character `_cn_varinfo_`. By default `_dist_weight_`.

Example:

```
- cn_varinfo='varname1:ext=dist_weight', 'varname2:ext=min_error'
```

to detect point to be extrapolated:


```
il_detect(:, :, :) = extrap_detect(td_var)
```

- `il_detect(:, :, :)` is 3D array of point to be extrapolated
- `td_var` is coarse grid variable to be extrapolated

to extrapolate variable:

```
CALL extrap_fill_value( td_var, [id_radius])
```

- `td_var` is coarse grid variable to be extrapolated
- `id_radius` is radius of the halo used to compute extrapolation [optional]

to add extraband to the variable (to be extrapolated):

```
CALL extrap_add_extrabands(td_var, [id_ysize,] [id_jsize] )
```

- `td_var` is variable structure
- `id_ysize` : i-direction size of extra bands [optional]
- `id_jsize` : j-direction size of extra bands [optional]

to delete extraband of a variable:

```
CALL extrap_del_extrabands(td_var, [id_ysize,] [id_jsize] )
```

- `td_var` is variable structure
- `id_ysize` : i-direction size of extra bands [optional]
- `id_jsize` : j-direction size of extra bands [optional]

Warning

`_FillValue` must not be zero (use `var_chg_FillValue()`)

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header

June, 2015

- extrapolate all land points (`_FillValue`)
- move deriv function to math module

July, 2015

- compute extrapolation from north west to south east, and from south east to north west

Todo

- create module for each extrapolation method
- smooth extrapolated points

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.24.2 Member Function/Subroutine Documentation

11.24.2.1 subroutine, public `extrap::extrap_add_extrabands (type(tvar), intent(inout) td_var, integer(i4), intent(in), optional id_ysize, integer(i4), intent(in), optional id_ysize)`

This subroutine add to the variable (to be extrapolated) an extraband of N points at north,south,east and west boundaries.

optionaly you could specify size of extra bands in i- and j-direction

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<code>in, out</code>	<code>td_var</code>	variable
<code>in</code>	<code>id_ysize</code>	i-direction size of extra bands (default= <code>im_minext</code>)
<code>in</code>	<code>id_ysize</code>	j-direction size of extra bands (default= <code>im_minext</code>)

Todo

- invalid special case for grid with north fold

11.24.2.2 subroutine, public extrap::extrap_del_extrabands (type(tvar), intent(inout) *td_var*, integer(i4), intent(in), optional *id_ysize*, integer(i4), intent(in), optional *id_ysize*)

This subroutine remove of the variable an extraband of N points at north,south,east and west boundaries.
optionaly you could specify size of extra bands in i- and j-direction

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_var</i>	variable
<i>in</i>	<i>id_ysize</i>	i-direction size of extra bands (default=im_minext)
<i>in</i>	<i>id_ysize</i>	j-direction size of extra bands (default=im_minext)

The documentation for this module was generated from the following file:

- src/extrap.f90

11.25 extrap::extrap_detect Interface Reference

Public Member Functions

- integer(i4) function,
dimension(td_var%t_dim(1)%i_len,td_var%t_dim(2)%i_len,td_var%t_dim(3)%i_len) [extrap__detect_wrapper](#)
(td_var)

This function sort variable to be extrapolated, depending on number of dimention, then detected point to be extrapolated.

- **detected**
- **point**
- **to**
- **be**
- **extrapolated**

11.25.1 Member Function/Subroutine Documentation

11.25.1.1 integer(i4) function, dimension(td_var%t_dim(1)%i_len, td_var%t_dim(2)%i_len, td_var%t_dim(3)%i_len)
extrap::extrap_detect::extrap__detect_wrapper (type(tvar), intent(in) *td_var*)

This function sort variable to be extrapolated, depending on number of dimention, then detected point to be extrapolated.

Author

J.Paul

Date

November, 2013 - Initial Version
June, 2015

- select all land points for extrapolation

Parameters

<code>in</code>	<code>td_var</code>	coarse grid variable to extrapolate
-----------------	---------------------	-------------------------------------

Returns

3D array of point to be extrapolated

The documentation for this interface was generated from the following files:

- `src/extrap.f90`

11.26 `extrap::extrap_fill_value` Interface Reference

Public Member Functions

- subroutine `extrap__fill_value_wrapper` (`td_var`, `id_radius`)
This subroutine select method to be used for extrapolation. If need be, increase number of points to be extrapolated. Finally launch `extrap__fill_value`.
 - **detected**
 - **point**
 - **to**
 - **be**
 - **interpolated**

11.26.1 Member Function/Subroutine Documentation

11.26.1.1 subroutine `extrap::extrap_fill_value::extrap__fill_value_wrapper` (`type(tvar)`, `intent(inout) td_var`, `integer(i4)`, `intent(in)`, optional `id_radius`)

This subroutine select method to be used for extrapolation. If need be, increase number of points to be extrapolated. Finally launch `extrap__fill_value`.

optionally, you could specify :

- refinement factor (default 1)
- offset between fine and coarse grid (default compute from refinement factor as $\text{offset}=(\text{rho}-1)/2$)
- number of point to be extrapolated in each direction (default `im_minext`)
- radius of the halo used to compute extrapolation
- maximum number of iteration

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- select all land points for extrapolation

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>id_radius</code>	radius of the halo used to compute extrapolation

The documentation for this interface was generated from the following files:

- `src/extrap.f90`

11.27 fct Module Reference

This module groups some basic useful function.

Data Types

- interface [fct_str](#)
- interface [operator\(//\)](#)

Public Member Functions

- INTEGER(i4) function, public [fct_getunit](#) ()
This function returns the next available I/O unit number.
- subroutine, public [fct_err](#) (id_status)
This subroutine handle Fortran status.
- subroutine, public [fct_pause](#) (cd_msg)
This subroutine create a pause statement.
- PURE CHARACTER(LEN=lc) function, public [fct_concat](#) (cd_arr, cd_sep)
This function concatenate all the element of a character array in a character string.
- PURE CHARACTER(LEN=lc) function, public [fct_lower](#) (cd_var)
This function convert string character upper case to lower case.
- PURE CHARACTER(LEN=lc) function, public [fct_upper](#) (cd_var)
This function convert string character lower case to upper case.
- PURE LOGICAL function, public [fct_is_num](#) (cd_var)
This function check if character is numeric.
- PURE LOGICAL function, public [fct_is_real](#) (cd_var)
This function check if character is real number.
- pure character(len=lc) function, public [fct_split](#) (cd_string, id_ind, cd_sep)
This function split string of character using separator character, by default '|', and return the element on index ind.
- pure character(len=lc) function, public [fct_basename](#) (cd_string, cd_sep)
This function return basename of a filename.
- pure character(len=lc) function, public [fct_dirname](#) (cd_string, cd_sep)
This function return dirname of a filename.

11.27.1 Detailed Description

This module groups some basic useful function.

to get free I/O unit number:

```
il_id=fct_getunit()
```

to convert "numeric" to string character:

```
cl_string=fct_str(numeric)
```

- "numeric" could be integer, real, or logical

to concatenate "numeric" to a string character:

```
cl_str=cd_char//num
```

- cd_char is the string character
- num is the numeric value (integer, real or logical)

to concatenate all the element of a character array:

```
cl_string=fct_concat(cd_arr [,cd_sep])
```

- cd_arr is a 1D array of character
- cd_sep is a separator character to add between each element of cd_arr [optional]

to convert character from lower to upper case:

```
cl_upper=fct_upper(cd_var)
```

to convert character from upper to lower case:

```
cl_lower=fct_lower(cd_var)
```

to check if character is numeric

```
ll_is_num=fct_is_num(cd_var)
```

to check if character is real

```
ll_is_real=fct_is_real(cd_var)
```

to split string into substring and return one of the element:

```
cl_str=fct_split(cd_string ,id_ind [,cd_sep])
```

- cd_string is a string of character
- id_ind is the indice of the lement to extract
- cd_sep is the separator use to split cd_string (default '|')

to get basename (name without path):

```
cl_str=fct_basename(cd_string [,cd_sep])
```

- cd_string is the string filename
- cd_sep is the separator to be used (default '/')

to get dirname (path of the filename):

```
cl_str=fct_dirname(cd_string [,cd_sep])
```

- cd_string is the string filename
- cd_sep is the separator to be used (default '/')

to create a pause statement:

```
CALL fct_pause(cd_msg)
```

- cd_msg : message to be added [optional]

to handle fortran error:

```
CALL fct_err(id_status)
```

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.27.2 Member Function/Subroutine Documentation

11.27.2.1 pure character(len=lc) function, public fct::fct_basename (character(len=*), intent(in) *cd_string*, character(len=*), intent(in), optional *cd_sep*)

This function return basename of a filename.

Actually it splits filename using separator '/' and return last string character.

Optionally you could specify another separator.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_string</i>	filename
<i>in</i>	<i>cd_sep</i>	separator character

Returns

basename (filename without path)

11.27.2.2 PURE CHARACTER(LEN=lc) function, public fct::fct_concat (character(*), dimension(:), intent(in) *cd_arr*, character(*), intent(in), optional *cd_sep*)

This function concatenate all the element of a character array in a character string.

optionnally a separator could be added between each element.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_arr</i>	array of character
<i>in</i>	<i>cd_sep</i>	separator character

Returns

character

11.27.2.3 pure character(len=lc) function, public fct::fct_dirname (character(len=*), intent(in) *cd_string*, character(len=*), intent(in), optional *cd_sep*)

This function return dirname of a filename.

Actually it splits filename using sperarator '/' and return all except last string character.

Optionally you could specify another separator.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_string</i>	filename
-----------	------------------	----------

<i>in</i>	<i>cd_sep</i>	separator character
-----------	---------------	---------------------

Returns

dirname (path of the filename)

11.27.2.4 subroutine, public fct::fct_err (integer(i4), intent(in) *id_status*)

This subroutine handle Fortran status.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>id_status</i>	
-----------	------------------	--

11.27.2.5 INTEGER(i4) function, public fct::fct_getunit ()

This function returns the next available I/O unit number.

Author

J.Paul

Date

November, 2013 - Initial Version

Returns

file id

11.27.2.6 PURE LOGICAL function, public fct::fct_is_num (character(len=*), intent(in) *cd_var*)

This function check if character is numeric.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_var</i>	character
-----------	---------------	-----------

Returns

character is numeric

11.27.2.7 PURE LOGICAL function, public fct::fct_is_real (character(len=*), intent(in) *cd_var*)

This function check if character is real number.

it allows exponential and decimal number exemple : 1e6, 2.3

Author

J.Paul

Date

June, 2015 - Initial Version

Parameters

<i>in</i>	<i>cd_var</i>	character
-----------	---------------	-----------

Returns

character is real number

11.27.2.8 PURE CHARACTER(LEN=l) function, public fct::fct_lower (character(*), intent(in) *cd_var*)

This function convert string character upper case to lower case.

The function IACHAR returns the ASCII value of the character passed as argument. The ASCII code has the uppercase alphabet starting at code 65, and the lower case one at code 101, therefore IACHAR('a')- IACHAR('A') would be the difference between the uppercase and the lowercase codes.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_var</i>	character
-----------	---------------	-----------

Returns

lower case character

11.27.2.9 subroutine, public fct::fct_pause (character(len=*), intent(in), optional *cd_msg*)

This subroutine create a pause statement.

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<i>in</i>	<i>cd_msg</i>	optional message to be added
-----------	---------------	------------------------------

11.27.2.10 pure character(len=lc) function, public fct::fct_split (character(len=*), intent(in) *cd_string*, integer(i4), intent(in) *id_ind*, character(len=*), intent(in), optional *cd_sep*)

This function split string of character using separator character, by default '|', and return the element on index ind.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_string</i>	string of character
<i>in</i>	<i>id_ind</i>	indice
<i>in</i>	<i>cd_sep</i>	separator character

Returns

return the element on index *id_ind*

11.27.2.11 PURE CHARACTER(LEN=lc) function, public fct::fct_upper (character(*), intent(in) *cd_var*)

This function convert string character lower case to upper case.

The function IACHAR returns the ASCII value of the character passed as argument. The ASCII code has the uppercase alphabet starting at code 65, and the lower case one at code 101, therefore IACHAR('a')- IACHAR('A') would be the difference between the uppercase and the lowercase codes.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>cd_var</code>	character
-----------------	---------------------	-----------

Returns

upper case character

The documentation for this module was generated from the following file:

- src/function.f90

11.28 fct::fct_str Interface Reference**Public Member Functions**

- PURE CHARACTER(LEN=lc) function [fct__i1_str](#) (bd_var)
This function convert integer(1) to string character.
- PURE CHARACTER(LEN=lc) function [fct__i2_str](#) (sd_var)
This function convert integer(2) to string character.
- PURE CHARACTER(LEN=lc) function [fct__i4_str](#) (id_var)
This function convert integer(4) to string character.
- PURE CHARACTER(LEN=lc) function [fct__i8_str](#) (kd_var)
This function convert integer(8) to string character.
- PURE CHARACTER(LEN=lc) function [fct__r4_str](#) (rd_var)
This function convert real(4) to string character.
- PURE CHARACTER(LEN=lc) function [fct__r8_str](#) (dd_var)
This function convert real(8) to string character.
- PURE CHARACTER(LEN=lc) function [fct__l_str](#) (ld_var)
This function convert logical to string character.

11.28.1 Member Function/Subroutine Documentation**11.28.1.1 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__i1_str (integer(i1), intent(in) bd_var)**

This function convert integer(1) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>bd_var</code>	integer(1) variable
-----------------	---------------------	---------------------

Returns

character of this integer variable

11.28.1.2 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__i2_str (integer(i2), intent(in) *sd_var*)

This function convert integer(2) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>sd_var</i>	integer(2) variable
-----------	---------------	---------------------

Returns

character of this integer variable

11.28.1.3 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__i4_str (integer(i4), intent(in) *id_var*)

This function convert integer(4) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>id_var</i>	integer(4) variable
-----------	---------------	---------------------

Returns

character of this integer variable

11.28.1.4 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__i8_str (integer(i8), intent(in) *kd_var*)

This function convert integer(8) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>kd_var</i>	integer(8) variable
-----------	---------------	---------------------

Returns

character of this integer variable

11.28.1.5 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__l_str (logical, intent(in) *ld_var*)

This function convert logical to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>ld_var</i>	logical variable
-----------	---------------	------------------

Returns

character of this integer variable

11.28.1.6 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__r4_str (real(sp), intent(in) *rd_var*)

This function convert real(4) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>rd_var</i>	real(4) variable
-----------	---------------	------------------

Returns

character of this real variable

11.28.1.7 PURE CHARACTER(LEN=lc) function fct::fct_str::fct__r8_str (real(dp), intent(in) *dd_var*)

This function convert real(8) to string character.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>dd_var</code>	real(8) variable
-----------------	---------------------	------------------

Returns

character of this real variable

The documentation for this interface was generated from the following file:

- `src/function.f90`

11.29 file Module Reference

This module manage file structure.

Data Types

- interface [file_clean](#)
- interface [file_copy](#)
- interface [file_del_att](#)
- interface [file_del_var](#)
- interface [file_rename](#)
- type [tfile](#)

Public Member Functions

- TYPE(TFILE) function, public [file_init](#) (`cd_file`, `cd_type`, `ld_wrt`, `id_ew`, `id_perio`, `id_pivot`, `cd_grid`)
This function initialize file structure.
- CHARACTER(LEN=lc) function, public [file_get_type](#) (`cd_file`)
This function get type of file, given file name.
- LOGICAL function, public [file_check_var_dim](#) (`td_file`, `td_var`)
This function check if variable dimension to be used have the same length that in file structure.
- subroutine, public [file_add_var](#) (`td_file`, `td_var`)
*This subroutine add a variable structure in a file structure.
Do not overwrite, if variable already in file structure.*
- subroutine, public [file_move_var](#) (`td_file`, `td_var`)
This subroutine overwrite variable structure in file structure.
- subroutine, public [file_add_att](#) (`td_file`, `td_att`)
*This subroutine add a global attribute in a file structure.
Do not overwrite, if attribute already in file structure.*
- subroutine, public [file_move_att](#) (`td_file`, `td_att`)
This subroutine move a global attribute structure from file structure.
- subroutine, public [file_add_dim](#) (`td_file`, `td_dim`)
This subroutine add a dimension structure in file structure. Do not overwrite, if dimension already in file structure.
- subroutine, public [file_del_dim](#) (`td_file`, `td_dim`)
This subroutine delete a dimension structure in file structure.
- subroutine, public [file_move_dim](#) (`td_file`, `td_dim`)
This subroutine move a dimension structure in file structure.
- subroutine, public [file_print](#) (`td_file`)
This subroutine print some information about file structure.
- CHARACTER(LEN=lc) function, public [file_add_suffix](#) (`cd_file`, `cd_type`)

This function add suffix to file name.

- INTEGER(i4) function, public `file_get_id` (td_file, cd_name)

This function return the file id, in a array of file structure, given file name.

- integer(i4) function `file_get_unit` (td_file)

This function get the next unused unit in array of file structure.

11.29.1 Detailed Description

This module manage file structure.

```
define type TFILE:<br/>
```

```
TYPE(tfile) :: t1_file
```

to initialize a file structure:

```
t1_file=file_init(cd_file [,cd_type] [,ld_wrt] [,cd_grid])
```

- cd_file is the file name
- cd_type is the type of the file ('cdf', 'dimg') [optional]
- ld_wrt file in write mode or not [optional] - cd_grid is the grid type (default 'ARAKAWA-C')

to get file name:

- t1_file%c_name

to get file id (units):

- t1_file%i_id

to get the type of the file (cdf, cdf4, dimg):

- t1_file%c_type

to know if file was open in write mode:

- t1_file%l_wrt

to get the record length of the file:

- t1_file%i_recl

Files variables

to get the number of variable in the file:

- t1_file%i_nvar

to get the array of variable structure associated to the file:

- t1_file%t_var(:)

Files attributes

to get the number of global attributes of the file:

- `tl_file%i_natt`

to get the array of attributes structure associated to the file:

- `tl_file%t_att(:)`

Files dimensions

to get the number of dimension used in the file:

- `tl_file%i_ndim`

to get the array of dimension structure (4 elts) associated to the file:

- `tl_file%t_dim(:)`

to print information about file structure:

```
CALL file_print(td_file)
```

to clean file structure:

```
CALL file_clean(td_file)
```

to add a global attribute structure in file structure:

```
CALL file_add_att(td_file, td_att)
```

- `td_att` is an attribute structure

to add a dimension structure in file structure:

```
CALL file_add_dim(td_file, td_dim)
```

- `td_dim` is a dimension structure

to add a variable structure in file structure:

```
CALL file_add_var(td_file, td_var)
```

- `td_var` is a variable structure

to delete a global attribute structure in file structure:

```
CALL file_del_att(td_file, td_att)
```

- `td_att` is an attribute structure

to delete a dimension structure in file structure:

```
CALL file_del_dim(td_file, td_dim)
```

- `td_dim` is a dimension structure

to delete a variable structure in file structure:

```
CALL file_del_var(td_file, td_var)
```

- `td_var` is a variable structure

to overwrite one attribute structure in file structure:

```
CALL file_move_att(td_file, td_att)
```

- `td_att` is an attribute structure

to overwrite one dimension structure in file structure:

```
CALL file_move_dim(td_file, td_dim)
```

- `td_dim` is a dimension structure

to overwrite one variable structure in file structure:

```
CALL file_move_var(td_file, td_var)
```

- `td_var` is a variable structure

to check if file and variable structure share same dimension:

```
ll_check_dim = file_check_var_dim(td_file, td_var)
```

- `td_var` is a variable structure

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- Fix memory leaks bug

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.29.2 Member Function/Subroutine Documentation

11.29.2.1 subroutine, public `file::file_add_att (type(tfile), intent(inout) td_file, type(tatt), intent(in) td_att)`

This subroutine add a global attribute in a file structure.

Do not overwrite, if attribute already in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_att</i>	attribute structure

11.29.2.2 subroutine, public file::file_add_dim (type(tfile), intent(inout) *td_file*, type(tdim), intent(in) *td_dim*)

This subroutine add a dimension structure in file structure. Do not overwrite, if dimension already in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- do not reorder dimension, before put in file

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.29.2.3 CHARACTER(LEN=lc) function, public file::file_add_suffix (character(len=*), intent(in) *cd_file*, character(len=*), intent(in) *cd_type*)

This function add suffix to file name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_file</i>	file structure
-----------	----------------	----------------

Returns

file name

11.29.2.4 subroutine, public file::file_add_var (type(tfile), intent(inout) *td_file*, type(tvar), intent(inout) *td_var*)

This subroutine add a variable structure in a file structure.

Do not overwrite, if variable already in file structure.

Note

variable value is suppose to be ordered ('x','y','z','t')

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add dimension in file if need be
- do not reorder dimension from variable, before put in file

September, 2015

- check variable dimension expected

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_var</i>	variable structure

11.29.2.5 LOGICAL function, public file::file_check_var_dim (type(tfile), intent(in) *td_file*, type(tvar), intent(in) *td_var*)

This function check if variable dimension to be used have the same length that in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_var</i>	variable structure

Returns

true if dimension of variable and file structure agree

11.29.2.6 subroutine, public file::file_del_dim (type(tfile), intent(inout) *td_file*, type(tdim), intent(in) *td_dim*)

This subroutine delete a dimension structure in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.29.2.7 INTEGER(i4) function, public file::file_get_id (type(tfile), dimension(:), intent(in) *td_file*, character(len=*) , intent(in) *cd_name*)

This function return the file id, in a array of file structure, given file name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_file</i>	array of file structure
<i>in</i>	<i>cd_name</i>	file name

Returns

file id in array of file structure (0 if not found)

11.29.2.8 CHARACTER(LEN=lc) function, public file::file_get_type (character(len=*) , intent(in) *cd_file*)

This function get type of file, given file name.

Actually it get suffix of the file name, and compare it to 'nc', 'cdf' or 'dimg'

If no suffix or suffix not identify, we assume file is dimg

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_file</i>	file name
-----------	----------------	-----------

Returns

type of file

11.29.2.9 integer(i4) function file::file_get_unit (type(tfile), dimension(:), intent(in) *td_file*)

This function get the next unused unit in array of file structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in	<i>td_file</i>	array of file
----	----------------	---------------

11.29.2.10 TYPE(TFILE) function, public file::file_init (character(len=*), intent(in) *cd_file*, character(len=*), intent(in), optional *cd_type*, logical, intent(in), optional *ld_wrt*, integer(i4), intent(in), optional *id_ew*, integer(i4), intent(in), optional *id_perio*, integer(i4), intent(in), optional *id_pivot*, character(len=*), intent(in), optional *cd_grid*)

This function initialize file structure.

If *cd_type* is not specify, check if file name include '.nc' or '.dimg'

Optionally, you could specify:

- write mode (default .FALSE., *ld_wrt*) - grid type (default: 'ARAKAWA-C')

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_file</i>	file name
in	<i>cd_type</i>	file type ('cdf', 'dimg')
in	<i>ld_wrt</i>	write mode (default .FALSE.)
in	<i>id_ew</i>	east-west overlap
in	<i>id_perio</i>	NEMO periodicity index
in	<i>id_pivot</i>	NEMO pivot point index F(0),T(1)
in	<i>cd_grid</i>	grid type (default 'ARAKAWA-C')

Returns

file structure

11.29.2.11 subroutine, public file::file_move_att (type(tfile), intent(inout) *td_file*, type(tatt), intent(in) *td_att*)

This subroutine move a global attribute structure from file structure.

Warning

change attribute id in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_att</i>	attribute structure

11.29.2.12 subroutine, public file::file_move_dim (type(tfile), intent(inout) *td_file*, type(tdim), intent(in) *td_dim*)

This subroutine move a dimension structure in file structure.

Warning

change dimension order in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.29.2.13 subroutine, public file::file_move_var (type(tfile), intent(inout) *td_file*, type(tvar), intent(in) *td_var*)

This subroutine overwrite variable structure in file structure.

Warning

change variable id in file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
<i>in</i>	<i>td_var</i>	variable structure

11.29.2.14 subroutine, public file::file_print (type(tfile), intent(in) *td_file*)

This subroutine print some information about file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
-----------------	----------------------	----------------

The documentation for this module was generated from the following file:

- `src/file.f90`

11.30 file::file_clean Interface Reference

Public Member Functions

- subroutine [file__clean_unit](#) (`td_file`)
This subroutine clean file strcuture.
- subroutine [file__clean_arr](#) (`td_file`)
This subroutine clean file array of file strcuture.

11.30.1 Member Function/Subroutine Documentation

11.30.1.1 subroutine `file::file_clean::file__clean_arr` (`type(tfile)`, `dimension(:)`, `intent(inout) td_file`)

This subroutine clean file array of file strcuture.

Author

J.Paul

Date

Marsh, 2014 - Inital version

Parameters

<code>in, out</code>	<code>td_file</code>	array file strcuture
----------------------	----------------------	----------------------

11.30.1.2 subroutine `file::file_clean::file__clean_unit` (`type(tfile)`, `intent(inout) td_file`)

This subroutine clean file strcuture.

Author

J.Paul

Date

November, 2013 - Inital version

Parameters

<code>in, out</code>	<code>td_file</code>	file strcuture
----------------------	----------------------	----------------

The documentation for this interface was generated from the following file:

- `src/file.f90`

11.31 file::file_copy Interface Reference

Public Member Functions

- type(tfile) function `file__copy_unit` (td_file)
This subroutine copy file structure in another one.
- type(tfile) function,
dimension(size(td_file(:))) `file__copy_arr` (td_file)
This subroutine copy a array of file structure in another one.

11.31.1 Member Function/Subroutine Documentation

11.31.1.1 type(tfile) function, dimension(size(td_file(:))) file::file_copy::file__copy_arr (type(tfile), dimension(:), intent(in) td_file)

This subroutine copy a array of file structure in another one.

file variable and attribute value are copied in a temporary array, so input and output file structure value do not point on the same "memory cell", and so on are independant.

Note

new file is assume to be closed.

Warning

do not use on the output of a function who create or read an structure (ex: `tl_file=file_copy(file_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

in	<i>td_file</i>	file structure
----	----------------	----------------

Returns

copy of input array of file structure

11.31.1.2 type(tfile) function file::file_copy::file__copy_unit (type(tfile), intent(in) td_file)

This subroutine copy file structure in another one.

file variable and attribute value are copied in a temporary array, so input and output file structure value do not point on the same "memory cell", and so on are independant.

Note

new file is assume to be closed.

Warning

do not use on the output of a function who create or read an structure (ex: `tl_file=file_copy(file_init())` is forbidden). This will create memory leaks.

to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_file</code>	file structure
-----------------	----------------------	----------------

Returns

copy of input file structure

The documentation for this interface was generated from the following file:

- `src/file.f90`

11.32 file::file_del_att Interface Reference

Public Member Functions

- subroutine [file__del_att_name](#) (`td_file`, `cd_name`)
This subroutine delete a global attribute structure in file structure, given attribute name.
- subroutine [file__del_att_str](#) (`td_file`, `td_att`)
This subroutine delete a global attribute structure from file structure, given attribute structure.

11.32.1 Member Function/Subroutine Documentation

11.32.1.1 subroutine `file::file_del_att::file__del_att_name` (`type(tfile)`, `intent(inout) td_file`, `character(len=*)`, `intent(in) cd_name`)

This subroutine delete a global attribute structure in file structure, given attribute name.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- define local attribute structure to avoid mistake with pointer

Parameters

in, out	<i>td_file</i>	file structure
in	<i>cd_name</i>	attribute name

11.32.1.2 subroutine file::file_del_att::file__del_att_str (type(tfile), intent(inout) *td_file*, type(tatt), intent(in) *td_att*)

This subroutine delete a global attribute structure from file structure, given attribute structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_file</i>	file structure
in	<i>td_att</i>	attribute structure

The documentation for this interface was generated from the following file:

- src/file.f90

11.33 file::file_del_var Interface Reference

Public Member Functions

- subroutine [file__del_var_name](#) (*td_file*, *cd_name*)
This subroutine delete a variable structure in file structure, given variable name or standard name.
- subroutine [file__del_var_str](#) (*td_file*, *td_var*)
This subroutine delete a variable structure in file structure, given variable structure.

11.33.1 Member Function/Subroutine Documentation

11.33.1.1 subroutine file::file_del_var::file__del_var_name (type(tfile), intent(inout) *td_file*, character(len=*) *cd_name*)

This subroutine delete a variable structure in file structure, given variable name or standard name.

Author

J.Paul

Date

November, 2013 - Initial Version
February, 2015

- define local variable structure to avoid mistake with pointer

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
<code>in</code>	<code>cd_name</code>	variable name or standard name

11.33.1.2 subroutine `file::file_del_var::file__del_var_str (type(tfile), intent(inout) td_file, type(tvar), intent(in) td_var)`

This subroutine delete a variable structure in file structure, given variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
<code>in</code>	<code>td_var</code>	variable structure

The documentation for this interface was generated from the following file:

- `src/file.f90`

11.34 file::file_rename Interface Reference

Public Member Functions

- CHARACTER(LEN=lc) function [file__rename_char](#) (`cd_file`, `id_num`)
This function rename file name, given processor number.
- TYPE(TFILE) function [file__rename_str](#) (`td_file`, `id_num`)
This function rename file name, given file structure.

11.34.1 Member Function/Subroutine Documentation

11.34.1.1 CHARACTER(LEN=lc) function `file::file_rename::file__rename_char (character(len=*), intent(in) cd_file, integer(i4), intent(in), optional id_num)`

This function rename file name, given processor number.

If no processor number is given, return file name without number If processor number is given, return file name with new number

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_file</i>	file structure
<i>in</i>	<i>id_num</i>	processor number (start to 1)

Returns

file name

11.34.1.2 TYPE(TFILE) function file::file_rename::file__rename_str (type(tfile), intent(in) *td_file*, integer(i4), intent(in), optional *id_num*)

This function rename file name, given file structure.

If no processor number is given, return file name without number I processor number is given, return file name with new number

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_file</i>	file structure
<i>in</i>	<i>id_num</i>	processor number (start to 1)

Returns

file structure

The documentation for this interface was generated from the following file:

- src/file.f90

11.35 filter Module Reference

This module is filter manager.

Data Types

- interface [filter_fill_value](#)

11.35.1 Detailed Description

This module is filter manager.

Filtering method to be used is specify inside variable structure, as array of string character.

td_var%c_filter(1) string character is the filter name choose between:

- 'hann'

- $rad < cutoff$: $filter = 0.5 + 0.5 * COS(\pi * \frac{rad}{cutoff})$
- $rad > cutoff$: $filter = 0$
- 'hamming'
 - $rad < cutoff$: $filter = 0.54 + 0.46 * COS(\pi * \frac{rad}{cutoff})$
 - $rad > cutoff$: $filter = 0$
- 'blackman'
 - $rad < cutoff$: $filter = 0.42 + 0.5 * COS(\pi * \frac{rad}{cutoff}) + 0.08 * COS(2\pi * \frac{rad}{cutoff})$
 - $rad > cutoff$: $filter = 0$
- 'gauss'
 - $filter = exp(-(\alpha * rad^2)/(2 * cutoff^2))$
- 'butterworth'
 - $filter = 1/(1 + (rad^2/cutoff^2)^\alpha)$ with $rad = \sqrt{(dist - radius)^2}$

td_var%c_filter(2) string character is the number of turn to be done

td_var%c_filter(3) string character is the cut-off frequency td_var%c_filter(4) string character is the halo radius (count in number of mesh grid)

td_var%c_filter(5) string character is the alpha parameter (for gauss and butterworth method)

Note

Filter method could be specify for each variable in namelist *namvar*, defining string character *cn_varinfo*. None by default.

Filter method parameters are informed inside bracket.

- α parameter is added for *gauss* and *butterworth* methods

The number of turn is specify using '*' separator.

Example:

- `cn_varinfo='varname1:flt=2*hamming(cutoff, radius)', 'varname2:flt=gauss(cutoff, radius, alpha)'`

to filter variable value:

```
CALL filter_fill_value( td_var )
```

- `td_var` is variable structure

Author

J.Paul

Date

November, 2013 - Initial Version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

The documentation for this module was generated from the following file:

- `src/filter.f90`

11.36 filter::filter_fill_value Interface Reference

Public Member Functions

- subroutine [filter__fill_value_wrapper](#) (td_var)
This subroutine filter variable value.

11.36.1 Member Function/Subroutine Documentation

11.36.1.1 subroutine filter::filter_fill_value::filter__fill_value_wrapper (type(tvar), intent(inout) td_var)

This subroutine filter variable value.

it checks if filtering method is available, gets parameter value, and launch filter__fill_value

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	td_var	variable structure
---------	--------	--------------------

The documentation for this interface was generated from the following file:

- src/filter.f90

11.37 global Module Reference

This module defines global variables and parameters.

Public Attributes

- integer(i4), parameter, public [ip_maxvar](#) =200
maximum number of variable
- integer(i4), parameter, public [ip_maxmtx](#) =50
matrix variable maximum dimension (cf create_bathy)
- integer(i4), parameter, public [ip_maxseg](#) =10
maximum number of segment for each boundary
- integer(i4), parameter, public [ip_nsep](#) =2
number of separator listed
- character(1), dimension([ip_nsep](#)),
parameter, public [cp_sep](#) = (';', '_')
list of separator
- integer(i4), parameter, public [ip_ncom](#) =2
number of comment character listed
- character(1), dimension([ip_ncom](#)),
parameter, public [cp_com](#) = ('#', '!')
list of comment character

- integer(i4), parameter, public `ip_ghost` =1
number of ghost cell
- integer(i4), parameter, public `ip_ninterp` =3
- character(len=lc), dimension(ip_ninterp),
parameter, public `cp_interp_list` = (/ 'nearest', 'cubic', 'linear' /)
- integer(i4), parameter, public `ip_nextrap` =2
- character(len=lc), dimension(ip_nextrap),
parameter, public `cp_extrap_list` = (/ 'dist_weight', 'min_error' /)
- integer(i4), parameter, public `ip_nfilter` =5
- character(len=lc), dimension(ip_nfilter),
parameter, public `cp_filter_list` = (/ 'butterworth', 'blackman', 'hamming', 'hann', 'gauss' /)
- real(dp), parameter `dp_fill_i1` =NF90_FILL_BYTE
byte fill value
- real(dp), parameter `dp_fill_i2` =NF90_FILL_SHORT
short fill value
- real(dp), parameter `dp_fill_i4` =NF90_FILL_INT
INT fill value.
- real(dp), parameter `dp_fill_sp` =NF90_FILL_FLOAT
real fill value
- real(dp), parameter, public `dp_fill` =NF90_FILL_DOUBLE
double fill value
- integer(i4), parameter, public `ip_npoint` =4
- integer(i4), parameter, public `jp_t` =1
- integer(i4), parameter, public `jp_u` =2
- integer(i4), parameter, public `jp_v` =3
- integer(i4), parameter, public `jp_f` =4
- character(len=1), dimension(ip_npoint),
parameter, public `cp_grid_point` = (/ 'T', 'U', 'V', 'F' /)
- integer(i4), parameter `ip_maxdimcfg` =10
maximum allowed dimension in configuration file
- integer(i4), parameter, public `ip_maxdim` =4
- integer(i4), parameter, public `jp_i` =1
- integer(i4), parameter, public `jp_j` =2
- integer(i4), parameter, public `jp_k` =3
- integer(i4), parameter, public `jp_l` =4
- character(len=ip_maxdim),
parameter, public `cp_dimorder` = 'xyzt'
dimension order to output
- integer(i4), parameter, public `ip_ncard` =4
- character(len=lc), dimension(ip_ncard),
parameter, public `cp_card` = (/ 'north', 'south', 'east', 'west' /)
- integer(i4), parameter, public `jp_north` =1
- integer(i4), parameter, public `jp_south` =2
- integer(i4), parameter, public `jp_east` =3
- integer(i4), parameter, public `jp_west` =4
- integer(i4), parameter `ip_maxdumcfg` = 10
maximum dummy variable, dimension, or attribute in configuration file

11.37.1 Detailed Description

This module defines global variables and parameters.

Author

J.paul

Date

November, 2013 - Initial Version

September, 2015

- define fill value for each variable type

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

The documentation for this module was generated from the following file:

- src/global.f90

11.38 grid Module Reference

This module is grid manager.

Data Types

- interface [grid_get_closest](#)
- interface [grid_get_coarse_index](#)
- interface [grid_get_ew_overlap](#)
- interface [grid_get_fine_offset](#)
- interface [grid_get_ghost](#)
- interface [grid_get_info](#)
- interface [grid_get_perio](#)
- interface [grid_get_pivot](#)

Public Member Functions

- LOGICAL function, public [grid_is_north_fold](#) (td_lat)
This subroutine check if there is north fold.
- subroutine, public [grid_check_dom](#) (td_coord, id_imin, id_imax, id_jmin, id_jmax)
This subroutine check domain validity.
- logical function, public [grid_is_global](#) (td_lon, td_lat)
This function check if grid is global or not.
- real(dp) function, dimension(size(dd_lon(:,:)),
[dim=1](#)),size(dd_lon(:,:), [dim=2](#))),
public [grid_distance](#) (dd_lon, dd_lat, dd_lonA, dd_latA)
This function compute the distance between a point A and grid points.
- subroutine, public [grid_check_coincidence](#) (td_coord0, td_coord1, id_imin0, id_imax0, id_jmin0, id_jmax0,
id_rho)
This subroutine check fine and coarse grid coincidence.

- subroutine, public `grid_add_ghost` (td_var, id_ghost)
This subroutine add ghost cell at boundaries.
- subroutine, public `grid_del_ghost` (td_var, id_ghost)
This subroutine delete ghost cell at boundaries.
- integer(i4) function,
dimension(td_var%t_dim(1)%i_len,td_var%t_dim(2)%i_len),
public `grid_split_domain` (td_var, id_level)
This subroutine compute closed sea domain.
- subroutine, public `grid_fill_small_dom` (td_var, id_mask, id_minsize)
This subroutine fill small closed sea with fill value.
- subroutine, public `grid_fill_small_msk` (id_mask, id_minsize)
This subroutine fill small domain inside bigger one.

11.38.1 Detailed Description

This module is grid manager.

to get NEMO pivot point index:


```
il_pivot=grid_get_pivot(td_file)
```

- il_pivot is NEMO pivot point index F(0), T(1)
- td_file is mpp structure

to get NEMO periodicity index:

```
il_perio=grid_get_perio(td_file)
```

- il_perio is NEMO periodicity index (0,1,2,3,4,5,6)
- td_file is mpp structure

to check domain validity:

```
CALL grid_check_dom(td_coord, id_imin, id_imax, id_jmin, id_jmax)
```

- td_coord is coordinates mpp structure
- id_imin is i-direction lower left point indice
- id_imax is i-direction upper right point indice
- id_jmin is j-direction lower left point indice
- id_jmax is j-direction upper right point indice

to get closest coarse grid indices of fine grid domain:

```
il_index(:,:)=grid_get_coarse_index(td_coord0, td_coord1,  
[id_rho,] [cd_point])
```

or

```
il_index(:,:)=grid_get_coarse_index(td_lon0, td_lat0, td_coord1,  
[id_rho,] [cd_point])
```

or

```
il_index(:,:)=grid_get_coarse_index(td_coord0, td_lon1, td_lat1,
                                   [id_rho,] [cd_point])
```

or

```
il_index(:,:)=grid_get_coarse_index(td_lon0, td_lat0, td_lon1, td_lat1,
                                   [id_rho,] [cd_point])
```

- `il_index(:,:)` is coarse grid indices (/ (/ imin0, imax0 /), (/ jmin0, jmax0 /) /)
- `td_coord0` is coarse grid coordinate mpp structure
- `td_coord1` is fine grid coordinate mpp structure
- `td_lon0` is coarse grid longitude variable structure
- `td_lat0` is coarse grid latitude variable structure
- `td_lon1` is fine grid longitude variable structure
- `td_lat1` is fine grid latitude variable structure
- `id_rho` is array of refinement factor (default 1)
- `cd_point` is Arakawa grid point (default 'T')

to know if grid is global:

```
ll_global=grid_is_global(td_lon, td_lat)
```

- `td_lon` is longitude variable structure
- `td_lat` is latitude variable structure

to know if grid contains north fold:

```
ll_north=grid_is_north_fold(td_lat)
```

- `td_lat` is latitude variable structure

to get coarse grid indices of the closest point from one fine grid point:

```
il_index(:)=grid_get_closest(dd_lon0(:,:), dd_lat0(:,:), dd_lon1, dd_lat1
                             [,dd_fill] [,cd_pos])
```

- `il_index(:)` is coarse grid indices (/ i0, j0 /)
- `dd_lon0` is coarse grid array of longitude value (real(8))
- `dd_lat0` is coarse grid array of latitude value (real(8))
- `dd_lon1` is fine grid longitude value (real(8))
- `dd_lat1` is fine grid latitude value (real(8))
- `dd_fill`
- `cd_pos`

to compute distance between a point A and grid points:

```
il_dist(:,:)=grid_distance(dd_lon, dd_lat, dd_lona, dd_lata)
```

- `il_dist(:,:)` is array of distance between point A and grid points
- `dd_lon` is array of longitude value (real(8))
- `dd_lat` is array of longitude value (real(8))
- `dd_lonA` is longitude of point A (real(8))
- `dd_latA` is latitude of point A (real(8))

to get offset between fine grid and coarse grid:

```
il_offset(:,:)=grid_get_fine_offset(td_coord0,
                                   id_imin0, id_jmin0, id_imax0, id_jmax0,
                                   td_coord1
                                   [,id_rho] [,cd_point])
```

or

```
il_offset(:,:)=grid_get_fine_offset(dd_lon0, dd_lat0,
                                   id_imin0, id_jmin0, id_imax0, id_jmax0,
                                   td_coord1
                                   [,id_rho] [,cd_point])
```

or

```
il_offset(:,:)=grid_get_fine_offset(td_coord0,
                                   id_imin0, id_jmin0, id_imax0, id_jmax0,
                                   dd_lon1, dd_lat1
                                   [,id_rho] [,cd_point])
```

or

```
il_offset(:,:)=grid_get_fine_offset(dd_lon0, dd_lat0,
                                   id_imin0, id_jmin0, id_imax0, id_jmax0,
                                   dd_lon1, dd_lat1
                                   [,id_rho] [,cd_point])
```

- `il_offset(:,:)` is offset array (/ (/ `i_offset_left`, `i_offset_right` /), (/ `j_offset_lower`, `j_offset_upper` /) /)
- `td_coord0` is coarse grid coordinate mpp structure
- `dd_lon0` is coarse grid longitude array (real(8))
- `dd_lat0` is coarse grid latitude array (real(8))
- `id_imin0` is coarse grid lower left corner i-indice of fine grid domain
- `id_jmin0` is coarse grid lower left corner j-indice of fine grid domain
- `id_imax0` is coarse grid upper right corner i-indice of fine grid domain
- `id_jmax0` is coarse grid upper right corner j-indice of fine grid domain
- `td_coord1` is fine grid coordinate mpp structure
- `dd_lon1` is fine grid longitude array (real(8))
- `dd_lat1` is fine grid latitude array (real(8))
- `id_rho` is array of refinement factor (default 1)
- `cd_point` is Arakawa grid point (default 'T')

to check fine and coarse grid coincidence:

```
CALL grid_check_coincidence(td_coord0, td_coord1,
                           id_imin0, id_imax0, id_jmin0, id_jmax0
                           ,id_rho)
```

- td_coord0 is coarse grid coordinate mpp structure
- td_coord1 is fine grid coordinate mpp structure
- id_imin0 is coarse grid lower left corner i-indice of fine grid domain
- id_imax0 is coarse grid upper right corner i-indice of fine grid domain
- id_jmin0 is coarse grid lower left corner j-indice of fine grid domain
- id_jmax0 is coarse grid upper right corner j-indice of fine grid domain
- id_rho is array of refinement factor

to add ghost cell at boundaries:

```
CALL grid_add_ghost(td_var, id_ghost)
```

- td_var is array of variable structure
- id_ghost is 2D array of ghost cell factor

to delete ghost cell at boundaries:

```
CALL grid_del_ghost(td_var, id_ghost)
```

- td_var is array of variable structure
- id_ghost is 2D array of ghost cell factor

to get ghost cell factor (use or not):

```
il_factor(:)= grid_get_ghost( td_var )
```

or

```
il_factor(:)= grid_get_ghost( td_mpp )
```

- il_factor(:) is array of ghost cell factor (0 or 1)
- td_var is variable structure
- td_mpp is mpp sturcture

to compute closed sea domain:

```
il_mask(:,:)=grid_split_domain(td_var, [id_level])
```

- il_mask(:,:) is domain mask
- td_var is variable strucutre
- id_level is level to be used [optional]

to fill small closed sea with _FillValue:

```
CALL grid_fill_small_dom(td_var, id_mask, [id_minsize])
```

- td_var is variable structure
- id_mask is domain mask (from grid_split_domain)
- id_minsize is minimum size of sea to be kept [optional]

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header

October, 2014

- use mpp file structure instead of file

February, 2015

- add function `grid_fill_small_msk` to fill small domain inside bigger one

February, 2016

- improve way to check coincidence (bug fix)
- manage grid cases for T,U,V or F point, with even or odd refinement (bug fix)

April, 2016

- add function to get closest grid point using coarse grid coordinates structure

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.38.2 Member Function/Subroutine Documentation

11.38.2.1 subroutine, public `grid::grid_add_ghost (type(tvar), intent(inout) td_var, integer(i4), dimension(2,2), intent(in) id_ghost)`

This subroutine add ghost cell at boundaries.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<code>in, out</code>	<code><i>td_var</i></code>	array of variable structure
<code>in</code>	<code><i>id_ghost</i></code>	array of ghost cell factor

11.38.2.2 subroutine, public `grid::grid_check_coincidence (type(tmpp), intent(in) td_coord0, type(tmpp), intent(in) td_coord1, integer(i4), intent(in) id_imin0, integer(i4), intent(in) id_imax0, integer(i4), intent(in) id_jmin0, integer(i4), intent(in) id_jmax0, integer(i4), dimension(:), intent(in) id_rho)`

This subroutine check fine and coarse grid coincidence.

Author

J.Paul

Date

November, 2013- Initial Version

October, 2014

- work on mpp file structure instead of file structure

February, 2016

- use F-point to check coincidence for even refinement
- use F-point estimation, if can not read it.

Parameters

in	<i>td_coord0</i>	coarse grid coordinate file structure
in	<i>td_coord1</i>	fine grid coordinate file structure
in	<i>id_imin0</i>	coarse grid lower left corner i-indice of fine grid domain
in	<i>id_imax0</i>	coarse grid upper right corner i-indice of fine grid domain
in	<i>id_jmin0</i>	coarse grid lower left corner j-indice of fine grid domain
in	<i>id_jmax0</i>	coarse grid upper right corner j-indice of fine grid domain
in	<i>id_rho</i>	array of refinement factor

11.38.2.3 subroutine, public grid::grid_check_dom (type(tmpp), intent(in) *td_coord*, integer(i4), intent(in) *id_imin*, integer(i4), intent(in) *id_imax*, integer(i4), intent(in) *id_jmin*, integer(i4), intent(in) *id_jmax*)

This subroutine check domain validity.

If maximum latitude greater than 88°N, program will stop.

Note

Not able to manage north fold for now.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>cd_coord</i>	coordinate file
in	<i>id_imin</i>	i-direction lower left point indice
in	<i>id_imax</i>	i-direction upper right point indice
in	<i>id_jmin</i>	j-direction lower left point indice
in	<i>id_jmax</i>	j-direction upper right point indice

11.38.2.4 subroutine, public grid::grid_del_ghost (type(tvar), intent(inout) *td_var*, integer(i4), dimension(2,2), intent(in) *id_ghost*)

This subroutine delete ghost cell at boundaries.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_var</i>	array of variable structure
<i>in</i>	<i>id_ghost</i>	array of ghost cell factor

11.38.2.5 `real(dp) function, dimension(size(dd_lon(:,:),dim=1), size(dd_lon(:,:),dim=2)), public grid::grid_distance (real(dp), dimension(:,:), intent(in) dd_lon, real(dp), dimension(:,:), intent(in) dd_lat, real(dp), intent(in) dd_lonA, real(dp), intent(in) dd_latA)`

This function compute the distance between a point A and grid points.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>dd_lon</i>	grid longitude array
<i>in</i>	<i>dd_lat</i>	grid latitude array
<i>in</i>	<i>dd_lonA</i>	longitude of point A
<i>in</i>	<i>dd_latA</i>	latitude of point A
<i>in</i>	<i>dd_fill</i>	

Returns

array of distance between point A and grid points.

11.38.2.6 `subroutine, public grid::grid_fill_small_dom (type(tvar), intent(inout) td_var, integer(i4), dimension(:,:), intent(in) id_mask, integer(i4), intent(in), optional id_minsize)`

This subroutine fill small closed sea with fill value.

the minimum size (number of point) of closed sea to be kept could be sepcify with *id_minsize*. By default only the biggest sea is preserve.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>id_mask</i>	domain mask (from <code>grid_split_domain</code>)
<i>in</i>	<i>id_minsize</i>	minimum size of sea to be kept

11.38.2.7 subroutine, public `grid::grid_fill_small_msk` (`integer(i4)`, `dimension(:, :)`, `intent(inout) id_mask`, `integer(i4)`, `intent(in) id_minsize`)

This subroutine fill small domain inside bigger one.

the minimum size (number of point) of domain sea to be kept could be is sepcified with `id_minsize`. smaller domain are included in the one they are embedded.

Author

J.Paul

Date

Ferbruay, 2015 - Initial Version

Parameters

<i>in, out</i>	<i>id_mask</i>	domain mask (from <code>grid_split_domain</code>)
<i>in</i>	<i>id_minsize</i>	minimum size of sea to be kept

11.38.2.8 logical function, public `grid::grid_is_global` (`type(tvar)`, `intent(in) td_lon`, `type(tvar)`, `intent(in) td_lat`)

This function check if grid is global or not.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_lon</i>	longitude structure
<i>in</i>	<i>td_lat</i>	latitude structure

11.38.2.9 LOGICAL function, public `grid::grid_is_north_fold` (`type(tvar)`, `intent(in) td_lat`)

This subroutine check if there is north fold.

check if maximum latitude greater than 88°N

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_lat</i>	latitude variable structure
-----------	---------------	-----------------------------

11.38.2.10 `integer(i4) function, dimension(td_var%t_dim(1)%i_len, td_var%t_dim(2)%i_len), public grid::grid_split_domain (type(tvvar), intent(in) td_var, integer(i4), intent(in), optional id_level)`

This subroutine compute closed sea domain.

to each domain is associated a negative value id (from -1 to ...)

optionaly you could specify which level use (default 1)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_var</i>	variable strucutre
<i>in</i>	<i>id_level</i>	level

Returns

domain mask

The documentation for this module was generated from the following file:

- src/grid.f90

11.39 grid::grid_get_closest Interface Reference

Public Member Functions

- `integer(i4) function, dimension(2) grid__get_closest_str (td_coord0, dd_lon1, dd_lat1, cd_pos, dd_fill)`
This function return grid indices of the closest point from point (lon1,lat1)
- `integer(i4) function, dimension(2) grid__get_closest_arr (dd_lon0, dd_lat0, dd_lon1, dd_lat1, cd_pos, dd_fill)`
This function return grid indices of the closest point from point (lon1,lat1)

11.39.1 Member Function/Subroutine Documentation

11.39.1.1 `integer(i4) function, dimension(2) grid::grid_get_closest::grid__get_closest_arr (real(dp), dimension(:,:), intent(in) dd_lon0, real(dp), dimension(:,:), intent(in) dd_lat0, real(dp), intent(in) dd_lon1, real(dp), intent(in) dd_lat1, character(len=*), intent(in), optional cd_pos, real(dp), intent(in), optional dd_fill)`

This function return grid indices of the closest point from point (lon1,lat1)

Note

overlap band should have been already removed from coarse grid array of longitude and latitude, before running this function

if you add `cd_pos` argument, you could choice to return closest point at

- lower left (ll) of the point
- lower right (lr) of the point
- upper left (ul) of the point
- upper right (ur) of the point
- lower (lo) of the point
- upper (up) of the point
- left (le) of the point
- right (ri) of the point

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- change dichotomy method to manage ORCA grid

February, 2016

- add optional use of relative position

Parameters

<code>in</code>	<code>dd_lon0</code>	coarse grid array of longitude
<code>in</code>	<code>dd_lat0</code>	coarse grid array of latitude
<code>in</code>	<code>dd_lon1</code>	fine grid longitude
<code>in</code>	<code>dd_lat1</code>	fine grid latitude
<code>in</code>	<code>cd_pos</code>	relative position of grid point from point
<code>in</code>	<code>dd_fill</code>	fill value

Returns

coarse grid indices of closest point of fine grid point

11.39.1.2 `integer(i4) function, dimension(2) grid::grid_get_closest::grid_get_closest_str (type(tmpp), intent(in) td_coord0, real(dp), intent(in) dd_lon1, real(dp), intent(in) dd_lat1, character(len=*) , intent(in), optional cd_pos, real(dp), intent(in), optional dd_fill)`

This function return grid indices of the closest point from point (`lon1,lat1`)

Note

overlap band should have been already removed from coarse grid array of longitude and latitude, before running this function

if you add `cd_pos` argument, you could choice to return closest point at

- lower left (ll) of the point
- lower right (lr) of the point
- upper left (ul) of the point
- upper right (ur) of the point
- lower (lo) of the point
- upper (up) of the point
- left (le) of the point
- right (ri) of the point

Author

J.Paul

Date

April, 2016 - Initial Version

October, 2016

- use max of zero and east-west overlap instead of east-west overlap

Parameters

in	<code>td_coord0</code>	coarse grid coordinate mpp structure
in	<code>dd_lon1</code>	fine grid longitude
in	<code>dd_lat1</code>	fine grid latitude
in	<code>cd_pos</code>	relative position of grid point from point
in	<code>dd_fill</code>	fill value

Returns

coarse grid indices of closest point of fine grid point

The documentation for this interface was generated from the following file:

- `src/grid.f90`

11.40 `grid::grid_get_coarse_index` Interface Reference

Public Member Functions

- `integer(i4)` function,
dimension(2, 2) `grid__get_coarse_index_ff` (`td_coord0`, `td_coord1`, `id_rho`, `cd_point`)
This function get closest coarse grid indices of fine grid domain.
- `integer(i4)` function,
dimension(2, 2) `grid__get_coarse_index_cf` (`td_lon0`, `td_lat0`, `td_coord1`, `id_rho`, `cd_point`)

This function get closest coarse grid indices of fine grid domain.

- integer(i4) function,
dimension(2, 2) `grid__get_coarse_index_fc` (td_coord0, td_lon1, td_lat1, id_rho, cd_point)

This function get closest coarse grid indices of fine grid domain.

- integer(i4) function,
dimension(2, 2) `grid__get_coarse_index_cc` (td_lon0, td_lat0, td_lon1, td_lat1, id_rho, cd_point)

This function get closest coarse grid indices of fine grid domain.

11.40.1 Member Function/Subroutine Documentation

11.40.1.1 integer(i4) function, dimension(2,2) `grid::grid_get_coarse_index::grid__get_coarse_index_cc` (type(tvar), intent(in) *td_lon0*, type(tvar), intent(in) *td_lat0*, type(tvar), intent(in) *td_lon1*, type(tvar), intent(in) *td_lat1*, integer(i4), dimension(:), intent(in), optional *id_rho*, character(len=*), intent(in), optional *cd_point*)

This function get closest coarse grid indices of fine grid domain.

it use coarse and fine grid array of longitude and latitude. optionally, you could specify the array of refinement factor (default 1.) optionally, you could specify on which Arakawa grid point you want to work (default 'T')

Note

do not use ghost cell

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- check grid point
- take into account EW overlap

February, 2016

- use delta (lon or lat)
- manage cases for T,U,V or F point, with even or odd refinement

Parameters

in	<i>td_lon0</i>	coarse grid longitude
in	<i>td_lat0</i>	coarse grid latitude
in	<i>td_lon1</i>	fine grid longitude
in	<i>td_lat1</i>	fine grid latitude
in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point ('T';'U';'V';'F')

Returns

coarse grid indices ((/imin0, imax0/), (/jmin0, jmax0/))

Todo -check case boundary domain on overlap band

11.40.1.2 `integer(i4) function, dimension(2,2) grid::grid_get_coarse_index::grid__get_coarse_index_cf (type(tvar), intent(in) td_lon0, type(tvar), intent(in) td_lat0, type(tmpp), intent(in) td_coord1, integer(i4), dimension(:), intent(in), optional id_rho, character(len=*), intent(in), optional cd_point)`

This function get closest coarse grid indices of fine grid domain.

it use coarse array of longitude and latitude and fine grid coordinates file. optionally, you could specify the array of refinement factor (default 1.) optionally, you could specify on which Arakawa grid point you want to work (default 'T')

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- use grid point to read coordinates variable.

October, 2014

- work on mpp file structure instead of file structure

February, 2015

- use longitude or latitude as standard name, if can not find longitude_T, latitude_T...

Parameters

in	<i>td_longitude0</i>	coarse grid longitude
in	<i>td_latitude0</i>	coarse grid latitude
in	<i>td_coord1</i>	fine grid coordinate mpp structure
in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point (default 'T')

Returns

coarse grid indices (*iimin0*, *imax0*), (*jmin0*, *jmax0*)

11.40.1.3 `integer(i4) function, dimension(2,2) grid::grid_get_coarse_index::grid__get_coarse_index_fc (type(tmpp), intent(in) td_coord0, type(tvar), intent(in) td_lon1, type(tvar), intent(in) td_lat1, integer(i4), dimension(:), intent(in), optional id_rho, character(len=*), intent(in), optional cd_point)`

This function get closest coarse grid indices of fine grid domain.

it use coarse grid coordinates file and fine grid array of longitude and latitude. optionally, you could specify the array of refinement factor (default 1.) optionally, you could specify on which Arakawa grid point you want to work (default 'T')

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- use grid point to read coordinates variable.

October, 2014

- work on mpp file structure instead of file structure

February, 2015

- use longitude or latitude as standard name, if can not find longitude_T, latitude_T...

Parameters

in	<i>td_coord0</i>	coarse grid coordinate mpp structure
in	<i>td_lon1</i>	fine grid longitude
in	<i>td_lat1</i>	fine grid latitude
in	<i>id_rho</i>	array of refinement factor (default 1.)
in	<i>cd_point</i>	Arakawa grid point (default 'T')

Returns

coarse grid indices (*((imin0, imax0/), (jmin0, jmax0/))*)

11.40.1.4 integer(i4) function, dimension(2,2) grid::grid_get_coarse_index::grid_get_coarse_index_ff (type(tmpp), intent(in) *td_coord0*, type(tmpp), intent(in) *td_coord1*, integer(i4), dimension(:), intent(in), optional *id_rho*, character(len=*) , intent(in), optional *cd_point*)

This function get closest coarse grid indices of fine grid domain.

it use coarse and fine grid coordinates files. optionally, you could specify the array of refinement factor (default 1.) optionally, you could specify on which Arakawa grid point you want to work (default 'T')

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- use grid point to read coordinates variable.

October, 2014

- work on mpp file structure instead of file structure

February, 2015

- use longitude or latitude as standard name, if can not find longitude_T, latitude_T...

Parameters

in	<i>td_coord0</i>	coarse grid coordinate mpp structure
in	<i>td_coord1</i>	fine grid coordinate mpp structure
in	<i>id_rho</i>	array of refinement factor (default 1.)
in	<i>cd_point</i>	Arakawa grid point (default 'T').

Returns

coarse grid indices(*((imin0, imax0/), (jmin0, jmax0/))*)

The documentation for this interface was generated from the following file:

- src/grid.f90

11.41 grid::grid_get_ew_overlap Interface Reference

Public Member Functions

- integer(i4) function [grid_get_ew_overlap_mpp](#) (td_mpp)

This function get East-West overlap.

- integer(i4) function [grid__get_ew_overlap_file](#) (td_file)

This function get East-West overlap.

- integer(i4) function [grid__get_ew_overlap_var](#) (td_var)

This function get East-West overlap.

11.41.1 Member Function/Subroutine Documentation

11.41.1.1 integer(i4) function `grid::grid_get_ew_overlap::grid__get_ew_overlap_file (type(tfile), intent(inout) td_file)`

This function get East-West overlap.

If no East-West wrap return -1, else return the size of the ovarlap band. East-West overlap is computed comparing longitude value of the South part of the domain, to avoid north fold boundary.

Author

J.Paul

Date

October, 2014 - Initial Version

October, 2016

- check varid for longitude_T

Parameters

<code>in</code>	<code>td_file</code>	file structure
-----------------	----------------------	----------------

Returns

East West overlap

11.41.1.2 integer(i4) function `grid::grid_get_ew_overlap::grid__get_ew_overlap_mpp (type(tmpp), intent(inout) td_mpp)`

This function get East-West overlap.

If no East-West wrap return -1, else return the size of the ovarlap band. East-West overlap is computed comparing longitude value of the South part of the domain, to avoid north fold boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

October, 2016

- check varid for longitude_T

Parameters

in	<i>td_mpp</i>	mpp structure
----	---------------	---------------

Returns

East West overlap

11.41.1.3 integer(i4) function grid::grid_get_ew_overlap::grid__get_ew_overlap_var (type(tvar), intent(inout) *td_var*)

This function get East-West overlap.

If no East-West wrap return -1, else return the size of the ovarlap band. East-West overlap is computed comparing longitude value of the South part of the domain, to avoid north fold boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

October, 2016

- check longitude as longname

Parameters

in	<i>td_lon</i>	longitude variable structure
----	---------------	------------------------------

Returns

East West overlap

The documentation for this interface was generated from the following file:

- src/grid.f90

11.42 grid::grid_get_fine_offset Interface Reference

Public Member Functions

- integer(i4) function,
dimension(2, 2) [grid__get_fine_offset_ff](#) (td_coord0, id_imin0, id_jmin0, id_imax0, id_jmax0, td_coord1, id_rho, cd_point)
This function get offset between fine grid and coarse grid.
- integer(i4) function,
dimension(2, 2) [grid__get_fine_offset_fc](#) (td_coord0, id_imin0, id_jmin0, id_imax0, id_jmax0, dd_lon1, dd_lat1, id_rho, cd_point)
This function get offset between fine grid and coarse grid.
- integer(i4) function,
dimension(2, 2) [grid__get_fine_offset_cf](#) (dd_lon0, dd_lat0, id_imin0, id_jmin0, id_imax0, id_jmax0, td_coord1, id_rho, cd_point)

This function get offset between fine grid and coarse grid.

- integer(i4) function,
dimension(2, 2) [grid__get_fine_offset_cc](#) (dd_lon0, dd_lat0, id_imin0, id_jmin0, id_imax0, id_jmax0, dd_lon1, dd_lat1, id_rho, cd_point)

This function get offset between fine grid and coarse grid.

11.42.1 Member Function/Subroutine Documentation

11.42.1.1 integer(i4) function, dimension(2,2) [grid::grid_get_fine_offset::grid__get_fine_offset_cc](#) (real(dp), dimension(:,:), intent(in) *dd_lon0*, real(dp), dimension(:,:), intent(in) *dd_lat0*, integer(i4), intent(in) *id_imin0*, integer(i4), intent(in) *id_jmin0*, integer(i4), intent(in) *id_imax0*, integer(i4), intent(in) *id_jmax0*, real(dp), dimension(:,:), intent(in) *dd_lon1*, real(dp), dimension(:,:), intent(in) *dd_lat1*, integer(i4), dimension(:), intent(in) *id_rho*, character(len=*) , intent(in), optional *cd_point*)

This function get offset between fine grid and coarse grid.

offset value could be 0,1,...,rho-1

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- rename from [grid_get_fine_offset](#)

May, 2015

- improve way to find offset

July, 2015

- manage case close to greenwich meridian

February, 2016

- use [grid_get_closest](#) to assess offset
- use delta (lon or lat)
- manage cases for T,U,V or F point, with even or odd refinement
- check lower left(upper right) fine grid point inside lower left(upper right) coarse grid cell.

Todo check case close from North fold.

Parameters

in	<i>dd_lon0</i>	coarse grid longitude array
in	<i>dd_lat0</i>	coarse grid latitude array
in	<i>id_imin0</i>	coarse grid lower left corner i-indices of fine grid domain
in	<i>id_jmin0</i>	coarse grid lower left corner j-indices of fine grid domain
in	<i>id_imax0</i>	coarse grid upper right corner i-indices of fine grid domain
in	<i>id_jmax0</i>	coarse grid upper right corner j-indices of fine grid domain
in	<i>dd_lon1</i>	fine grid longitude array
in	<i>dd_lat1</i>	fine grid latitude array

in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point

Returns

offset array (/ (/i_offset_left,i_offset_right/),(/j_offset_lower,j_offset_upper/)/)

11.42.1.2 integer(i4) function, dimension(2,2) grid::grid_get_fine_offset::grid_get_fine_offset_cf (real(dp), dimension(:,:), intent(in) *dd_lon0*, real(dp), dimension(:,:), intent(in) *dd_lat0*, integer(i4), intent(in) *id_imin0*, integer(i4), intent(in) *id_jmin0*, integer(i4), intent(in) *id_imax0*, integer(i4), intent(in) *id_jmax0*, type(tmpp), intent(in) *td_coord1*, integer(i4), dimension(:), intent(in), optional *id_rho*, character(len=*), intent(in), optional *cd_point*)

This function get offset between fine grid and coarse grid.

optionally, you could specify on which Arakawa grid point you want to work (default 'T') offset value could be 0,1,...,rho-1

Author

J.Paul

Date

September, 2014 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>dd_lon0</i>	coarse grid longitude array
in	<i>dd_lat0</i>	coarse grid latitude array
in	<i>id_imin0</i>	coarse grid lower left corner i-indices of fine grid domain
in	<i>id_jmin0</i>	coarse grid lower left corner j-indices of fine grid domain
in	<i>id_imax0</i>	coarse grid upper right corner i-indices of fine grid domain
in	<i>id_jmax0</i>	coarse grid upper right corner j-indices of fine grid domain
in	<i>td_coord1</i>	fine grid coordinate
in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point

Returns

offset array (/ (/i_offset_left,i_offset_right/),(/j_offset_lower,j_offset_upper/)/)

11.42.1.3 integer(i4) function, dimension(2,2) grid::grid_get_fine_offset::grid_get_fine_offset_fc (type(tmpp), intent(in) *td_coord0*, integer(i4), intent(in) *id_imin0*, integer(i4), intent(in) *id_jmin0*, integer(i4), intent(in) *id_imax0*, integer(i4), intent(in) *id_jmax0*, real(dp), dimension(:,:), intent(in) *dd_lon1*, real(dp), dimension(:,:), intent(in) *dd_lat1*, integer(i4), dimension(:), intent(in), optional *id_rho*, character(len=*), intent(in), optional *cd_point*)

This function get offset between fine grid and coarse grid.

optionally, you could specify on which Arakawa grid point you want to work (default 'T') offset value could be 0,1,...,rho-1

Author

J.Paul

Date

September, 2014 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>td_coord0</i>	coarse grid coordinate
in	<i>id_imin0</i>	coarse grid lower left corner i-indice of fine grid domain
in	<i>id_jmin0</i>	coarse grid lower left corner j-indice of fine grid domain
in	<i>id_imax0</i>	coarse grid upper right corner i-indice of fine grid domain
in	<i>id_jmax0</i>	coarse grid upper right corner j-indice of fine grid domain
in	<i>dd_lon1</i>	fine grid longitude array
in	<i>dd_lat1</i>	fine grid latitude array
in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point

Returns

offset array (/ (/i_offset_left,i_offset_right/),(/j_offset_lower,j_offset_upper/) /)

11.42.1.4 integer(i4) function, dimension(2,2) grid::grid_get_fine_offset::grid_get_fine_offset_ff (type(tmpp), intent(in) *td_coord0*, integer(i4), intent(in) *id_imin0*, integer(i4), intent(in) *id_jmin0*, integer(i4), intent(in) *id_imax0*, integer(i4), intent(in) *id_jmax0*, type(tmpp), intent(in) *td_coord1*, integer(i4), dimension(:), intent(in), optional *id_rho*, character(len=*), intent(in), optional *cd_point*)

This function get offset between fine grid and coarse grid.

optionally, you could specify on which Arakawa grid point you want to work (default 'T') offset value could be 0,1,...,rho-1

Author

J.Paul

Date

September, 2014 - Initial Version

October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>td_coord0</i>	coarse grid coordinate
in	<i>id_imin0</i>	coarse grid lower left corner i-indice of fine grid domain
in	<i>id_jmin0</i>	coarse grid lower left corner j-indice of fine grid domain
in	<i>id_imax0</i>	coarse grid upper right corner i-indice of fine grid domain
in	<i>id_jmax0</i>	coarse grid upper right corner j-indice of fine grid domain
in	<i>td_coord1</i>	fine grid coordinate
in	<i>id_rho</i>	array of refinement factor
in	<i>cd_point</i>	Arakawa grid point

Returns

offset array (/ (/i_offset_left,i_offset_right/),(/j_offset_lower,j_offset_upper/) /)

The documentation for this interface was generated from the following file:

- src/grid.f90

11.43 grid::grid_get_ghost Interface Reference

Public Member Functions

- integer(i4) function,
dimension(2, 2) [grid__get_ghost_var](#) (td_var)
This function check if ghost cell are used or not, and return ghost cell factor (0,1) in horizontal plan.
- integer(i4) function,
dimension(2, 2) [grid__get_ghost_mpp](#) (td_mpp)
This function check if ghost cell are used or not, and return ghost cell factor (0,1) in i- and j-direction.

11.43.1 Member Function/Subroutine Documentation

11.43.1.1 integer(i4) function, dimension(2,2) grid::grid_get_ghost::grid__get_ghost_mpp (type(tmpp), intent(in) td_mpp)

This function check if ghost cell are used or not, and return ghost cell factor (0,1) in i- and j-direction.
get longitude an latitude array, then check if domain is global, and if there is an East-West overlap

Author

J.Paul

Date

September, 2014 - Initial Version
October, 2014

- work on mpp file structure instead of file structure

Parameters

in	<i>td_file</i>	file sturcture
----	----------------	----------------

Returns

array of ghost cell factor

11.43.1.2 integer(i4) function, dimension(2,2) grid::grid_get_ghost::grid__get_ghost_var (type(tvar), intent(in) td_var)

This function check if ghost cell are used or not, and return ghost cell factor (0,1) in horizontal plan.
check if domain is global, and if there is an East-West overlap.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	variable sturcture
-----------------	---------------------	--------------------

Returns

array of ghost cell factor

The documentation for this interface was generated from the following file:

- `src/grid.f90`

11.44 `grid::grid_get_info` Interface Reference

Public Member Functions

- subroutine `grid__get_info_mpp` (`td_mpp`)
This subroutine get information about global domain, given mpp structure.
- subroutine `grid__get_info_file` (`td_file`)
This subroutine get information about global domain, given file strucutre.

11.44.1 Member Function/Subroutine Documentation

11.44.1.1 subroutine `grid::grid_get_info::grid__get_info_file` (`type(tfile)`, `intent(inout) td_file`)

This subroutine get information about global domain, given file strucutre.

open edge files then:

- compute NEMO pivot point
- compute NEMO periodicity
- compute East West overlap

Note

need all processor files to be there

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
----------------------	----------------------	----------------

11.44.1.2 subroutine grid::grid_get_info::grid_get_info_mpp (type(tmpp), intent(inout) td_mpp)

This subroutine get information about global domain, given mpp structure.

open edge files then:

- compute NEMO pivot point
- compute NEMO periodicity
- compute East West overlap

Note

need all processor files

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
----	---------------	---------------

The documentation for this interface was generated from the following file:

- src/grid.f90

11.45 grid::grid_get_perio Interface Reference

Public Member Functions

- integer(i4) function [grid__get_perio_mpp](#) (td_mpp, id_pivot)
This subroutine search NEMO periodicity given mpp structure and optionally pivot point index.
- integer(i4) function [grid__get_perio_file](#) (td_file, id_pivot)
This subroutine search NEMO periodicity index given file structure, and optionally pivot point index.
- integer(i4) function [grid__get_perio_var](#) (td_var, id_pivot)
This subroutine search NEMO periodicity index given variable structure and pivot point index.

11.45.1 Member Function/Subroutine Documentation

11.45.1.1 integer(i4) function grid::grid_get_perio::grid__get_perio_file (type(tfile), intent(in) td_file, integer(i4), intent(in), optional id_pivot)

This subroutine search NEMO periodicity index given file structure, and optionally pivot point index.

The variable used must be on T point.

0: closed boundaries 1: cyclic east-west boundary 2: symmetric boundary condition across the equator 3: North fold boundary (with a F-point pivot) 4: North fold boundary (with a F-point pivot) and cyclic east-west boundary 5: North fold boundary (with a T-point pivot) 6: North fold boundary (with a T-point pivot) and cyclic east-west boundary

Warning

pivot point should have been computed before run this script. see [grid_get_pivot](#).

Author

J.Paul

Date

October, 2014 - Initial version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_pivot</i>	pivot point index

11.45.1.2 integer(i4) function `grid::grid_get_perio::grid__get_perio_mpp (type(tmpp), intent(in) td_mpp, integer(i4), intent(in), optional id_pivot)`

This subroutine search NEMO periodicity given mpp structure and optionally pivot point index.

The variable used must be on T point.

0: closed boundaries 1: cyclic east-west boundary 2: symmetric boundary condition across the equator 3: North fold boundary (with a T-point pivot) 4: North fold boundary (with a T-point pivot) and cyclic east-west boundary 5: North fold boundary (with a F-point pivot) 6: North fold boundary (with a F-point pivot) and cyclic east-west boundary

Warning

pivot point should have been computed before run this script. see [grid_get_pivot](#).

Author

J.Paul

Date

October, 2014 - Initial version

Parameters

in	<i>td_mpp</i>	mpp file structure
in	<i>id_pivot</i>	pivot point index

11.45.1.3 integer(i4) function `grid::grid_get_perio::grid__get_perio_var (type(tvar), intent(in) td_var, integer(i4), intent(in) id_pivot)`

This subroutine search NEMO periodicity index given variable structure and pivot point index.

The variable must be on T point.

0: closed boundaries 1: cyclic east-west boundary 2: symmetric boundary condition across the equator 3: North fold boundary (with a T-point pivot) 4: North fold boundary (with a T-point pivot) and cyclic east-west boundary 5: North fold boundary (with a F-point pivot) 6: North fold boundary (with a F-point pivot) and cyclic east-west boundary

Warning

pivot point should have been computed before run this script. see [grid_get_pivot](#).

Author

J.Paul

Date

November, 2013 - Initial version
October, 2014

- work on variable structure instead of file structure

Parameters

<code>in</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>id_pivot</code>	pivot point index

The documentation for this interface was generated from the following file:

- src/grid.f90

11.46 grid::grid_get_pivot Interface Reference

Public Member Functions

- integer(i4) function [grid__get_pivot_mpp](#) (td_mpp)
This function compute NEMO pivot point index from input mpp variable.
- integer(i4) function [grid__get_pivot_file](#) (td_file)
This function compute NEMO pivot point index from input file variable.
- integer(i4) function [grid__get_pivot_var](#) (td_var)
This function compute NEMO pivot point index of the input variable.

11.46.1 Member Function/Subroutine Documentation

11.46.1.1 integer(i4) function grid::grid_get_pivot::grid__get_pivot_file (type(tfile), intent(in) td_file)

This function compute NEMO pivot point index from input file variable.

- F-point : 0
- T-point : 1

check north points of latitude grid (indices jpj to jpj-3) depending on which grid point (T,F,U,V) variable is defined

Warning

- do not work with ORCA2 grid (T-point)

Author

J.Paul

Date

Ocotber, 2014 - Initial version

Parameters

<i>in</i>	<i>td_file</i>	file structure
-----------	----------------	----------------

Returns

pivot point index

11.46.1.2 integer(i4) function `grid::grid_get_pivot::grid__get_pivot_mpp (type(tmpp), intent(in) td_mpp)`

This function compute NEMO pivot point index from input mpp variable.

- F-point : 0
- T-point : 1

check north points of latitude grid (indices `npj` to `npj-3`) depending on which grid point (T,F,U,V) variable is defined

Warning

- do not work with ORCA2 grid (T-point)

Author

J.Paul

Date

October, 2014 - Initial version

Parameters

<i>in</i>	<i>td_mpp</i>	mpp file structure
-----------	---------------	--------------------

Returns

pivot point index

11.46.1.3 integer(i4) function `grid::grid_get_pivot::grid__get_pivot_var (type(tvar), intent(in) td_var)`

This function compute NEMO pivot point index of the input variable.

- F-point : 0
- T-point : 1

check north points of latitude grid (indices `npj` to `npj-3`) depending on which grid point (T,F,U,V) variable is defined

Note

variable must be at least 2D variable, and should not be coordinate variable (i.e lon, lat)

Warning

- do not work with ORCA2 grid (T-point)

Author

J.Paul

Date

November, 2013 - Initial version

September, 2014

- add dummy loop in case variable not over right point.

October, 2014

- work on variable structure instead of file structure

Parameters

in	<i>td_lat</i>	latitude variable structure
in	<i>td_var</i>	variable structure

Returns

pivot point index

The documentation for this interface was generated from the following file:

- src/grid.f90

11.47 grid_hgr Module Reference

This module manage Horizontal grid.

Data Types

- type [tnamh](#)

Public Member Functions

- subroutine, public [grid_hgr_init](#) (jpi, jpj, jpk, ld_domcfg)
This function initialise hgr structure.
- subroutine, public [grid_hgr_clean](#) (ld_domcfg)
This function clean hgr structure.
- type([tnamh](#)) function, public [grid_hgr_nam](#) (cd_coord, id_perio, cd_namelist)
This function initialise hgr namelist structure.
- subroutine, public [grid_hgr_fill](#) (td_nam, jpi, jpj, ld_domcfg)
This subroutine fill horizontal mesh (hgr structure)

Public Attributes

- type(tvar), save, public **tg_tmask**
- type(tvar), save, public **tg_umask**
- type(tvar), save, public **tg_vmask**
- type(tvar), save, public **tg_fmask**
- type(tvar), save, public **tg_ssmask**
- type(tvar), save, public **tg_glamt**

- type(tvar), save, public **tg_glamu**
- type(tvar), save, public **tg_glamv**
- type(tvar), save, public **tg_glamf**
- type(tvar), save, public **tg_gphit**
- type(tvar), save, public **tg_gphiu**
- type(tvar), save, public **tg_gphiv**
- type(tvar), save, public **tg_gphif**
- type(tvar), save, public **tg_e1t**
- type(tvar), save, public **tg_e1u**
- type(tvar), save, public **tg_e1v**
- type(tvar), save, public **tg_e1f**
- type(tvar), save, public **tg_e2t**
- type(tvar), save, public **tg_e2u**
- type(tvar), save, public **tg_e2v**
- type(tvar), save, public **tg_e2f**
- type(tvar), save, public **tg_ff_t**
- type(tvar), save, public **tg_ff_f**
- type(tvar), save, public **tg_gcost**
- type(tvar), save, public **tg_gcosu**
- type(tvar), save, public **tg_gcosv**
- type(tvar), save, public **tg_gcosf**
- type(tvar), save, public **tg_g sint**
- type(tvar), save, public **tg_gsinu**
- type(tvar), save, public **tg_gsinv**
- type(tvar), save, public **tg_gsinf**

11.47.1 Detailed Description

This module manage Horizontal grid.

** Purpose : Compute the geographical position (in degree) of the model grid-points, the horizontal scale factors (in meters) and the Coriolis factor (in s-1).

** Method : The geographical position of the model grid-points is defined from analytical functions, fslam and fsphi, the derivatives of which gives the horizontal scale factors e1,e2. Defining two function fslam and fsphi and their derivatives in the two horizontal directions (fse1 and fse2), the model grid-point position and scale factors are given by:

- t-point:
 - $glamt(i,j) = fslam(i,j) e1t(i,j) = fse1(i,j)$
 - $gphit(i,j) = fsphi(i,j) e2t(i,j) = fse2(i,j)$
- u-point:
 - $glamu(i,j) = fslam(i+1/2,j) e1u(i,j) = fse1(i+1/2,j)$
 - $gphiu(i,j) = fsphi(i+1/2,j) e2u(i,j) = fse2(i+1/2,j)$
- v-point:
 - $glamv(i,j) = fslam(i,j+1/2) e1v(i,j) = fse1(i,j+1/2)$
 - $gphiv(i,j) = fsphi(i,j+1/2) e2v(i,j) = fse2(i,j+1/2)$
- f-point:
 - $glamf(i,j) = fslam(i+1/2,j+1/2) e1f(i,j) = fse1(i+1/2,j+1/2)$
 - $gphif(i,j) = fsphi(i+1/2,j+1/2) e2f(i,j) = fse2(i+1/2,j+1/2)$

Where fse1 and fse2 are defined by:

- $fse1(i,j) = ra * rad * \sqrt{(\cos(\phi) di(fslam))^{**2} - di(fsphi)^{**2}}(i,j)$
- $fse2(i,j) = ra * rad * \sqrt{(\cos(\phi) dj(fslam))^{**2} - dj(fsphi)^{**2}}(i,j)$

The coriolis factor is given at z-point by:

- $ff = 2.*\omega*\sin(\phi)$ (in s-1)

This routine is given as an example, it must be modified following the user's desiderata. nevertheless, the output as well as the way to compute the model grid-point position and horizontal scale factors must be respected in order to insure second order accuracy schemes.

Note

If the domain is periodic, verify that scale factors are also periodic, and the coriolis term again.

** Action :

- define glamt, glamu, glamv, glamf: longitude of t-, u-, v- and f-points (in degree)
- define gphit, gphiu, gphiv, gphif: latitude of t-, u-, v- and f-points (in degree)
- define e1t, e2t, e1u, e2u, e1v, e2v, e1f, e2f: horizontal
- scale factors (in meters) at t-, u-, v-, and f-points.
- define ff: coriolis factor at f-point

References : Marti, Madec and Delecluse, 1992, JGR Madec, Imbard, 1996, Clim. Dyn.

Author

G, Madec

Date

March, 1988 - Original code

January, 1996

- terrain following coordinates

February, 1997

- print mesh informations

November, 1999

- M. Imbard : NetCDF format with IO-IPSL

August, 2000

- D. Ludicone : Reduced section at Bab el Mandeb

September, 2001

- M. Levy : eel config: grid in km, beta-plane

August, 2002

- G. Madec : F90: Free form and module, namelist

January, 2004

- A.M. Treguier, J.M. Molines : Case 4 (Mercator mesh) use of parameters in par_CONFIG-Rxx.h90, not in namelist

May, 2004

- A. Koch-Larrouy : Add Gyre configuration

February, 2011

- G. Madec : add cell surface (e1e2t)

September, 2015

- J, Paul : rewrite to SIREN format from

Id:

domhgr.F90 5506 2015-06-29 15:19:38Z clevy

Date

October, 2016

- J, Paul : update from trunk (revision 6961): add wetting and drying, ice sheet coupling..
- J, Paul : compute coriolis factor at f-point and at t-point
- J, Paul : do not use anymore special case for ORCA grid

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.47.2 Member Function/Subroutine Documentation

11.47.2.1 subroutine, public grid_hgr::grid_hgr_clean (logical, intent(in) *ld_domcfg*)

This function clean hgr structure.

Author

J.Paul

Date

September, 2015 - Initial version

11.47.2.2 subroutine, public grid_hgr::grid_hgr_fill (type(tnamh), intent(in) *td_nam*, integer(i4), intent(in) *jpi*, integer(i4), intent(in) *jjj*, logical, intent(in) *ld_domcfg*)

This subroutine fill horizontal mesh (hgr structure)

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>td_nam</i>	
in	<i>jpi</i>	
in	<i>npj</i>	

11.47.2.3 subroutine, public grid_hgr::grid_hgr_init (integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*, integer(i4), intent(in) *npk*, logical, intent(in) *ld_domcfg*)

This function initialise hgr structure.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>jpi</i>	
in	<i>npj</i>	

11.47.2.4 type(tnamh) function, public grid_hgr::grid_hgr_nam (character(len=*), intent(in) *cd_coord*, integer(i4), intent(in) *id_perio*, character(len=*), intent(in) *cd_namelist*)

This function initialise hgr namelist structure.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>cd_coord</i>	
in	<i>id_perio</i>	
in	<i>cd_namelist</i>	

Returns

hgr namelist structure

The documentation for this module was generated from the following file:

- src/grid_hgr.f90

11.48 grid_zgr Module Reference

This module manage Vertical grid.

Data Types

- type [tnamz](#)

Public Member Functions

- subroutine, public [grid_zgr_init](#) (jpi, jpj, jpk, ld_sco)
This function initialise global variable needed to compute vertical mesh.
- subroutine, public [grid_zgr_clean](#) (ld_sco)
This function clean hgr structure.
- type([tnamz](#)) function, public [grid_zgr_nam](#) (cd_coord, id_perio, cd_namelist)
This function initialise zgr namelist structure.
- subroutine, public [grid_zgr_fill](#) (td_nam, jpi, jpj, jpk, td_bathy, td_risfdep)
This subroutine fill vertical mesh.
- subroutine, public [grid_zgr_zps_init](#) (jpi, jpj)
This function initialise global variable needed to compute vertical mesh.
- subroutine, public [grid_zgr_zps_clean](#) ()
This function clean hgr structure.
- subroutine, public [grid_zgr_sco_init](#) (jpi, jpj)
This function initialise global variable needed to compute vertical mesh.
- subroutine, public [grid_zgr_sco_clean](#) ()
This function clean structure.
- subroutine, public [grid_zgr_sco_stiff](#) (td_nam, jpi, jpj, jpk)
This subroutine stretch the s-coordinate system.

Public Attributes

- type(tvar), save, public [tg_gdepw_1d](#)
- type(tvar), save, public [tg_gdept_1d](#)
- type(tvar), save, public [tg_e3w_1d](#)
- type(tvar), save, public [tg_e3t_1d](#)
- type(tvar), save, public [tg_e3tp](#)
- type(tvar), save, public [tg_e3wp](#)
- type(tvar), save, public [tg_rx1](#)
- type(tvar), save, public [tg_mbathy](#)
- type(tvar), save, public [tg_misfdep](#)
- type(tvar), save, public [tg_gdept_0](#)
- type(tvar), save, public [tg_gdepw_0](#)
- type(tvar), save, public [tg_e3t_0](#)
- type(tvar), save, public [tg_e3u_0](#)
- type(tvar), save, public [tg_e3v_0](#)
- type(tvar), save, public [tg_e3w_0](#)
- type(tvar), save, public [tg_e3f_0](#)
- type(tvar), save, public [tg_e3uw_0](#)
- type(tvar), save, public [tg_e3vw_0](#)
- type(tvar), save, public [tg_mbkt](#)
- type(tvar), save, public [tg_mikt](#)
- type(tvar), save, public [tg_hbatt](#)
- type(tvar), save, public [tg_hbatu](#)
- type(tvar), save, public [tg_hbatv](#)
- type(tvar), save, public [tg_hbatf](#)
- type(tvar), save, public [tg_gsig](#)

- type(tvar), save, public **tg_gsigw**
- type(tvar), save, public **tg_gsi3w**
- type(tvar), save, public **tg_esigt**
- type(tvar), save, public **tg_esigw**

11.48.1 Detailed Description

This module manage Vertical grid.

** Purpose : set the depth of model levels and the resulting vertical scale factors.

** Method :

- reference 1D vertical coordinate (gdep._1d, e3._1d)
- read/set ocean depth and ocean levels (bathy, mbathy)
- vertical coordinate (gdep., e3.) depending on the coordinate chosen :
 - In_zco=T z-coordinate
 - In_zps=T z-coordinate with partial steps
 - In_zco=T s-coordinate

** Action : define gdep., e3., mbathy and bathy

Author

G, Madec

Date

December, 1995 - Original code : s vertical coordinate

July, 1997

- lbc_ink call

September, 2002

- A. Bozec, G. Madec : F90: Free form and module

September, 2002

- A. de Miranda : rigid-lid + islands

August, 2003

- G. Madec : Free form and module

October, 2005

- A. Beckmann : modifications for hybrid s-coordinates & new stretching function

April, 2006

- R. Benshila, G. Madec : add zgr_zco

June, 2008

- G. Madec : insertion of domzgr_zps.h90 & condng style

July, 2009

- R. Benshila : Suppression of rigid-lid option

November, 2011

- G. Madec : add mbk. arrays associated to the deepest ocean level

August, 2012

- J. Siddorn : added Siddorn and Furner stretching function

December, 2012

- R. Bourdalle-Badie and G. Reffray : modify C1D case

November, 2014

- P. Mathiot and C. Harris : add ice shelf capabilitye

November, 2015

- H. Liu : Modifications for Wetting/Drying

October, 2016

- J, Paul : update from trunk (revision 6961): add wetting and drying, ice sheet coupling..
- J, Paul : do not use anymore special case for ORCA grid.

November, 2016

- J, Paul : vertical scale factors e3. = dk[gdep] or old definition

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.48.2 Member Function/Subroutine Documentation

11.48.2.1 subroutine, public grid_zgr::grid_zgr_clean (logical, intent(in) *ld_sco*)

This function clean hgr structure.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

<i>in</i>	<i>ld_sco</i>
-----------	---------------

11.48.2.2 subroutine, public grid_zgr::grid_zgr_fill (type(tnamz), intent(in) *td_nam*, integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*, integer(i4), intent(in) *jpk*, type(tvar), intent(inout) *td_bathy*, type(tvar), intent(inout) *td_risfdep*)

This subroutine fill vertical mesh.

Author

J.Paul

Date

September, 2015 - Initial version

October, 2016

- ice shelf cavity

Parameters

in	<i>td_nam</i>	
in	<i>jpi</i>	
in	<i>npj</i>	
in	<i>jpk</i>	
in	<i>td_bathy</i>	
in	<i>td_risfdep</i>	

11.48.2.3 subroutine, public grid_zgr::grid_zgr_init (integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*, integer(i4), intent(in) *jpk*, logical, intent(in) *ld_sco*)

This function initialise global variable needed to compute vertical mesh.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>jpi</i>	
in	<i>npj</i>	
in	<i>jpk</i>	
in	<i>ld_sco</i>	

11.48.2.4 type(tnamz) function, public grid_zgr::grid_zgr_nam (character(len=*), intent(in) *cd_coord*, integer(i4), intent(in) *id_perio*, character(len=*), intent(in) *cd_namelist*)

This function initialise zgr namelist structure.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>cd_coord</i>	
in	<i>id_perio</i>	
in	<i>cd_namelist</i>	

Returns

hgr namelist structure

11.48.2.5 subroutine, public grid_zgr::grid_zgr_sco_clean ()

This function clean structure.

Author

J.Paul

Date

September, 2015 - Initial version

11.48.2.6 subroutine, public grid_zgr::grid_zgr_sco_init (integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*)

This function initialise global variable needed to compute vertical mesh.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

in	<i>jpi</i>	
in	<i>npj</i>	

11.48.2.7 subroutine, public grid_zgr::grid_zgr_sco_stiff (type(tnamz), intent(in) *td_nam*, integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*, integer(i4), intent(in) *jpk*)

This subroutine stretch the s-coordinate system.

** Method : s-coordinate stretch

Reference : Madec, Lott, Delecluse and Crepon, 1996. JPO, 26, 1393-1408.

Author

J.Paul

Date

September, 2015 - rewrite from domain (dom_stiff)

Parameters

in	<i>td_nam</i>	
in	<i>jpi</i>	
in	<i>npj</i>	
in	<i>jpk</i>	

11.48.2.8 subroutine, public grid_zgr::grid_zgr_zps_clean ()

This function clean hgr structure.

Author

J.Paul

Date

September, 2015 - Initial version

11.48.2.9 subroutine, public grid_zgr::grid_zgr_zps_init (integer(i4), intent(in) *jpi*, integer(i4), intent(in) *npj*)

This function initialise global variable needed to compute vertical mesh.

Author

J.Paul

Date

September, 2015 - Initial version

Parameters

<i>in</i>	<i>jpi</i>	
<i>in</i>	<i>npj</i>	

The documentation for this module was generated from the following file:

- src/grid_zgr.f90

11.49 interp Module Reference

This module manage interpolation on regular grid.

Data Types

- interface [interp_detect](#)
- interface [interp_fill_value](#)
- type [tinterp](#)

Public Member Functions

- subroutine, public [interp_create_mixed_grid](#) (td_var, td_mix, id_rho)
This subroutine create mixed grid.
- subroutine, public [interp_clean_mixed_grid](#) (td_mix, td_var, id_rho, id_offset)
This subroutine remove points added on mixed grid to compute interpolation. And save interpolated value over domain.

11.49.1 Detailed Description

This module manage interpolation on regular grid.

Interpolation method to be used is specify inside variable structure, as array of string character.

- `td_var%c_interp(1)` string character is the interpolation name choose between:
 - 'nearest'
 - 'cubic'
 - 'linear'
- `td_var%c_interp(2)` string character is an operation to be used on interpolated value. operation have to be multiplication '*' or division '/'. coefficient have to be refinement factor following i-direction 'rhoi', j-direction 'rhoj', or k-direction 'rhok'. Examples: '*rhoi', '/rhoj'.

Note

Those informations are read from namelist or variable configuration file (default).

Interpolation method could be specify for each variable in namelist *namvar*, defining string character *cn_varinfo*.

Example:

- `cn_varinfo='varname1:int=cubic/rhoi', 'varname2:int=linear'`

to create mixed grid (with coarse grid point needed to compute interpolation):

```
CALL interp_create_mixed_grid( td_var, td_mix [,id_rho] )
```

- `td_var` is coarse grid variable (should be extrapolated)
- `td_mix` is mixed grid variable structure [output]
- `id_rho` is array of refinement factor [optional]

to detected point to be interpolated:

```
il_detect(:, :, :) = interp_detect( td_mix [,id_rho] )
```

- `il_detect(:, :, :)` is 3D array of detected point to be interpolated
- `td_mix` is mixed grid variable
- `id_rho` is array of refinement factor [optional]

to interpolate variable value:

```
CALL interp_fill_value( td_var [,id_rho] [,id_offset] )
```

- `td_var` is variable structure
- `id_rho` is array of refinement factor [optional]
- `id_offset` is array of offset between fine and coarse grid [optional]

to clean mixed grid (remove points added on mixed grid to compute interpolation):

```
CALL interp_clean_mixed_grid( td_mix, td_var, id_rho )
```

- `td_mix` is mixed grid variable structure
- `td_var` is variable structure [output]
- `id_rho` is array of refinement factor [optional]
- `id_offset` is array of offset between fine and coarse grid [optional]

Note

It use to work on ORCA grid, as we work only with grid indices.

Warning

due to the use of second derivative when using cubic interpolation you should add at least 2 extrabands.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header
- use interpolation method modules

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.49.2 Member Function/Subroutine Documentation

11.49.2.1 subroutine, public `interp::interp_clean_mixed_grid (type(tvar), intent(in) td_mix, type(tvar), intent(out) td_var, integer(i4), dimension(:), intent(in) id_rho, integer(i4), dimension(2,2), intent(in) id_offset)`

This subroutine remove points added on mixed grid to compute interpolation. And save interpolated value over domain.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- use offset to save useful domain

Parameters

in	<i>td_mix</i>	mixed grid variable structure
out	<i>td_var</i>	variable structure
in	<i>id_rho</i>	array of refinement factor (default 1)
in	<i>id_offset</i>	2D array of offset between fine and coarse grid

11.49.2.2 subroutine, public `interp::interp_create_mixed_grid (type(tvar), intent(in) td_var, type(tvar), intent(out) td_mix, integer(i4), dimension(:), intent(in), optional id_rho)`

This subroutine create mixed grid.

Created grid is fine resolution grid. First and last point are coarse grid point.

A special case is done for even refinement on ARAKAWA-C grid.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_var</i>	coarse grid variable (should be extrapolated)
out	<i>td_mix</i>	mixed grid variable
in	<i>id_rho</i>	array of refinement factor (default 1)

The documentation for this module was generated from the following file:

- `src/interp.f90`

11.50 interp_cubic Module Reference

This module manage cubic interpolation on regular grid.

Public Member Functions

- subroutine, public `interp_cubic_fill (dd_value, dd_fill, id_detect, id_rho, ld_even, ld_discont)`
This subroutine compute horizontal cubic interpolation on 4D array of value.

11.50.1 Detailed Description

This module manage cubic interpolation on regular grid.

to compute cubic interpolation:

```
CALL interp_cubic_fill(dd_value, dd_fill, id_detect, id_rho, ld_even [,ld_discont] )
```

- `dd_value` is 2D array of variable value
- `dd_fill` is the FillValue of variable
- `id_detect` is 2D array of point to be interpolated (see `interp` module)
- `id_rho` is array of refinement factor

- `ld_even` indicates even refinement or not
- `ld_discont` indicates longitudinal discontinuity (-180°/180°, 0°/360°) or not

Author

J.Paul

Date

September, 2014 -Initial version
 June, 2015

- use math module

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.50.2 Member Function/Subroutine Documentation

11.50.2.1 subroutine, public `interp_cubic::interp_cubic_fill` (`real(dp)`, `dimension(:, :, :, :)`, `intent(inout) dd_value`, `real(dp)`, `intent(in) dd_fill`, `integer(i4)`, `dimension(:, :, :)`, `intent(inout) id_detect`, `integer(i4)`, `dimension(:)`, `intent(in) id_rho`, `logical`, `dimension(:)`, `intent(in) ld_even`, `logical`, `intent(in)`, optional `ld_discont`)

This subroutine compute horizontal cubic interpolation on 4D array of value.

Author

J.Paul

Date

September, 2014 - Initial Version
 July, 2015

- reinitialise detect array for each level

Parameters

<code>in, out</code>	<code>dd_value</code>	2D array of variable value
<code>in</code>	<code>dd_fill</code>	FillValue of variable
<code>in, out</code>	<code>id_detect</code>	2D array of point to be interpolated
<code>in</code>	<code>id_rho</code>	array of refinement factor
<code>in</code>	<code>ld_even</code>	even refinement or not
<code>in</code>	<code>ld_discont</code>	longitudinal discontinuity (-180°/180°, 0°/360°) or not

The documentation for this module was generated from the following file:

- `src/interp_cubic.f90`

11.51 interp::interp_detect Interface Reference**Public Member Functions**

- `integer(i4)` function, `dimension(td_mix%t_dim(1)%i_len, td_mix%t_dim(2)%i_len, td_mix%t_dim(3)%i_len)` [interp__detect_wrapper](#) (`td_mix`, `id_rho`)

This function detected point to be interpolated.

11.51.1 Member Function/Subroutine Documentation

11.51.1.1 `integer(i4) function, dimension(td_mix%t_dim(1)%i_len, td_mix%t_dim(2)%i_len, td_mix%t_dim(3)%i_len)`
`interp::interp_detect::interp__detect_wrapper (type(tvar), intent(in) td_mix, integer(i4), dimension(:), intent(in),`
`optional id_rho)`

This function detected point to be interpolated.

Actually it checks, the number of dimension used for this variable and launch `interp__detect` which detected point to be interpolated.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_mix</i>	mixed grid variable (to interpolate)
in	<i>id_rho</i>	array of refinement factor

Returns

3D array of detected point to be interpolated

The documentation for this interface was generated from the following file:

- `src/interp.f90`

11.52 `interp::interp_fill_value` Interface Reference

Public Member Functions

- subroutine [`interp__fill_value_wrapper`](#) (`td_var`, `id_rho`, `id_offset`)
This subroutine interpolate variable value.

11.52.1 Member Function/Subroutine Documentation

11.52.1.1 `subroutine interp::interp_fill_value::interp__fill_value_wrapper (type(tvar), intent(inout) td_var, integer(i4),`
`dimension(:), intent(in), optional id_rho, integer(i4), dimension(:,:), intent(in), optional id_offset)`

This subroutine interpolate variable value.

Actually it checks, the number of dimension used for this variable and launch `interp__fill_value`.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>id_rho</i>	array of refinement factor
in	<i>id_offset</i>	2D array of offset between fine and coarse grid

The documentation for this interface was generated from the following file:

- src/interp.f90

11.53 interp_linear Module Reference

This module manage linear interpolation on regular grid.

Public Member Functions

- subroutine, public `interp_linear_fill` (dd_value, dd_fill, id_detect, id_rho, ld_even, ld_discont)

This subroutine compute horizontal linear interpolation on 4D array of value.

11.53.1 Detailed Description

This module manage linear interpolation on regular grid.

to compute linear interpolation:

```
CALL interp_linear_fill(dd_value, dd_fill, id_detect, id_rho, ld_even [,ld_discont] )
```

- dd_value is 2D array of variable value
- dd_fill is the FillValue of variable
- id_detect is 2D array of point to be interpolated (see interp module)
- id_rho is array of refinement factor
- ld_even indicates even refinement or not
- ld_discont indicates longitudinal discontinuity (-180°/180°, 0°/360°) or not

Author

J.Paul

Date

September, 2014 - Initial version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.53.2 Member Function/Subroutine Documentation

11.53.2.1 subroutine, public `interp_linear::interp_linear_fill` (`real(dp)`, `dimension(:, :, :, :)`, `intent(inout) dd_value`, `real(dp)`, `intent(in) dd_fill`, `integer(i4)`, `dimension(:, :, :)`, `intent(inout) id_detect`, `integer(i4)`, `dimension(:)`, `intent(in) id_rho`, `logical`, `dimension(:)`, `intent(in) ld_even`, `logical`, `intent(in)`, `optional ld_discont`)

This subroutine compute horizontal linear interpolation on 4D array of value.

Author

J.Paul

Date

September, 2014 - Initial Version

July, 2015 - reinitialise detect array for each level

Parameters

<code>in, out</code>	<code>dd_value</code>	2D array of variable value
<code>in</code>	<code>dd_fill</code>	FillValue of variable
<code>in, out</code>	<code>id_detect</code>	2D array of point to be interpolated
<code>in</code>	<code>id_rho</code>	array of refinement factor
<code>in</code>	<code>ld_even</code>	even refinement or not
<code>in</code>	<code>ld_discont</code>	longitudinal discontinuity (-180°/180°, 0°/360°) or not

The documentation for this module was generated from the following file:

- `src/interp_linear.f90`

11.54 interp_nearest Module Reference

This module manage nearest interpolation on regular grid.

Public Member Functions

- subroutine, public `interp_nearest_fill` (`dd_value`, `id_detect`, `id_rho`)
This subroutine compute horizontal nearest interpolation on 4D array of value.

11.54.1 Detailed Description

This module manage nearest interpolation on regular grid.

to compute nearest interpolation:

```
CALL interp_nearest_fill(dd_value, dd_fill, id_detect, id_rho, ld_even [,ld_discont] )
```

- `dd_value` is 2D array of variable value
- `dd_fill` is the FillValue of variable
- `id_detect` is 2D array of point to be interpolated (see `interp` module)
- `id_rho` is array of refinement factor
- `ld_even` indicates even refinement or not
- `ld_discont` indicates longitudinal discontinuity (-180°/180°, 0°/360°) or not

Author

J.Paul

Date

September, 2014 - Initial version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.54.2 Member Function/Subroutine Documentation

11.54.2.1 subroutine, public `interp_nearest::interp_nearest_fill (real(dp), dimension(:, :, :, :), intent(inout) dd_value, integer(i4), dimension(:, :, :), intent(inout) id_detect, integer(i4), dimension(:), intent(in) id_rho)`

This subroutine compute horizontal nearest interpolation on 4D array of value.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<code>in, out</code>	<code>dd_value</code>	2D array of variable value
<code>in, out</code>	<code>id_detect</code>	2D array of point to be interpolated
<code>in</code>	<code>id_rho</code>	array of refinement factor

The documentation for this module was generated from the following file:

- `src/interp_nearest.f90`

11.55 iom Module Reference

Input/Output manager : Library to read input files.

Data Types

- interface [iom_read_att](#)
- interface [iom_read_dim](#)
- interface [iom_read_var](#)

Public Member Functions

- subroutine, public [iom_open](#) (td_file)
This function open a file in read or write mode.
- subroutine, public [iom_create](#) (td_file)
This function create a file.
- subroutine, public [iom_close](#) (td_file)
This subroutine close file.
- subroutine, public [iom_write_file](#) (td_file, cd_dimorder)
This subroutine write file structure in an opened file.

11.55.1 Detailed Description

Input/Output manager : Library to read input files.

to open file:


```
CALL iom_open(td_file)
```

- td_file is file structure

to create file:

```
CALL iom_create(td_file)
```

- td_file is file structure

to write in file:

```
CALL iom_write_file(td_file)
```

to close file:

```
CALL iom_close(tl_file)
```

to read one dimension in file:

```
tl_dim = iom_read_dim(tl_file, id_dimid)
```

or

```
tl_dim = iom_read_dim(tl_file, cd_name)
```

- id_dimid is dimension id
- cd_name is dimension name

to read variable or global attribute in file:

```
tl_att = iom_read_att(tl_file, id_varid, id_attid)
```

or

```
tl_att = iom_read_att(tl_file, id_varid, cd_attname)
```

or

```
tl_att = iom_read_att(tl_file, cd_varname, id_attid)
```

or

```
tl_att = iom_read_att(tl_file, cd_varname, cd_attname)
```

- id_varid is variable id
- id_attid is attribute id
- cd_attname is attribute name

- `cd_varname` is variable name or standard name

to read one variable in file:

```
tl_var = iom_read_var(td_file, id_varid, [id_start, id_count])
```

or

```
tl_var = iom_read_var(td_file, cd_name, [id_start, [id_count,]])
```

- `id_varid` is variable id
- `cd_name` is variable name or standard name.
- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]

Author

J.Paul

Date

November, 2013 - Initial Version

Todo

- see `lbc_Ink`
- see `goup netcdf4`

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.55.2 Member Function/Subroutine Documentation

11.55.2.1 subroutine, public `iom::iom_close (type(tfile), intent(inout) td_file)`

This subroutine close file.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code><i>td_file</i></code>	file structure
----------------------	-----------------------------	----------------

11.55.2.2 subroutine, public `iom::iom_create (type(tfile), intent(inout) td_file)`

This function create a file.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
----------------------	----------------------	----------------

11.55.2.3 subroutine, public iom::iom_open (type(tfile), intent(inout) *td_file*)

This function open a file in read or write mode.

If try to open a file in write mode that did not exist, create it.

If file exist, get information about:

- the number of variables
- the number of dimensions
- the number of global attributes
- the ID of the unlimited dimension
- the file format and finally read dimensions.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
----------------------	----------------------	----------------

11.55.2.4 subroutine, public iom::iom_write_file (type(tfile), intent(inout) *td_file*, character(len=*) , intent(in), optional *cd_dimorder*)

This subroutine write file structure in an opened file.

optionally, you could specify dimension order (default 'xyzt')

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015 - add dimension order option

Parameters

<code>in</code>	<code>td_file</code>	file structure
-----------------	----------------------	----------------

The documentation for this module was generated from the following file:

- src/iom.f90

11.56 iom_cdf Module Reference

NETCDF Input/Output manager : Library to read Netcdf input files.

Data Types

- interface [iom_cdf_fill_var](#)
- interface [iom_cdf_read_att](#)
- interface [iom_cdf_read_dim](#)
- interface [iom_cdf_read_var](#)

Public Member Functions

- subroutine, public [iom_cdf_open](#) (td_file)
This subroutine open a netcdf file in read or write mode.
- subroutine, public [iom_cdf_close](#) (td_file)
This subroutine close netcdf file.
- subroutine, public [iom_cdf_write_file](#) (td_file, cd_dimorder)
This subroutine write file structure in an opened netcdf file.

11.56.1 Detailed Description

NETCDF Input/Output manager : Library to read Netcdf input files.

to open netcdf file:


```
CALL iom_cdf_open(td_file)
```

- td_file is file structure (see [file](#))

to write in netcdf file:

```
CALL iom_cdf_write_file(td_file)
```

to close netcdf file:

```
CALL iom_cdf_close(tl_file)
```

to read one dimension in netcdf file:

```
tl_dim = iom_cdf_read_dim(tl_file, id_dimid)
```

or

```
tl_dim = iom_cdf_read_dim(tl_file, cd_name)
```

- id_dimid is dimension id
- cd_name is dimension name

to read one attribute in netcdf file:

```
tl_att = iom_cdf_read_att(tl_file, id_varid, id_attid)
```

or

```
tl_att = iom_cdf_read_att(tl_file, id_varid, cd_name)
```

- `id_varid` is variable id
- `id_attid` is attribute id
- `cd_name` is attribute name

to read one variable in netcdf file:

```
tl_var = iom_cdf_read_var(td_file, id_varid, [id_start, id_count])
```

or

```
tl_var = iom_cdf_read_var(td_file, cd_name, [id_start, [id_count,]])
```

- `id_varid` is variable id
- `cd_name` is variable name
- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]

Author

J.Paul

Date

November, 2013 - Initial Version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.56.2 Member Function/Subroutine Documentation

11.56.2.1 subroutine, public `iom_cdf::iom_cdf_close (type(tfile), intent(inout) td_file)`

This subroutine close netcdf file.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_file</i>	file structure
---------	----------------	----------------

11.56.2.2 subroutine, public iom_cdf::iom_cdf_open (type(tfile), intent(inout) *td_file*)

This subroutine open a netcdf file in read or write mode.

if try to open a file in write mode that did not exist, create it.

if file already exist, get information about0:

- the number of variables
- the number of dimensions
- the number of global attributes
- the ID of the unlimited dimension
- the file format Finally it read dimensions, and 'longitude' variable to compute East-West overlap.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_file</i>	file structure
---------	----------------	----------------

11.56.2.3 subroutine, public iom_cdf::iom_cdf_write_file (type(tfile), intent(inout) *td_file*, character(len=*) , intent(in), optional *cd_dimorder*)

This subroutine write file structure in an opened netcdf file.

optionally, you could specify dimension order (default 'xyzt')

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- add dimension order option

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
----------------------	----------------------	----------------

The documentation for this module was generated from the following file:

- `src/iom_cdf.f90`

11.57 iom_cdf::iom_cdf_fill_var Interface Reference

Public Member Functions

- subroutine `iom_cdf__fill_var_id` (`td_file`, `id_varid`, `id_start`, `id_count`)
This subroutine fill variable value in an opened netcdf file, given variable id.
- subroutine `iom_cdf__fill_var_name` (`td_file`, `cd_name`, `id_start`, `id_count`)
This subroutine fill variable value in an opened netcdf file, given variable name or standard name.
- subroutine `iom_cdf__fill_var_all` (`td_file`, `id_start`, `id_count`)
This subroutine fill all variable value from an opened netcdf file.

11.57.1 Member Function/Subroutine Documentation

11.57.1.1 subroutine `iom_cdf::iom_cdf_fill_var::iom_cdf__fill_var_all` (`type(tfiler)`, `intent(inout) td_file`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_count`)

This subroutine fill all variable value from an opened netcdf file.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array (`'x','y','z','t'`)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension

11.57.1.2 subroutine `iom_cdf::iom_cdf_fill_var::iom_cdf__fill_var_id` (`type(tfiler)`, `intent(inout) td_file`, `integer(i4)`, `intent(in) id_varid`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_count`)

This subroutine fill variable value in an opened netcdf file, given variable id.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array (`'x','y','z','t'`)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

11.57.1.3 subroutine `iom_cdf::iom_cdf_fill_var::iom_cdf_fill_var_name` (type(tfile), intent(inout) *td_file*, character(len=*)
intent(in) *cd_name*, integer(i4), dimension(:), intent(in), optional *id_start*, integer(i4), dimension(:), intent(in), optional
id_count)

This subroutine fill variable value in an opened netcdf file, given variable name or standard name.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t')

look first for variable name. If it doesn't exist in file, look for variable standard name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_file</i>	file structure
in	<i>cd_name</i>	variable name or standard name
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

The documentation for this interface was generated from the following file:

- src/iom_cdf.f90

11.58 iom_cdf::iom_cdf_read_att Interface Reference

Public Member Functions

- TYPE(TATT) function `iom_cdf__read_att_id` (*td_file*, *id_varid*, *id_attid*)
This function read variable or global attribute in an opened netcdf file, given attribute id.
- TYPE(TATT) function `iom_cdf__read_att_name` (*td_file*, *id_varid*, *cd_name*)
This function read variable or global attribute in an opened netcdf file, given attribute name.

11.58.1 Member Function/Subroutine Documentation

11.58.1.1 TYPE(TATT) function `iom_cdf::iom_cdf_read_att::iom_cdf_read_att_id` (type(tfile), intent(in) *td_file*, integer(i4),
intent(in) *id_varid*, integer(i4), intent(in) *id_attid*)

This function read variable or global attribute in an opened netcdf file, given attribute id.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id. use NF90_GLOBAL to read global attribute in a file
in	<i>id_attid</i>	attribute id

Returns

attribute structure

11.58.1.2 TYPE(TATT) function `iom_cdf::iom_cdf_read_att::iom_cdf_read_att_name (type(tfiler), intent(in) td_file, integer(i4), intent(in) id_varid, character(len=*), intent(in) cd_name)`

This function read variable or global attribute in an opened netcdf file, given attribute name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id. use NF90_GLOBAL to read global attribute in a file
in	<i>cd_name</i>	attribute name

Returns

attribute structure

The documentation for this interface was generated from the following file:

- `src/iom_cdf.f90`

11.59 iom_cdf::iom_cdf_read_dim Interface Reference

Public Member Functions

- TYPE(TDIM) function `iom_cdf__read_dim_id` (`td_file`, `id_dimid`)
This function read one dimension in an opened netcdf file, given dimension id.
- TYPE(TDIM) function `iom_cdf__read_dim_name` (`td_file`, `cd_name`)
This function read one dimension in an opened netcdf file, given dimension name.

11.59.1 Member Function/Subroutine Documentation

11.59.1.1 TYPE(TDIM) function `iom_cdf::iom_cdf_read_dim::iom_cdf_read_dim_id (type(tfiler), intent(in) td_file, integer(i4), intent(in) id_dimid)`

This function read one dimension in an opened netcdf file, given dimension id.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015 - create unused dimension, when reading dimension of length less or equal to zero

Parameters

in	<i>td_file</i>	file structure
in	<i>id_dimid</i>	dimension id

Returns

dimension structure

11.59.1.2 TYPE(TDIM) function `iom_cdf::iom_cdf_read_dim::iom_cdf_read_dim_name (type(tfile), intent(in) td_file, character(len=*), intent(in) cd_name)`

This function read one dimension in an opened netcdf file, given dimension name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>cd_name</i>	dimension name

Returns

dimension structure

The documentation for this interface was generated from the following file:

- `src/iom_cdf.f90`

11.60 iom_cdf::iom_cdf_read_var Interface Reference

Public Member Functions

- TYPE(TVAR) function `iom_cdf__read_var_id` (`td_file`, `id_varid`, `id_start`, `id_count`)
This function read variable value in an opened netcdf file, given variable id.
- TYPE(TVAR) function `iom_cdf__read_var_name` (`td_file`, `cd_name`, `id_start`, `id_count`)
This function read variable value in an opened netcdf file, given variable name or standard name.

11.60.1 Member Function/Subroutine Documentation

11.60.1.1 TYPE(TVAR) function `iom_cdf::iom_cdf_read_var::iom_cdf__read_var_id` (`type(tfile)`, `intent(in) td_file`, `integer(i4)`, `intent(in) id_varid`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_count`)

This function read variable value in an opened netcdf file, given variable id.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t')

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
<code>in</code>	<code>id_varid</code>	variable id
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension

Returns

variable structure

11.60.1.2 TYPE(TVAR) function `iom_cdf::iom_cdf_read_var::iom_cdf__read_var_name` (`type(tfile)`, `intent(in) td_file`, `character(len=*)`, `intent(in)`, optional `cd_name`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, optional `id_count`)

This function read variable value in an opened netcdf file, given variable name or standard name.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t')

look first for variable name. If it doesn't exist in file, look for variable standard name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
<code>in</code>	<code>cd_name</code>	variable name or standard name.
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read

in	id_count	number of indices selected along each dimension
----	----------	---

Returns

variable structure

The documentation for this interface was generated from the following file:

- src/iom_cdf.f90

11.61 iom_dom Module Reference

This module allow to read domain (defined as domain structure) in a mpp files.

Data Types

- interface [iom_dom_read_var](#)

Public Member Functions

- subroutine, public [iom_dom_open](#) (td_mpp, td_dom, id_perio, id_ew)
This subroutine open files composing mpp structure over domain to be used.
- subroutine, public [iom_dom_close](#) (td_mpp)
This subroutine close files composing mpp structure.

11.61.1 Detailed Description

This module allow to read domain (defined as domain structure) in a mpp files.

to read one variable in an mpp files over domain defined as domain structure:


```
tl_var=iom_dom_read_var( td_mpp, id_varid, td_dom )
```

or

```
tl_var=iom_dom_read_var( td_mpp, cd_name, td_dom )
```

- td_mpp is a mpp structure
- id_varid is a variable id
- cd_name is variable name or standard name
- td_dom is a domain structure

Author

J.Paul

Date

October, 2014 - Initial Version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.61.2 Member Function/Subroutine Documentation

11.61.2.1 subroutine, public iom_dom::iom_dom_close (type(tmpp), intent(inout) *td_mpp*)

This subroutine close files composing mpp structure.

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

<i>in</i>	<i>td_mpp</i>	mpp structure
-----------	---------------	---------------

11.61.2.2 subroutine, public iom_dom::iom_dom_open (type(tmpp), intent(inout) *td_mpp*, type(tdom), intent(in) *td_dom*, integer(i4), intent(in), optional *id_perio*, integer(i4), intent(in), optional *id_ew*)

This subroutine open files composing mpp structure over domain to be used.

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
----------------	---------------	---------------

The documentation for this module was generated from the following file:

- src/iom_dom.f90

11.62 iom_dom::iom_dom_read_var Interface Reference

Public Member Functions

- TYPE(TVAR) function [iom_dom__read_var_id](#) (*td_mpp*, *id_varid*, *td_dom*)
This function read variable value in opened mpp files, given variable id and domain structure.
- TYPE(TVAR) function [iom_dom__read_var_name](#) (*td_mpp*, *cd_name*, *td_dom*)
This function read variable value in opened mpp files, given variable name or standard name, and domain structure.

11.62.1 Member Function/Subroutine Documentation

11.62.1.1 TYPE(TVAR) function iom_dom::iom_dom_read_var::iom_dom__read_var_id (type(tmpp), intent(in) *td_mpp*, integer(i4), intent(in) *id_varid*, type(tdom), intent(in) *td_dom*)

This function read variable value in opened mpp files, given variable id and domain structure.

Optionally start indices and number of point to be read could be specify. as well as East West overlap of the global domain.

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>id_varid</i>	variable id
in	<i>td_dom</i>	domain structure

Returns

variable structure

11.62.1.2 TYPE(TVAR) function `iom_dom::iom_dom_read_var::iom_dom__read_var_name (type(tmpp), intent(in) td_mpp, character(len=*), intent(in) cd_name, type(tdom), intent(in) td_dom)`

This function read variable value in opened mpp files, given variable name or standard name, and domain structure. Optionally start indices and number of point to be read could be specify. as well as East West overlap of the global domain.

look first for variable name. If it doesn't exist in file, look for variable standard name.

If variable name is not present, check variable standard name.

Author

J.Paul

Date

October, 2014 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>cd_name</i>	variable name
in	<i>td_dom</i>	domain structure

Returns

variable structure

The documentation for this interface was generated from the following file:

- `src/iom_dom.f90`

11.63 iom_mpp Module Reference

This module manage massively parallel processing Input/Output manager. Library to read/write mpp files.

Data Types

- interface [iom_mpp_read_var](#)

Public Member Functions

- subroutine, public [iom_mpp_open](#) (td_mpp, id_perio, id_ew)
This subroutine open files composing mpp structure to be used.
- subroutine, public [iom_mpp_create](#) (td_mpp)
This subroutine create files, composing mpp structure to be used, in write mode.
- subroutine, public [iom_mpp_close](#) (td_mpp)
This subroutine close files composing mpp structure.
- subroutine, public [iom_mpp_write_file](#) (td_mpp, cd_dimorder)
This subroutine write files composing mpp structure.

11.63.1 Detailed Description

This module manage massively parallel processing Input/Output manager. Library to read/write mpp files.

to open mpp files (only file to be used (see mpp_get_use) will be open):


```
CALL iom_mpp_open(td_mpp)
```

- td_mpp is a mpp structure

to creates mpp files:

```
CALL iom_mpp_create(td_mpp)
```

- td_mpp is a mpp structure

to write in mpp files :

```
CALL iom_mpp_write_file(td_mpp)
```

- td_mpp is a mpp structure

to close mpp files:

```
CALL iom_mpp_close(td_mpp)
```

to read one variable in an mpp files:

```
tl_var=iom_mpp_read_var( td_mpp, id_varid, [id_start, id_count] [,id_ew] )
```

or

```
tl_var=iom_mpp_read_var( td_mpp, cd_name, [id_start, id_count] [,id_ew] )
```

- td_mpp is a mpp structure
- id_varid is a variable id
- cd_name is variable name or standard name
- id_start is a integer(4) 1D array of index from which the data values will be read [optional]
- id_count is a integer(4) 1D array of the number of indices selected along each dimension [optional]
- id_ew East West overlap [optional]

to fill variable value in mpp structure:

```
CALL iom_mpp_fill_var(td_mpp, id_varid, [id_start, id_count] [,id_ew] )
```

or

```
CALL iom_mpp_fill_var(td_mpp, cd_name, [id_start, id_count] [,id_ew] )
```

- `td_mpp` is mpp structure
- `id_varid` is variable id
- `cd_name` is variable name or standard name
- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]
- `id_ew` East West overlap [optional]

to fill all variable in mpp structure:

```
CALL iom_mpp_fill_var(td_mpp, [id_start, id_count] [,id_ew] )
```

- `td_mpp` is mpp structure
- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]
- `id_ew` East West overlap

to write files composing mpp structure:

```
CALL iom_mpp_write_file(td_mpp)
```

Author

J.Paul

Date

November, 2013 - Initial Version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.63.2 Member Function/Subroutine Documentation

11.63.2.1 subroutine, public `iom_mpp::iom_mpp_close (type(tmpp), intent(inout) td_mpp)`

This subroutine close files composing mpp structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_mpp</code>	mpp structure
-----------------	---------------------	---------------

11.63.2.2 subroutine, public `iom_mpp::iom_mpp_create (type(tmpp), intent(inout) td_mpp)`

This subroutine create files, composing mpp structure to be used, in write mode.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_mpp</code>	mpp structure
----------------------	---------------------	---------------

11.63.2.3 subroutine, public `iom_mpp::iom_mpp_open (type(tmpp), intent(inout) td_mpp, integer(i4), intent(in), optional id_perio, integer(i4), intent(in), optional id_ew)`

This subroutine open files composing mpp structure to be used.

If try to open a file in write mode that did not exist, create it.

If file already exist, get information about:

- the number of variables
- the number of dimensions
- the number of global attributes
- the ID of the unlimited dimension
- the file format and finally read dimensions.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_mpp</code>	mpp structure
----------------------	---------------------	---------------

11.63.2.4 subroutine, public `iom_mpp::iom_mpp_write_file (type(tmpp), intent(inout) td_mpp, character(len=*) , intent(in), optional cd_dimorder)`

This subroutine write files composing mpp structure.

optionally, you could specify the dimension order (default 'xyzt')

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015 - add dimension order option

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
	<i>ln]</i>	cd_dimorder dimension order

The documentation for this module was generated from the following file:

- src/iom_mpp.f90

11.64 iom_mpp::iom_mpp_read_var Interface Reference

Public Member Functions

- TYPE(TVAR) function [iom_mpp__read_var_id](#) (*td_mpp*, *id_varid*, *id_start*, *id_count*)
This function read variable value in opened mpp files, given variable id.
- TYPE(TVAR) function [iom_mpp__read_var_name](#) (*td_mpp*, *cd_name*, *id_start*, *id_count*)
This function read variable value in opened mpp files, given variable name or standard name.

11.64.1 Member Function/Subroutine Documentation

11.64.1.1 TYPE(TVAR) function `iom_mpp::iom_mpp_read_var::iom_mpp__read_var_id (type(tmpp), intent(in) td_mpp, integer(i4), intent(in) id_varid, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count)`

This function read variable value in opened mpp files, given variable id.

Optionally start indices and number of point to be read could be specify. as well as East West overlap of the global domain.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- use start and count array instead of domain structure.

Parameters

<i>in</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>id_varid</i>	variable id

in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

Returns

variable structure

11.64.1.2 TYPE(TVAR) function `iom_mpp::iom_mpp_read_var::iom_mpp_read_var_name (type(tmpp), intent(in) td_mpp, character(len=*) cd_name, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count)`

This function read variable value in opened mpp files, given variable name or standard name.

Optionally start indices and number of point to be read could be specify. as well as East West overlap of the global domain.

look first for variable name. If it doesn't exist in file, look for variable standard name.

If variable name is not present, check variable standard name.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- use start and count array instead of domain structure.

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>cd_name</i>	variable name
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

Returns

variable structure

The documentation for this interface was generated from the following file:

- `src/iom_mpp.f90`

11.65 iom::iom_read_att Interface Reference

Public Member Functions

- TYPE(TATT) function `iom__read_att_varname_id` (`td_file`, `cd_varname`, `id_attid`)

This function read attribute (of variable or global) in an opened file, given variable name or standard name and attribute id.

- **given**
- **variable**
- **name**
- **or**

- **standard**
- **name**
- **and**
- **attribute**
- **id**
- TYPE(TATT) function `iom__read_att_varid_id` (td_file, id_varid, id_attid)
 - This function read attribute (of variable or global) in an opened file, given variable id and attribute id.*
- **given**
- **variable**
- **id**
- **and**
- **attribute**
- **id**
- TYPE(TATT) function `iom__read_att_varname_name` (td_file, cd_varname, cd_attname)
 - This function read attribute (of variable or global) in an opened file, given variable name or standard name, and attribute name.*
- **given**
- **variable**
- **name**
- **or**
- **standard**
- **name**
- **and**
- **attribute**
- **name**
- TYPE(TATT) function `iom__read_att_varid_name` (td_file, id_varid, cd_attname)
 - This function read attribute (of variable or global) in an opened file, given variable id and attribute name.*
- **given**
- **variable**
- **id**
- **and**
- **attribute**
- **name**

11.65.1 Member Function/Subroutine Documentation

11.65.1.1 TYPE(TATT) function `iom::iom_read_att::iom__read_att_varid_id` (type(tfiler), intent(in) *td_file*, integer(i4), intent(in) *id_varid*, integer(i4), intent(in) *id_attid*)

This function read attribute (of variable or global) in an opened file, given variable id and attribute id.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id. use NF90_GLOBAL to read global attribute in a file
in	<i>id_attid</i>	attribute id

Returns

attribute structure

11.65.1.2 TYPE(TATT) function `iom::iom_read_att::iom__read_att_varid_name (type(tfile), intent(in) td_file, integer(i4), intent(in) id_varid, character(len=*), intent(in) cd_attname)`

This function read attribute (of variable or global) in an opened file, given variable id and attribute name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id. use NF90_GLOBAL to read global attribute in a file
in	<i>cd_attname</i>	attribute name

Returns

attribute structure

11.65.1.3 TYPE(TATT) function `iom::iom_read_att::iom__read_att_varname_id (type(tfile), intent(in) td_file, character(len=lc), intent(in) cd_varname, integer(i4), intent(in) id_attid)`

This function read attribute (of variable or global) in an opened file, given variable name or standard name and attribute id.

- to get global attribute use 'GLOBAL' as variable name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>cd_varname</i>	variable name. use 'GLOBAL' to read global attribute in a file
in	<i>id_attid</i>	attribute id

Returns

attribute structure

11.65.1.4 TYPE(TATT) function `iom::iom_read_att::iom_read_att_varname_name (type(tfile), intent(in) td_file, character(len=*), intent(in) cd_varname, character(len=*), intent(in) cd_attname)`

This function read attribute (of variable or global) in an opened file, given variable name or standard name, and attribute name.

- to get global attribute use 'GLOBAL' as variable name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<code>td_file</code>	file structure
in	<code>cd_varname</code>	variable name or standard name. use 'GLOBAL' to read global attribute in a file
in	<code>cd_attname</code>	attribute name

Returns

attribute structure

The documentation for this interface was generated from the following files:

- `src/iom.f90`

11.66 iom::iom_read_dim Interface Reference

Public Member Functions

- TYPE(TDIM) function `iom__read_dim_id` (`td_file`, `id_dimid`)
This function read one dimension in an opened file, given dimension id.
- TYPE(TDIM) function `iom__read_dim_name` (`td_file`, `cd_name`)
This function read one dimension in an opened netcdf file, given dimension name.

11.66.1 Member Function/Subroutine Documentation

11.66.1.1 TYPE(TDIM) function `iom::iom_read_dim::iom__read_dim_id (type(tfile), intent(in) td_file, integer(i4), intent(in) id_dimid)`

This function read one dimension in an opened file, given dimension id.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_dimid</i>	dimension id

Returns

dimension structure

11.66.1.2 TYPE(TDIM) function `iom::iom_read_dim::iom__read_dim_name (type(tfile), intent(in) td_file, character(len=*), intent(in) cd_name)`

This function read one dimension in an opened netcdf file, given dimension name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>cd_name</i>	dimension name

Returns

dimension structure

The documentation for this interface was generated from the following file:

- `src/iom.f90`

11.67 iom::iom_read_var Interface Reference

Public Member Functions

- TYPE(TVAR) function `iom__read_var_id` (`td_file`, `id_varid`, `id_start`, `id_count`)
This function read variable value in an opened file, given variable id.
- TYPE(TVAR) function `iom__read_var_name` (`td_file`, `cd_name`, `id_start`, `id_count`)
This function read variable value in an opened file, given variable name or standard name.

11.67.1 Member Function/Subroutine Documentation

11.67.1.1 TYPE(TVAR) function `iom::iom_read_var::iom__read_var_id (type(tfile), intent(in) td_file, integer(i4), intent(in) id_varid, integer(i4), dimension(ip_maxdim), intent(in), optional id_start, integer(i4), dimension(ip_maxdim), intent(in), optional id_count)`

This function read variable value in an opened file, given variable id.

start indices and number of indices selected along each dimension could be specify in a 4 dimension array (`'x','y','z','t'`)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>id_varid</i>	variable id
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

Returns

variable structure

11.67.1.2 TYPE(TVAR) function `iom::iom_read_var::iom__read_var_name (type(tfile), intent(in) td_file, character(len=*), intent(in) cd_name, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count)`

This function read variable value in an opened file, given variable name or standard name.

start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t')

look first for variable name. If it doesn't exist in file, look for variable standard name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>cd_name</i>	variable name or standard name
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

Returns

variable structure

The documentation for this interface was generated from the following file:

- src/iom.f90

11.68 iom_rstdimg Module Reference

This module is a library to read/write dimg file.

Data Types

- interface [iom_rstdimg_read_dim](#)
- interface [iom_rstdimg_read_var](#)

Public Member Functions

- subroutine, public [iom_rstdimg_open](#) (td_file)
This subroutine open a dimg file in read or write mode.
- subroutine, public [iom_rstdimg_close](#) (td_file)
This subroutine close dimg file.
- subroutine, public [iom_rstdimg_get_mpp](#) (td_file)
This subroutine get sub domain decomposition in a dimg file.
- subroutine, public [iom_rstdimg_write_file](#) (td_file)
This subroutine write dimg file from file structure.

11.68.1 Detailed Description

This module is a library to read/write dimg file.

to open dimg file (create file structure):


```
CALL iom_rstdimg_open(td_file)
```

- td_file is file structure (see file.f90)

to write in dimg file:

```
CALL iom_rstdimg_write_file(td_file)
```

to close dimg file:

```
CALL iom_rstdimg_close(tl_file)
```

to read one dimension in dimg file:

```
tl_dim = iom_rstdimg_read_dim(tl_file, id_dimid)
```

or

```
tl_dim = iom_rstdimg_read_dim(tl_file, cd_name)
```

- id_dimid is dimension id
- cd_name is dimension name

to read one variable in dimg file:

```
tl_var = iom_rstdimg_read_var(td_file, id_varid, [id_start, id_count])
```

or

```
tl_var = iom_rstdimg_read_var(td_file, cd_name, [id_start, [id_count]])
```

- `id_varid` is variable id
- `cd_name` is variable name or standard name
- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]

to get sub domain decomposition in a dimg file:

```
CALL iom_rstdimg_get_mpp(td_file)
```

Author

J.Paul

Date

November, 2013 - Initial Version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.68.2 Member Function/Subroutine Documentation

11.68.2.1 subroutine, public `iom_rstdimg::iom_rstdimg_close` (`type(tfile)`, intent(inout) `td_file`)

This subroutine close dimg file.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_file</code>	file structure
----------------------	----------------------	----------------

11.68.2.2 subroutine, public `iom_rstdimg::iom_rstdimg_get_mpp` (`type(tfile)`, intent(inout) `td_file`)

This subroutine get sub domain decomposition in a dimg file.

domain decomposition informations are saved in attributes.

Author

J.Paul

Date

November, 2013 - Initial Version

January, 2016

- mismatch with "halo" indices

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
----------------	----------------	----------------

11.68.2.3 subroutine, public iom_rstdimg::iom_rstdimg_open (type(tfile), intent(inout) *td_file*)

This subroutine open a dimg file in read or write mode.

if try to open a file in write mode that did not exist, create it.

if file already exist, get information about:

- the number of variables
- the number of dimensions
- the number of global attributes
- the ID of the unlimited dimension
- the file format Finally it read dimensions, and 'longitude' variable to compute East-West overlap.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
----------------	----------------	----------------

11.68.2.4 subroutine, public iom_rstdimg::iom_rstdimg_write_file (type(tfile), intent(inout) *td_file*)

This subroutine write dimg file from file structure.

dimg file have to be already opened in write mode.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- use iom_rstdimg__get_rec

Parameters

<i>in, out</i>	<i>td_file</i>	file structure
----------------	----------------	----------------

The documentation for this module was generated from the following file:

- src/iom_rstdimg.f90

11.69 iom_rstdim::iom_rstdim_read_dim Interface Reference

Public Member Functions

- TYPE(TDIM) function `iom_rstdim__read_dim_id` (`td_file`, `id_dimid`)
This function read one dimension in an opened netcdf file, given dimension id.
- TYPE(TDIM) function `iom_rstdim__read_dim_name` (`td_file`, `cd_name`)
This function read one dimension in an opened netcdf file, given dimension name.

11.69.1 Member Function/Subroutine Documentation

11.69.1.1 TYPE(TDIM) function `iom_rstdim::iom_rstdim_read_dim::iom_rstdim__read_dim_id` (`type(tfile)`, `intent(in) td_file`, `integer(i4)`, `intent(in) id_dimid`)

This function read one dimension in an opened netcdf file, given dimension id.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
<code>in</code>	<code>id_dimid</code>	dimension id

Returns

dimension structure

11.69.1.2 TYPE(TDIM) function `iom_rstdim::iom_rstdim_read_dim::iom_rstdim__read_dim_name` (`type(tfile)`, `intent(in) td_file`, `character(len=*)`, `intent(in) cd_name`)

This function read one dimension in an opened netcdf file, given dimension name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
<code>in</code>	<code>cd_name</code>	dimension name

Returns

dimension structure

The documentation for this interface was generated from the following file:

- `src/iom_rstdim.f90`

11.70 iom_rstdimg::iom_rstdimg_read_var Interface Reference

Public Member Functions

- TYPE(TVAR) function `iom_rstdimg__read_var_id` (`td_file`, `id_varid`, `id_start`, `id_count`)
This function read variable value in an opened dimg file, given variable id.
- TYPE(TVAR) function `iom_rstdimg__read_var_name` (`td_file`, `cd_name`, `id_start`, `id_count`)
This function read variable value in an opened dimg file, given variable name or standard name.

11.70.1 Member Function/Subroutine Documentation

11.70.1.1 TYPE(TVAR) function `iom_rstdimg::iom_rstdimg_read_var::iom_rstdimg__read_var_id` (`type(tfile)`, `intent(in) td_file`, `integer(i4)`, `intent(in) id_varid`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`)

This function read variable value in an opened dimg file, given variable id.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t')

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_file</code>	file structure
<code>in</code>	<code>id_varid</code>	variable id
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension

Returns

variable structure

11.70.1.2 TYPE(TVAR) function `iom_rstdimg::iom_rstdimg_read_var::iom_rstdimg__read_var_name` (`type(tfile)`, `intent(in) td_file`, `character(len=*)`, `intent(in) cd_name`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`)

This function read variable value in an opened dimg file, given variable name or standard name.

Optionally, start indices and number of indices selected along each dimension could be specify in a 4 dimension array ('x','y','z','t') look first for variable name. If it doesn't exist in file, look for variable standard name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	file structure
in	<i>cd_name</i>	variable name or standard name
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension

Returns

variable structure

The documentation for this interface was generated from the following file:

- src/iom_rstdimg.f90

11.71 kind Module Reference

This module defines the F90 kind parameter for common data types.

Public Attributes

- integer, parameter, public **sp** = SELECTED_REAL_KIND(6, 37)
single precision (real 4)
- integer, parameter, public **dp** = SELECTED_REAL_KIND(12, 307)
double precision (real 8)
- integer, parameter, public **wp** = **dp**
working precision
- integer, parameter, public **i1** = SELECTED_INT_KIND(1)
single precision (integer 1)
- integer, parameter, public **i2** = SELECTED_INT_KIND(4)
single precision (integer 2)
- integer, parameter, public **i4** = SELECTED_INT_KIND(9)
single precision (integer 4)
- integer, parameter, public **i8** = SELECTED_INT_KIND(14)
double precision (integer 8)
- integer, parameter, public **lc** = 256
Length of Character strings.

11.71.1 Detailed Description

This module defines the F90 kind parameter for common data types.

Author

G. Madec

Date

June, 2006 - Initial Version
December, 2012 - G. Madec

- add a standard length of character strings

Todo

- check i8 max value

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

The documentation for this module was generated from the following file:

- src/kind.f90

11.72 lbc Module Reference

This module groups lateral boundary conditions subroutine.

Data Types

- interface [lbc__hide_nfd](#)
- interface [lbc_hide](#)
- interface [lbc_Ink](#)
- interface [lbc_nfd](#)

11.72.1 Detailed Description

This module groups lateral boundary conditions subroutine.

Warning

keep only non mpp case

Author

G. Madec

Date

June, 1997 - Original code

September, 2002

- F90: Free form and module

Marsh, 2009

- R. Benschila : External north fold treatment

December, 2012

- S.Mocavero, I. Epicoco : Add 'lbc_bdy_Ink' and lbc_obc_Ink' routine to optimize the BDY/OBC communications

December, 2012

- R. Bourdalle-Badie and G. Reffray : add a C1D case

January, 2015

- J.Paul : rewrite with SIREN coding rules

Marsh, 2015

- J.Paul : add hide subroutine

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

The documentation for this module was generated from the following file:

- src/lbc.f90

11.73 lbc::lbc__hide_nfd Interface Reference

Public Member Functions

- subroutine [lbc__hide_nfd_2d](#) (dd_array, cd_type, id_perio, dd_psgn, dd_fill)
This subroutine manage 2D lateral boundary condition : hide North fold treatment without processor exchanges.

11.73.1 Member Function/Subroutine Documentation

- 11.73.1.1 subroutine `lbc::lbc__hide_nfd::lbc__hide_nfd_2d` (real(dp), dimension(:,:), intent(inout) *dd_array*, character(len=*), intent(in) *cd_type*, integer(i4), intent(in) *id_perio*, real(dp), intent(in) *dd_psgn*, real(dp), intent(in), optional *dd_fill*)

This subroutine manage 2D lateral boundary condition : hide North fold treatment without processor exchanges.

Warning

keep only non mpp case
do not use additional halos

Author

J.Paul
• Marsh, 2015- initial version

Parameters

in, out	<i>dd_array</i>	2D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	
in	<i>dd_fill</i>	

The documentation for this interface was generated from the following file:

- src/lbc.f90

11.74 lbc::lbc_hide Interface Reference

Public Member Functions

- subroutine [lbc__hide_lnk_2d](#) (dd_array, cd_type, id_perio, dd_psgn, dd_fill)
This subroutine hide lateral boundary conditions on a 2D array (non mpp case)

11.74.1 Member Function/Subroutine Documentation

- 11.74.1.1 subroutine `lbc::lbc_hide::lbc__hide_lnk_2d` (real(dp), dimension(:,:), intent(inout) *dd_array*, character(len=*), intent(in) *cd_type*, integer(i4), intent(in) *id_perio*, real(dp), intent(in) *dd_psgn*, real(dp), intent(in), optional *dd_fill*)

This subroutine hide lateral boundary conditions on a 2D array (non mpp case)

```
dd_psign = -1 :   change the sign across the north fold
              = 1 : no change of the sign across the north fold
              = 0 : no change of the sign across the north fold and
                  strict positivity preserved: use inner row/column
                  for closed boundaries.
```

Author

J.Paul

- Marsh, 2015- initial version

Parameters

in, out	<i>dd_array</i>	2D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	
in	<i>dd_fill</i>	fillValue

The documentation for this interface was generated from the following file:

- src/lbc.f90

11.75 lbc::lbc_Ink Interface Reference**Public Member Functions**

- subroutine [lbc__Ink_3d](#) (*dd_array*, *cd_type*, *id_perio*, *dd_psgn*, *dd_fill*)
This subroutine set lateral boundary conditions on a 3D array (non mpp case)
- subroutine [lbc__Ink_2d](#) (*dd_array*, *cd_type*, *id_perio*, *dd_psgn*, *dd_fill*)
This subroutine set lateral boundary conditions on a 2D array (non mpp case)

11.75.1 Member Function/Subroutine Documentation

11.75.1.1 subroutine `lbc::lbc_Ink::lbc__Ink_2d` (`real(dp)`, `dimension(:,:)`, `intent(inout) dd_array`, `character(len=*)`, `intent(in) cd_type`, `integer(i4)`, `intent(in) id_perio`, `real(dp)`, `intent(in) dd_psgn`, `real(dp)`, `intent(in)`, `optional dd_fill`)

This subroutine set lateral boundary conditions on a 2D array (non mpp case)

```
dd_psgn = -1 :   change the sign across the north fold
           = 1 : no change of the sign across the north fold
           = 0 : no change of the sign across the north fold and
                 strict positivity preserved: use inner row/column
                 for closed boundaries.
```

Author

J.Paul

- January, 2015- rewrite with SIREN coding rules

Parameters

in, out	<i>dd_array</i>	2D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	
in	<i>dd_fill</i>	fillValue

11.75.1.2 subroutine lbc::lbc_Ink::lbc__Ink_3d (real(dp), dimension(:,:,:), intent(inout) *dd_array*, character(len=*), intent(in) *cd_type*, integer(i4), intent(in) *id_perio*, real(dp), intent(in) *dd_psgn*, real(dp), intent(in), optional *dd_fill*)

This subroutine set lateral boundary conditions on a 3D array (non mpp case)

```
dd_psign = -1 :   change the sign across the north fold
              = 1 : no change of the sign across the north fold
              = 0 : no change of the sign across the north fold and
                    strict positivity preserved: use inner row/column
                    for closed boundaries.
```

Author

J.Paul

- January, 2015- rewrite with SIREN coding rules

Parameters

in, out	<i>dd_array</i>	3D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	
in	<i>dd_fill</i>	fillValue

The documentation for this interface was generated from the following file:

- src/lbc.f90

11.76 lbc::lbc_nfd Interface Reference

Public Member Functions

- subroutine [lbc__nfd_3d](#) (*dd_array*, *cd_type*, *id_perio*, *dd_psgn*)
This subroutine manage 3D lateral boundary condition : North fold treatment without processor exchanges.
- subroutine [lbc__nfd_2d](#) (*dd_array*, *cd_type*, *id_perio*, *dd_psgn*)
This subroutine manage 2D lateral boundary condition : North fold treatment without processor exchanges.

11.76.1 Member Function/Subroutine Documentation

11.76.1.1 subroutine lbc::lbc_nfd::lbc__nfd_2d (real(dp), dimension(:,:), intent(inout) *dd_array*, character(len=*), intent(in) *cd_type*, integer(i4), intent(in) *id_perio*, real(dp), intent(in) *dd_psgn*)

This subroutine manage 2D lateral boundary condition : North fold treatment without processor exchanges.

Warning

keep only non mpp case
do not use additional halos

Author

J.Paul

- January, 2015- rewrite with SIREN coding rules

Parameters

in, out	<i>dd_array</i>	2D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	

11.76.1.2 subroutine lbc::lbc_nfd::lbc_nfd_3d (real(dp), dimension(:,:,:), intent(inout) *dd_array*, character(len=*) , intent(in) *cd_type*, integer(i4), intent(in) *id_perio*, real(dp), intent(in) *dd_psgn*)

This subroutine manage 3D lateral boundary condition : North fold treatment without processor exchanges.

Warning

keep only non mpp case

Author

J.Paul

- January, 2015- rewrite with SIREN coding rules

Parameters

in, out	<i>dd_array</i>	3D array
in	<i>cd_type</i>	point grid
in	<i>id_perio</i>	NEMO periodicity of the grid
in	<i>dd_psgn</i>	

The documentation for this interface was generated from the following file:

- src/lbc.f90

11.77 logger Module Reference

This module manage log file.

Data Types

- type [tlogger](#)

Public Member Functions

- subroutine, public [logger_open](#) (cd_file, cd_verbosity, id_maxerror, id_logid)
This subroutine create a log file with default verbosity ('warning').
- subroutine, public [logger_close](#) ()
This subroutine close a log file.
- subroutine, public [logger_clean](#) ()
This subroutine clean a log structure.
- subroutine, public [logger_flush](#) ()
This subroutine flushing output into log file.
- recursive subroutine, public [logger_header](#) ()
This subroutine write header on log file.

- subroutine, public `logger_footer` ()
This subroutine write footer on log file.
- subroutine, public `logger_trace` (cd_msg, ld_flush)
This subroutine write trace message on log file.
- subroutine, public `logger_debug` (cd_msg, ld_flush)
This subroutine write debug message on log file.
- subroutine, public `logger_info` (cd_msg, ld_flush)
This subroutine write info message on log file.
- subroutine, public `logger_warn` (cd_msg, ld_flush)
This subroutine write warning message on log file.
- subroutine, public `logger_error` (cd_msg, ld_flush)
This subroutine write error message on log file.
- recursive subroutine, public `logger_fatal` (cd_msg)
This subroutine write fatal error message on log file, close log file and stop process.

11.77.1 Detailed Description

This module manage log file.

This module create log file and fill it depending of verbosity.

verbosity could be choosen between :

- trace : Most detailed information.
- debug : Detailed information on the flow through the system.
- info : Interesting runtime events (startup/shutdown).
- warning: Use of deprecated APIs, poor use of API, 'almost' errors, other runtime situations that are undesirable or unexpected, but not necessarily "wrong".
- error : Other runtime errors or unexpected conditions.
- fatal : Severe errors that cause premature termination.
- none : to not create and write any information in logger file.
in this case only FATAL ERROR will be detected.

Note

default verbosity is warning

If total number of error exceeded maximum number authorized, program stop.

to open/create logger file:

```
CALL logger_open(cd_file, [cd_verbosity,] [id_maxerror,] [id_loggerid])
```

- cd_file is logger file name
- cd_verbosity is verbosity to be used [optional, default 'warning']
- id_loggerid is file id [optional, use only to flush]
- id_maxerror is the maximum number of error authorized before program stop [optional, default 5]

to close logger file:

```
CALL logger_close()
```

to clean logger file:

```
CALL logger_clean()
```

to write header in logger file:

```
CALL logger_header()
```

to write footer in logger file:

```
CALL logger_footer()
```

to flushing output:

```
CALL logger_flush()
```

to write TRACE message in logger file:

```
CALL logger_trace(cd_msg [,ld_flush])
```

- cd_msg is TRACE message
- ld_flush to flush output [optional]

to write DEBUG message in logger file:

```
CALL logger_debug(cd_msg [,ld_flush])
```

- cd_msg is DEBUG message
- ld_flush to flush output [optional]

to write INFO message in logger file:

```
CALL logger_info(cd_msg [,ld_flush])
```

- cd_msg is INFO message
- ld_flush to flush output [optional]

to write WARNING message in logger file:

```
CALL logger_warn(cd_msg [,ld_flush])
```

- cd_msg is WARNING message
- ld_flush to flush output [optional]

to write ERROR message in logger file:

```
CALL logger_error(cd_msg [,ld_flush])
```

- cd_msg is ERROR message
- ld_flush to flush output [optional]

to write FATAL message in logger file:

```
CALL logger_fatal(cd_msg)
```

- cd_msg is FATAL message

Examples :

```
CALL logger_open('logfile.txt','info')
```

```
CALL logger_header()  
CALL logger_debug('une info de debug')  
CALL logger_info('une info')  
CALL logger_warn('un warning')  
CALL logger_error('une erreur')  
CALL logger_footer()  
CALL logger_close()  
CALL logger_clean()
```

```
CALL logger_open('logfile.txt')
```

```
CALL logger_header()  
CALL logger_debug('une info de debug')  
CALL logger_info('une info')  
CALL logger_warn('un warning')  
CALL logger_error('une erreur')  
CALL logger_footer()  
CALL logger_close()  
CALL logger_clean()
```

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- check verbosity validity
- add 'none' verbosity level to not used logger file

January, 2016

- add logger_clean subroutine

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.77.2 Member Function/Subroutine Documentation

11.77.2.1 subroutine, public logger::logger_clean ()

This subroutine clean a log structure.

Author

J.Paul

Date

January, 2016 - Initial Version

11.77.2.2 subroutine, public `logger::logger_close ()`

This subroutine close a log file.

Author

J.Paul

Date

November, 2013 - Initial Version

11.77.2.3 subroutine, public `logger::logger_debug (character(len=*), intent(in) cd_msg, logical, intent(in), optional ld_flush)`

This subroutine write debug message on log file.

Optionally you could flush output.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_msg</i>	message to write
<i>in</i>	<i>ld_flush</i>	flushing ouput

11.77.2.4 subroutine, public `logger::logger_error (character(len=*), intent(in) cd_msg, logical, intent(in), optional ld_flush)`

This subroutine write error message on log file.

Optionally you could flush output.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>cd_msg</i>	message to write
<i>in</i>	<i>ld_flush</i>	flushing ouput

11.77.2.5 recursive subroutine, public `logger::logger_fatal (character(len=*), intent(in) cd_msg)`

This subroutine write fatal error message on log file, close log file and stop process.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2015

- stop program for FATAL ERROR if verbosity is none

Parameters

<i>in</i>	<i>cd_msg</i>	message to write
-----------	---------------	------------------

11.77.2.6 subroutine, public logger::logger_flush ()

This subroutine flushing output into log file.

Author

J.Paul

Date

November, 2013 - Initial Version

11.77.2.7 subroutine, public logger::logger_footer ()

This subroutine write footer on log file.

Author

J.Paul

Date

November, 2013 - Initial Version

11.77.2.8 recursive subroutine, public logger::logger_header ()

This subroutine write header on log file.

Author

J.Paul

Date

November, 2013 - Initial Version

11.77.2.9 subroutine, public logger::logger_info (character(len=*), intent(in) *cd_msg*, logical, intent(in), optional *id_flush*)

This subroutine write info message on log file.

Optionally you could flush output.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_msg</i>	message to write
in	<i>id_flush</i>	flushing ouput

11.77.2.10 subroutine, public logger::logger_open (character(len=*), intent(in) *cd_file*, character(len=*), intent(in), optional *cd_verbosity*, integer(i4), intent(in), optional *id_maxerror*, integer(i4), intent(in), optional *id_logid*)

This subroutine create a log file with default verbosity ('warning').

Optionally verbosity could be change to ('trace','debug','info','warning','error','fatal').

Optionally maximum number of error allowed could be change.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_file</i>	log file name
in	<i>cd_verbosity</i>	log file verbosity
in	<i>id_maxerror</i>	maximum number of error
in	<i>id_logid</i>	log file id (use to flush)

11.77.2.11 subroutine, public logger::logger_trace (character(len=*), intent(in) *cd_msg*, logical, intent(in), optional *id_flush*)

This subroutine write trace message on log file.

Optionally you could flush output.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_msg</i>	message to write
in	<i>ld_flush</i>	flushing ouput

11.77.2.12 subroutine, public logger::logger_warn (character(len=*), intent(in) *cd_msg*, logical, intent(in), optional *ld_flush*)

This subroutine write warning message on log file.

Optionally you could flush output.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_msg</i>	message to write
in	<i>ld_flush</i>	flushing ouput

The documentation for this module was generated from the following file:

- src/logger.f90

11.78 math Module Reference

This module groups some useful mathematical function.

Data Types

- interface [math_mean](#)
- interface [math_median](#)
- interface [math_mwe](#)

Public Member Functions

- pure recursive subroutine, public [math_qsortc](#) (dd_array)
This subroutine sort a 1D array.
- pure subroutine, public [math_unwrap](#) (dd_array, dd_discont)
This subroutine correct phase angles to produce smoother phase plots.
- REAL(dp) RECURSIVE function, public [math_compute](#) (cd_var)
This function compute simple operation.
- pure real(dp) function,
dimension(size(dd_value, dim=1)),
public [math_deriv_1d](#) (dd_value, dd_fill, ld_discont)
This function compute derivative of 1D array.
- real(dp) function, dimension(size(dd_value,
dim=1),size(dd_value, dim=2)),
public [math_deriv_2d](#) (dd_value, dd_fill, cd_dim, ld_discont)

This function compute derivative of 2D array. you have to specify in which direction derivative have to be computed: first (I) or second (J) dimension.

- pure real(dp) function,
dimension(size(dd_value, dim=1),size(dd_value,
dim=2),size(dd_value, dim=3)),
public `math_deriv_3d` (dd_value, dd_fill, cd_dim, ld_discont)

This function compute derivative of 3D array. you have to specify in which direction derivative have to be computed: first (I), second (J) or third (K) dimension.

11.78.1 Detailed Description

This module groups some useful mathematical function.

to compute the mean of an array:


```
dl_value=math_mean( dl_value, dd_fill )
```

- dl_value is 1D or 2D array
- dd_fill is FillValue

to compute the median of an array:

```
dl_value=math_median( dl_value, dd_fill )
```

- dl_value is 1D or 2D array
- dd_fill is FillValue

to compute the mean without extremum of an array:

```
dl_value=math_mwe( dl_value, id_next, dd_fill )
```

- dl_value is 1D or 2D array
- id_next is the number of extremum to be removed
- dd_fill is FillValue

to sort an 1D array:

```
CALL math_QsortC(dl_value)
```

- dl_value is 1D array

to correct phase angles to produce smoother phase:

```
CALL math_unwrap(dl_value, [dl_discont])
```

- dl_value is 1D array
- dl_discont maximum discontinuity between values, default pi

to compute simple operation

```
dl_res=math_compute( cl_var )
```


- `cl_var` operation to compute (string of character)
- `dl_res` result of the operation, `real(dp)`

to compute first derivative of 1D array:

```
dl_value(:)=math_deriv_1d( dd_value(:), dd_fill, [ld_discont] )
```

- `dd_value` is 1D array of variable
- `dd_fill` is `FillValue` of variable
- `ld_discont` is logical to take into account longitudinal East-West discontinuity [optional]

to compute first derivative of 2D array:

```
dl_value(:,:)=math_deriv_2d( dd_value(:,:), dd_fill, cd_dim,  
                             [ld_discont] )
```

- `dd_value` is 2D array of variable
- `dd_fill` is `FillValue` of variable
- `cd_dim` is character to compute derivative on first (I) or second (J) dimension
- `ld_discont` is logical to take into account longitudinal East-West discontinuity [optional]

to compute first derivative of 3D array:

```
dl_value(:,:,:)=math_deriv_3d( dd_value(:,:,:), dd_fill, cd_dim,  
                                [ld_discont] )
```

- `dd_value` is 3D array of variable
- `dd_fill` is `FillValue` of variable
- `cd_dim` is character to compute derivative on first (I), second (J), or third (K) dimension
- `ld_discont` is logical to take into account longitudinal East-West discontinuity [optional]

Author

J.Paul

Date

January, 2015 - Initial version

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.78.2 Member Function/Subroutine Documentation

11.78.2.1 REAL(dp) RECURSIVE function, public math::math_compute (character(len=*), intent(in) *cd_var*)

This function compute simple operation.

- operation should be write as a string of character.
- operators allowed are : +,-,*,/
- to ordered operation you should use parentheses

exemples: '1e6/(16/122)', '(3/2)*(2+1)'

Author

J.Paul

Date

June, 2015 - initial version

Parameters

<i>in</i>	<i>cd_var</i>	operation to compute (string of character)
-----------	---------------	--

Returns

result of the operation, real(dp)

11.78.2.2 pure real(dp) function, dimension(size(*dd_value*,dim=1)), public math::math_deriv_1d (real(dp), dimension(:), intent(in) *dd_value*, real(dp), intent(in) *dd_fill*, logical, intent(in), optional *ld_discont*)

This function compute derivative of 1D array.

optionaly you could specify to take into account east west discontinuity (-180° 180° or 0° 360° for longitude variable)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>dd_value</i>	1D array of variable to be extrapolated
<i>in</i>	<i>dd_fill</i>	FillValue of variable
<i>in</i>	<i>ld_discont</i>	logical to take into account east west discontinuity

11.78.2.3 real(dp) function, dimension(size(*dd_value*,dim=1), size(*dd_value*,dim=2)), public math::math_deriv_2d (real(dp), dimension(:,:), intent(in) *dd_value*, real(dp), intent(in) *dd_fill*, character(len=*), intent(in) *cd_dim*, logical, intent(in), optional *ld_discont*)

This function compute derivative of 2D array. you have to specify in which direction derivative have to be computed: first (I) or second (J) dimension.

optionaly you could specify to take into account east west discontinuity (-180° 180° or 0° 360° for longitude variable)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>dd_value</i>	2D array of variable to be extrapolated
in	<i>dd_fill</i>	FillValue of variable
in	<i>cd_dim</i>	compute derivative on first (I) or second (J) dimension
in	<i>ld_discont</i>	logical to take into account east west discontinuity

11.78.2.4 pure real(dp) function, dimension(size(dd_value,dim=1), size(dd_value,dim=2), size(dd_value,dim=3)), public
 math::math_deriv_3d (real(dp), dimension(:, :, :), intent(in) *dd_value*, real(dp), intent(in) *dd_fill*, character(len=*)
 intent(in) *cd_dim*, logical, intent(in), optional *ld_discont*)

This function compute derivative of 3D array. you have to specify in which direction derivative have to be computed: first (I), second (J) or third (K) dimension.

optionaly you could specify to take into account east west discontinuity (-180° 180° or 0° 360° for longitude variable)

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>dd_value</i>	3D array of variable to be extrapolated
in	<i>dd_fill</i>	FillValue of variable
in	<i>cd_dim</i>	compute derivative on first (I) second (J) or third (K) dimension
in	<i>ld_discont</i>	logical to take into account east west discontinuity

11.78.2.5 pure recursive subroutine, public math::math_qsortc (real(dp), dimension(:), intent(inout) *dd_array*)

This subroutine sort a 1D array.

Recursive Fortran 95 quicksort routine sorts real numbers into ascending numerical order Author: Juli Rew, SCD Consulting (juliana@ucar.edu), 9/03 Based on algorithm from Cormen et al., Introduction to Algorithms, 1997 printing

Author

J.Paul

Date

January, 2015 - Rewrite with SIREN coding rules

Parameters

<code>in, out</code>	<code>dd_array</code>	1D array
----------------------	-----------------------	----------

11.78.2.6 pure subroutine, public `math::math_unwrap (real(dp), dimension(:), intent(inout) dd_array, real(dp), intent(in), optional dd_discont)`

This subroutine correct phase angles to produce smoother phase plots.

This code is based on numpy unwrap function

Unwrap by changing deltas between values to 2π complement.

Unwrap radian phase `dd_array` by changing absolute jumps greater than `dd_discont` to their 2π complement.

Note

If the discontinuity in `dd_array` is smaller than `pi`, but larger than `dd_discont`, no unwrapping is done because taking the 2π complement would only make the discontinuity larger.

Author

J.Paul

Date

Marsh, 2015 - Rewrite in fortran, with SIREN coding rules

Parameters

<code>in, out</code>	<code>dd_array</code>	1D array
<code>in</code>	<code>dd_discont</code>	maximum discontinuity between values, default pi

The documentation for this module was generated from the following file:

- `src/math.f90`

11.79 math::math_mean Interface Reference

Public Member Functions

- PURE REAL(dp) function `math__mean_1d` (`dd_array`, `dd_fill`)
This function compute the mean of a 1D array.
- PURE REAL(dp) function `math__mean_2d` (`dd_array`, `dd_fill`)
This function compute the mean of a 2D array.

11.79.1 Member Function/Subroutine Documentation

11.79.1.1 PURE REAL(dp) function `math::math_mean::math__mean_1d (real(dp), dimension(:), intent(in) dd_array, real(dp), intent(in), optional dd_fill)`

This function compute the mean of a 1D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

in	<i>dd_array</i>	1D array
in	<i>dd_fill</i>	fillValue

Returns

mean value, real(dp)

11.79.1.2 PURE REAL(dp) function `math::math_mean::math__mean_2d` (real(dp), dimension(:,:), intent(in) *dd_array*, real(dp), intent(in), optional *dd_fill*)

This function compute the mean of a 2D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

in	<i>dd_array</i>	2D array
in	<i>dd_fill</i>	fillValue

Returns

mean value, real(dp)

The documentation for this interface was generated from the following file:

- src/math.f90

11.80 math::math_median Interface Reference

Public Member Functions

- PURE REAL(dp) function `math__median_1d` (*dd_array*, *dd_fill*)
This function compute the median of a 1D array.
- PURE REAL(dp) function `math__median_2d` (*dd_array*, *dd_fill*)
This function compute the median of a 2D array.

11.80.1 Member Function/Subroutine Documentation

11.80.1.1 PURE REAL(dp) function `math::math_median::math__median_1d` (`real(dp)`, `dimension(:)`, `intent(in) dd_array`, `real(dp)`, `intent(in)`, optional `dd_fill`)

This function compute the median of a 1D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

<code>in</code>	<code>dd_array</code>	1D array
<code>in</code>	<code>dd_fill</code>	fillValue

Returns

median value, `real(dp)`

11.80.1.2 PURE REAL(dp) function `math::math_median::math__median_2d` (`real(dp)`, `dimension(:,:)`, `intent(in) dd_array`, `real(dp)`, `intent(in)`, optional `dd_fill`)

This function compute the median of a 2D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

<code>in</code>	<code>dd_array</code>	2D array
<code>in</code>	<code>dd_fill</code>	fillValue

Returns

median value, `real(dp)`

The documentation for this interface was generated from the following file:

- `src/math.f90`

11.81 `math::math_mwe` Interface Reference

Public Member Functions

- PURE REAL(dp) function `math__mwe_1d` (`dd_array`, `id_next`, `dd_fill`)
This function compute the mean without extremum of a 1D array.
- PURE REAL(dp) function `math__mwe_2d` (`dd_array`, `id_next`, `dd_fill`)
This function compute the mean without extremum of a 2D array.

11.81.1 Member Function/Subroutine Documentation

11.81.1.1 PURE REAL(dp) function `math::math_mwe::math__mwe_1d` (`real(dp)`, `dimension(:)`, `intent(in) dd_array`, `integer(i4)`, `intent(in)`, optional `id_next`, `real(dp)`, `intent(in)`, optional `dd_fill`)

This function compute the mean without extremum of a 1D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

<code>in</code>	<code>dd_array</code>	1D array
<code>in</code>	<code>id_next</code>	number of extremum to be removed
<code>in</code>	<code>dd_fill</code>	fillValue

Returns

median value, `real(dp)`

11.81.1.2 PURE REAL(dp) function `math::math_mwe::math__mwe_2d` (`real(dp)`, `dimension(:,:)`, `intent(in) dd_array`, `integer(i4)`, `intent(in)`, optional `id_next`, `real(dp)`, `intent(in)`, optional `dd_fill`)

This function compute the mean without extremum of a 2D array.

Author

J.Paul

Date

January, 2015 - Initial Version

Parameters

<code>in</code>	<code>dd_array</code>	2D array
<code>in</code>	<code>id_next</code>	number of extremum to be removed
<code>in</code>	<code>dd_fill</code>	fillValue

Returns

median value, `real(dp)`

The documentation for this interface was generated from the following file:

- `src/math.f90`

11.82 mpp Module Reference

This module manage massively parallel processing.

Data Types

- interface [mpp__add_proc](#)
- interface [mpp__check_dim](#)
- interface [mpp__del_proc](#)
- interface [mpp_clean](#)
- interface [mpp_copy](#)
- interface [mpp_del_att](#)
- interface [mpp_del_var](#)
- interface [mpp_get_use](#)
- interface [mpp_init](#)
- type [tlay](#)
domain layout structure
- type [tmpp](#)

Public Member Functions

- subroutine, public [mpp_print](#) (td_mpp)
This subroutine print some information about mpp structure.
- subroutine, public [mpp_add_var](#) (td_mpp, td_var)
This subroutine add variable in all files of mpp structure.
- subroutine, public [mpp_move_var](#) (td_mpp, td_var)
This subroutine overwrite variable in mpp structure.
- subroutine, public [mpp_add_dim](#) (td_mpp, td_dim)
This subroutine add a dimension structure in a mpp structure. Do not overwrite, if dimension already in mpp structure.
- subroutine, public [mpp_del_dim](#) (td_mpp, td_dim)
This subroutine delete a dimension structure in a mpp structure.
- subroutine, public [mpp_move_dim](#) (td_mpp, td_dim)
This subroutine move a dimension structure in mpp structure.
- subroutine, public [mpp_add_att](#) (td_mpp, td_att)
This subroutine add global attribute to mpp structure.
- subroutine, public [mpp_move_att](#) (td_mpp, td_att)
This subroutine overwrite attribute in mpp structure.
- subroutine, public [mpp_get_contour](#) (td_mpp)
This subroutine get sub domains which form global domain border.
- integer(i4) function,
dimension(4), public [mpp_get_proc_index](#) (td_mpp, id_procid)
This function return processor indices, without overlap boundary, given processor id.
- integer(i4) function,
dimension(2), public [mpp_get_proc_size](#) (td_mpp, id_procid)
This function return processor domain size, depending of domain decomposition type, given sub domain id.
- subroutine, public [mpp_get_dom](#) (td_mpp)
This subroutine determine domain decomposition type. (full, overlap, noverlap)
- INTEGER(i4) function, public [mpp_get_index](#) (td_mpp, cd_name)
This function return the mpp id, in a array of mpp structure, given mpp base name.
- TYPE(TVAR) function, public [mpp_recombine_var](#) (td_mpp, cd_name)
This function recombine variable splitted mpp structure.

Public Attributes

- integer(i4) **im_iumout** = 44
- logical **Im_layout** = .FALSE.

11.82.1 Detailed Description

This module manage massively parallel processing.

define type TMPP:

```
TYPE(tmpp) :: tl_mpp
```

to initialise a mpp structure:

```
tl_mpp=mpp_init( cd_file, id_mask,
                [id_niproc,] [id_njproc,] [id_nproc,]
                [id_preci,] [id_precj,]
                [cd_type,] [id_ew])
```

or

```
tl_mpp=mpp_init( cd_file, td_var,
                [id_niproc,] [id_njproc,] [id_nproc,]
                [id_preci,] [id_precj,]
                [cd_type] )
```

or

```
tl_mpp=mpp_init( td_file [,id_ew] )
```

- `cd_file` is the filename of the global domain file, in which MPP will be done (example: Bathymetry)
- `td_file` is the file structure of one processor file composing an MPP
- `id_mask` is the 2D mask of global domain [optional]
- `td_var` is a variable structure (on T-point) from global domain file. mask of the domain will be computed using FillValue [optional]
- `id_niproc` is the number of processor following I-direction to be used [optional]
- `id_njproc` is the number of processor following J-direction to be used [optional]
- `id_nproc` is the total number of processor to be used [optional]
- `id_preci` is the size of the overlap region following I-direction [optional]
- `id_precj` is the size of the overlap region following J-direction [optional]
- `cd_type` is the type of files composing MPP [optional]
- `id_ew` is east-west overlap [optional]

to get mpp name:

- `tl_mpp%c_name`

to get the total number of processor:

- `tl_mpp%i_nproc`

to get the number of processor following I-direction:

- `tl_mpp%i_niproc`

to get the number of processor following J-direction:

- `tl_mpp%i_njproc`

to get the length of the overlap region following I-direction:

- `tl_mpp%i_prci`

to get the length of the overlap region following J-direction:

- `tl_mpp%i_prcj`

to get the type of files composing mpp structure:

- `tl_mpp%c_type`

to get the type of the global domain:

- `tl_mpp%c_dom`

MPP dimensions (global domain)

to get the number of dimensions to be used in mpp structure:

- `tl_mpp%i_ndim`

to get the array of dimension structure (4 elts) associated to the mpp structure:

- `tl_mpp%t_dim(:)`

MPP processor (files composing domain)

- `tl_mpp%t_proc(:)`

to clean a mpp structure:

```
CALL mpp_clean(tl_mpp)
```

to print information about mpp:

```
CALL mpp_print(tl_mpp)
```

to add variable to mpp:

```
CALL mpp_add_var(td_mpp, td_var)
```

- `td_var` is a variable structure

to add dimension to mpp:

```
CALL mpp_add_dim(td_mpp, td_dim)
```

- `td_dim` is a dimension structure

to add attribute to mpp:

```
CALL mpp_add_att(td_mpp, td_att)
```

- `td_att` is a attribute structure

to delete variable from mpp:

```
CALL mpp_del_var(td_mpp, td_var)
```

or

```
CALL mpp_del_var(td_mpp, cd_name)
```

- `td_var` is a variable structure
- `cd_name` is variable name or standard name

to delete dimension from mpp:

```
CALL mpp_del_dim(td_mpp, td_dim)
```

- `td_dim` is a dimension structure

to delete attribute from mpp:

```
CALL mpp_del_att(td_mpp, td_att)
```

or

```
CALL mpp_del_att(td_mpp, cd_name)
```

- `td_att` is a attribute structure
- `cd_name` is attribute name

to overwrite variable to mpp:

```
CALL mpp_move_var(td_mpp, td_var)
```

- `td_var` is a variable structure

to overwrite dimension to mpp:

```
CALL mpp_move_dim(td_mpp, td_dim)
```

- `td_dim` is a dimension structure

to overwrite attribute to mpp:

```
CALL mpp_move_att(td_mpp, td_att)
```

- `td_att` is a attribute structure

to determine domain decomposition type:

```
CALL mpp_get_dom(td_mpp)
```

to get processors to be used:

```
CALL mpp_get_use( td_mpp, id_imin, id_imax, &  
& id_jmin, id_jmax )
```

- id_imin
- id_imax
- id_jmin
- id_jmax

to get sub domains which form global domain contour:

```
CALL mpp_get_contour( td_mpp )
```

to get global domain indices of one processor:

```
il_ind(1:4)=mpp_get_proc_index( td_mpp, id_procid )
```

- il_ind(1:4) are global domain indices (i1,i2,j1,j2)
- id_procid is the processor id

to get the processor domain size:

```
il_size(1:2)=mpp_get_proc_size( td_mpp, id_procid )
```

- il_size(1:2) are the size of domain following I and J
- id_procid is the processor id

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- Fix memory leaks bug

October, 2015

- improve way to compute domain layout

January, 2016

- allow to print layout file (use lm_layout, hard coded)
- add mpp__compute_halo and mpp__read_halo

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.82.2 Member Function/Subroutine Documentation

11.82.2.1 subroutine, public mpp::mpp_add_att (type(tmpp), intent(inout) *td_mpp*, type(tatt), intent(in) *td_att*)

This subroutine add global attribute to mpp structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>td_att</i>	attribute structure

11.82.2.2 subroutine, public mpp::mpp_add_dim (type(tmpp), intent(inout) *td_mpp*, type(tdim), intent(in) *td_dim*)

This subroutine add a dimension structure in a mpp structure. Do not overwrite, if dimension already in mpp structure.

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- rewrite the same as way var_add_dim

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.82.2.3 subroutine, public mpp::mpp_add_var (type(tmpp), intent(inout) *td_mpp*, type(tvar), intent(inout) *td_var*)

This subroutine add variable in all files of mpp structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>td_var</i>	variable structure

11.82.2.4 subroutine, public mpp::mpp_del_dim (type(tmpp), intent(inout) *td_mpp*, type(tdim), intent(in) *td_dim*)

This subroutine delete a dimension structure in a mpp structure.

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- rewrite the same as way var_del_dim

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.82.2.5 subroutine, public mpp::mpp_get_contour (type(tmpp), intent(inout) *td_mpp*)

This subroutine get sub domains which form global domain border.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
----------------	---------------	---------------

11.82.2.6 subroutine, public mpp::mpp_get_dom (type(tmpp), intent(inout) *td_mpp*)

This subroutine determine domain decomposition type. (full, overlap, noverlap)

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in, out	<i>td_mpp</i>	mpp structure
---------	---------------	---------------

11.82.2.7 **INTEGER(i4)** function, public `mpp::mpp_get_index (type(tmpp), dimension(:), intent(in) td_mpp, character(len=*), intent(in) cd_name)`

This function return the mpp id, in a array of mpp structure, given mpp base name.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_file</i>	array of file structure
in	<i>cd_name</i>	file name

Returns

file id in array of file structure (0 if not found)

11.82.2.8 **integer(i4)** function, dimension(4), public `mpp::mpp_get_proc_index (type(tmpp), intent(in) td_mpp, integer(i4), intent(in) id_procid)`

This function return processor indices, without overlap boundary, given processor id.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>id_procid</i>	processor id

Returns

array of index (/ i1, i2, j1, j2 /)

11.82.2.9 **integer(i4)** function, dimension(2), public `mpp::mpp_get_proc_size (type(tmpp), intent(in) td_mpp, integer(i4), intent(in) id_procid)`

This function return processor domain size, depending of domain decomposition type, given sub domain id.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>id_procid</i>	sub domain id

Returns

array of index (/ isize, jsize /)

11.82.2.10 subroutine, public mpp::mpp_move_att (type(tmpp), intent(inout) *td_mpp*, type(tatt), intent(in) *td_att*)

This subroutine overwrite attribute in mpp structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in, out	<i>td_mpp</i>	mpp structure
in	<i>td_att</i>	attribute structure

11.82.2.11 subroutine, public mpp::mpp_move_dim (type(tmpp), intent(inout) *td_mpp*, type(tdim), intent(in) *td_dim*)

This subroutine move a dimension structure in mpp structure.

Warning

dimension order may have changed

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_mpp</i>	mpp structure
in	<i>td_dim</i>	dimension structure

11.82.2.12 subroutine, public mpp::mpp_move_var (type(tmpp), intent(inout) *td_mpp*, type(tvar), intent(in) *td_var*)

This subroutine overwrite variable in mpp structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp structure
<i>in</i>	<i>td_var</i>	variable structure

11.82.2.13 subroutine, public mpp::mpp_print (type(tmpp), intent(in) *td_mpp*)

This subroutine print some information about mpp structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_mpp</i>	mpp structure
-----------	---------------	---------------

11.82.2.14 TYPE(TVAR) function, public mpp::mpp_recombine_var (type(tmpp), intent(in) *td_mpp*, character(len=*) *cd_name*)

This function recombine variable splitted mpp structure.

Author

J.Paul

Date

Ocotber, 2014 - Initial Version

Parameters

<i>in</i>	<i>td_mpp</i>	mpp file structure
<i>in</i>	<i>cd_name</i>	variable name

Returns

variable structure

The documentation for this module was generated from the following file:

- src/mpp.f90

11.83 mpp::mpp__add_proc Interface Reference

Public Member Functions

- subroutine [mpp__add_proc_unit](#) (td_mpp, td_proc)

11.83.1 Member Function/Subroutine Documentation

11.83.1.1 subroutine `mpp::mpp__add_proc::mpp__add_proc_unit (type(tmpp), intent(inout) td_mpp, type(tfile), intent(in) td_proc)`

This subroutine add processor to mpp structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<code>in, out</code>	<code><i>td_mpp</i></code>	mpp strcuture
<code>in</code>	<code><i>td_proc</i></code>	processor strcuture

Todo • check proc type

The documentation for this interface was generated from the following file:

- `src/mpp.f90`

11.84 `mpp::mpp__check_dim` Interface Reference

Public Member Functions

- LOGICAL function [`mpp__check_proc_dim`](#) (`td_mpp`, `td_proc`)

This function check if variable and mpp structure use same dimension.

- **check**
- **if**
- **processor**
- **and**
- **mpp**
- **structure**
- **use**
- **same**
- **dimension**

- LOGICAL function [`mpp__check_var_dim`](#) (`td_mpp`, `td_var`)

This function check if variable and mpp structure use same dimension.

- **check**
- **if**
- **variable**
- **and**
- **mpp**
- **structure**
- **use**
- **same**
- **dimension**

11.84.1 Member Function/Subroutine Documentation

11.84.1.1 LOGICAL function `mpp::mpp__check_dim::mpp__check_proc_dim (type(tmpp), intent(in) td_mpp, type(tfile), intent(in) td_proc)`

This function check if variable and mpp structure use same dimension.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>td_proc</i>	processor structure

Returns

dimension of processor and mpp structure agree (or not)

11.84.1.2 LOGICAL function `mpp::mpp__check_dim::mpp__check_var_dim (type(tmpp), intent(in) td_mpp, type(tvar), intent(in) td_var)`

This function check if variable and mpp structure use same dimension.

Author

J.Paul

Date

November, 2013 - Initial Version
September 2015

- do not check used dimension here

Parameters

in	<i>td_mpp</i>	mpp structure
in	<i>td_var</i>	variable structure

Returns

dimension of variable and mpp structure agree (or not)

The documentation for this interface was generated from the following files:

- `src/mpp.f90`

11.85 mpp::mpp__del_proc Interface Reference

Public Member Functions

- subroutine [mpp__del_proc_id](#) (td_mpp, id_procid)

This subroutine delete processor in mpp structure, given processor id.

- subroutine [mpp__del_proc_str](#) (td_mpp, td_proc)

This subroutine delete processor in mpp structure, given processor structure.

11.85.1 Member Function/Subroutine Documentation

11.85.1.1 subroutine `mpp::mpp__del_proc::mpp__del_proc_id (type(tmpp), intent(inout) td_mpp, integer(i4), intent(in) id_procid)`

This subroutine delete processor in mpp structure, given processor id.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp strcuture
<i>in</i>	<i>id_procid</i>	processor id

11.85.1.2 subroutine `mpp::mpp__del_proc::mpp__del_proc_str (type(tmpp), intent(inout) td_mpp, type(tfile), intent(in) td_proc)`

This subroutine delete processor in mpp structure, given processor structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	: mpp strcuture
<i>in</i>	<i>td_proc</i>	: file/processor structure

The documentation for this interface was generated from the following file:

- src/mpp.f90

11.86 mpp::mpp_clean Interface Reference

Public Member Functions

- subroutine [mpp__clean_unit](#) (td_mpp)
This subroutine clean mpp strcuture.
- subroutine [mpp__clean_arr](#) (td_mpp)
This subroutine clean mpp strcuture.

11.86.1 Member Function/Subroutine Documentation

11.86.1.1 subroutine mpp::mpp_clean::mpp__clean_arr (type(tmpp), dimension(:), intent(inout) *td_mpp*)

This subroutine clean mpp strcuture.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp strcuture
----------------	---------------	---------------

11.86.1.2 subroutine mpp::mpp_clean::mpp__clean_unit (type(tmpp), intent(inout) *td_mpp*)

This subroutine clean mpp strcuture.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp strcuture
----------------	---------------	---------------

The documentation for this interface was generated from the following file:

- src/mpp.f90

11.87 mpp::mpp_copy Interface Reference

Public Member Functions

- type(tmpp) function [mpp__copy_unit](#) (*td_mpp*)
This subroutine copy mpp structure in another one.
- type(tmpp) function, dimension(size(*td_mpp*(:))) [mpp__copy_arr](#) (*td_mpp*)
This subroutine copy an array of mpp structure in another one.

11.87.1 Member Function/Subroutine Documentation

11.87.1.1 type(tmpp) function, dimension(size(*td_mpp*(:))) mpp::mpp_copy::mpp__copy_arr (type(tmpp), dimension(:), intent(in) *td_mpp*)

This subroutine copy an array of mpp structure in another one.

mpp file are copied in a temporary array, so input and output mpp structure do not point on the same "memory cell", and so on are independant.

Warning

do not use on the output of a function who create or read an structure (ex: `tl_file=file_copy(file_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_mpp</code>	mpp structure
-----------------	---------------------	---------------

Returns

copy of input array of mpp structure

11.87.1.2 `type(tmpp)` function `mpp::mpp_copy::mpp__copy_unit (type(tmpp), intent(in) td_mpp)`

This subroutine copy mpp structure in another one.

mpp file are copied in a temporary array, so input and output mpp structure do not point on the same "memory cell", and so on are independant.

Warning

do not use on the output of a function who create or read an structure (ex: `tl_file=file_copy(file_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_mpp</code>	mpp structure
-----------------	---------------------	---------------

Returns

copy of input mpp structure

The documentation for this interface was generated from the following file:

- `src/mpp.f90`

11.88 mpp::mpp_del_att Interface Reference

Public Member Functions

- subroutine [mpp__del_att_name](#) (td_mpp, cd_name)
This subroutine delete attribute in mpp structure, given attribute name.
- subroutine [mpp__del_att_str](#) (td_mpp, td_att)
This subroutine delete attribute in mpp structure, given attribute structure.

11.88.1 Member Function/Subroutine Documentation

11.88.1.1 subroutine `mpp::mpp_del_att::mpp__del_att_name (type(tmpp), intent(inout) td_mpp, character(len=*) intent(in) cd_name)`

This subroutine delete attribute in mpp structure, given attribute name.

Author

J.Paul

Date

November, 2013 - Initial version
February, 2015

- define local attribute structure to avoid mistake with pointer

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp strcuture
<i>in</i>	<i>cd_name</i>	attribute name

11.88.1.2 subroutine `mpp::mpp_del_att::mpp__del_att_str (type(tmpp), intent(inout) td_mpp, type(tatt), intent(in) td_att)`

This subroutine delete attribute in mpp structure, given attribute structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

<i>in, out</i>	<i>td_mpp</i>	mpp strcuture
<i>in</i>	<i>td_att</i>	attribute strcuture

The documentation for this interface was generated from the following file:

- `src/mpp.f90`

11.89 mpp::mpp_del_var Interface Reference

Public Member Functions

- subroutine [mpp__del_var_name](#) (td_mpp, cd_name)
This subroutine delete variable in mpp structure, given variable name.
- subroutine [mpp__del_var_str](#) (td_mpp, td_var)
This subroutine delete variable in mpp structure, given variable structure.
- subroutine [mpp__del_var_mpp](#) (td_mpp)
This subroutine delete all variable in mpp strcuture.

11.89.1 Member Function/Subroutine Documentation

11.89.1.1 subroutine mpp::mpp_del_var::mpp__del_var_mpp (type(tmpp), intent(inout) td_mpp)

This subroutine delete all variable in mpp strcuture.

Author

J.Paul

Date

October, 2014 - Initial version

Parameters

in, out	td_mpp	mpp strcuture
---------	--------	---------------

11.89.1.2 subroutine mpp::mpp_del_var::mpp__del_var_name (type(tmpp), intent(inout) td_mpp, character(len=*), intent(in) cd_name)

This subroutine delete variable in mpp structure, given variable name.

Author

J.Paul

Date

November, 2013 - Initial version

February, 2015

- define local variable structure to avoid mistake with pointer

Parameters

in, out	td_mpp	mpp strcuture
in	cd_name	variable name

11.89.1.3 subroutine mpp::mpp_del_var::mpp__del_var_str (type(tmpp), intent(inout) td_mpp, type(tvar), intent(in) td_var)

This subroutine delete variable in mpp structure, given variable structure.

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in, out	<i>td_mpp</i>	mpp strcuture
in	<i>td_var</i>	variable strcuture

The documentation for this interface was generated from the following file:

- src/mpp.f90

11.90 mpp::mpp_get_use Interface Reference

Public Member Functions

- subroutine [mpp__get_use_unit](#) (td_mpp, id_imin, id_imax, id_jmin, id_jmax)
This subroutine get sub domains which cover "zoom domain".

11.90.1 Member Function/Subroutine Documentation

11.90.1.1 subroutine `mpp::mpp_get_use::mpp__get_use_unit` (type(tmpp), intent(inout) *td_mpp*, integer(i4), intent(in), optional *id_imin*, integer(i4), intent(in), optional *id_imax*, integer(i4), intent(in), optional *id_jmin*, integer(i4), intent(in), optional *id_jmax*)

This subroutine get sub domains which cover "zoom domain".

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in, out	<i>td_mpp</i>	mpp strcuture
in	<i>id_imin</i>	i-direction lower indice
in	<i>id_imax</i>	i-direction upper indice
in	<i>id_jmin</i>	j-direction lower indice
in	<i>id_jmax</i>	j-direction upper indice

The documentation for this interface was generated from the following file:

- src/mpp.f90

11.91 mpp::mpp_init Interface Reference

Public Member Functions

- type(tmpp) function [mpp__init_mask](#) (cd_file, id_mask, id_niproc, id_njproc, id_nproc, id_prci, id_prcj, cd-_type, id_ew, id_perio, id_pivot, td_dim)

This function initialise mpp structure, given file name, and optionally mask and number of processor following I and J .

- TYPE(TMPP) function `mpp__init_var` (cd_file, td_var, id_niproc, id_njproc, id_nproc, id_preci, id_precj, cd_type, id_perio, id_pivot)

This function initialise mpp structure, given variable structure and optionally number of processor following I and J .

- TYPE(TMPP) function `mpp__init_file` (td_file, id_ew, id_perio, id_pivot)

This function initialise a mpp structure given file structure.

11.91.1 Member Function/Subroutine Documentation

11.91.1.1 TYPE(TMPP) function `mpp::mpp_init::mpp__init_file` (type(tfiler), intent(in) *td_file*, integer(i4), intent(in), optional *id_ew*, integer(i4), intent(in), optional *id_perio*, integer(i4), intent(in), optional *id_pivot*)

This function initialise a mpp structure given file structure.

It reads restart dimg files, or some netcdf files.

Warning

netcdf file must contains some attributes:

- DOMAIN_number_total
- DOMAIN_size_global
- DOMAIN_number
- DOMAIN_position_first
- DOMAIN_position_last
- DOMAIN_halo_size_start
- DOMAIN_halo_size_end or the file is assume to be no mpp file.

Author

J.Paul

Date

November, 2013 - Initial Version

January, 2016

- mismatch with "halo" indices, use `mpp__compute_halo`

Parameters

in	<i>td_file</i>	file structure
in	<i>id_ew</i>	east-west overlap
in	<i>id_perio</i>	NEMO periodicity index
in	<i>id_pivot</i>	NEMO pivot point index F(0),T(1)

Returns

mpp structure

11.91.1.2 `type(tmpp)` function `mpp::mpp_init::mpp__init_mask` (`character(len=*)`, `intent(in) cd_file`, `integer(i4)`, `dimension(:, :)`, `intent(in) id_mask`, `integer(i4)`, `intent(in)`, `optional id_niproc`, `integer(i4)`, `intent(in)`, `optional id_njproc`, `integer(i4)`, `intent(in)`, `optional id_nproc`, `integer(i4)`, `intent(in)`, `optional id_preci`, `integer(i4)`, `intent(in)`, `optional id_precj`, `character(len=*)`, `intent(in)`, `optional cd_type`, `integer(i4)`, `intent(in)`, `optional id_ew`, `integer(i4)`, `intent(in)`, `optional id_perio`, `integer(i4)`, `intent(in)`, `optional id_pivot`, `type(tdim)`, `dimension(ip_maxdim)`, `intent(in)`, `optional td_dim`)

This function initialise mpp structure, given file name, and optionally mask and number of processor following I and J .

- If no total number of processor is defined (`id_nproc`), optimize the domain decomposition (look for the domain decomposition with the most land processor to remove)
- length of the overlap region (`id_preci`, `id_precj`) could be specify in I and J direction (default value is 1)

Author

J.Paul

Date

November, 2013 - Initial version
September, 2015

- allow to define dimension with array of dimension structure

Date

January, 2016

- use RESULT to rename output
- mismatch with "halo" indices

Parameters

<code>in</code>	<code>cd_file</code>	file name of one file composing mpp domain
<code>in</code>	<code>id_mask</code>	domain mask
<code>in</code>	<code>id_niproc</code>	number of processors following i
<code>in</code>	<code>id_njproc</code>	number of processors following j
<code>in</code>	<code>id_nproc</code>	total number of processors
<code>in</code>	<code>id_preci</code>	i-direction overlap region
<code>in</code>	<code>id_precj</code>	j-direction overlap region
<code>in</code>	<code>cd_type</code>	type of the files (cdf, cdf4, dimg)
<code>in</code>	<code>id_ew</code>	east-west overlap
<code>in</code>	<code>id_perio</code>	NEMO periodicity index
<code>in</code>	<code>id_pivot</code>	NEMO pivot point index F(0),T(1)
<code>in</code>	<code>td_dim</code>	array of dimension structure

Returns

mpp structure

11.91.1.3 `TYPE(TMPP)` function `mpp::mpp_init::mpp__init_var` (`character(len=*)`, `intent(in) cd_file`, `type(tvar)`, `intent(in) td_var`, `integer(i4)`, `intent(in)`, `optional id_niproc`, `integer(i4)`, `intent(in)`, `optional id_njproc`, `integer(i4)`, `intent(in)`, `optional id_nproc`, `integer(i4)`, `intent(in)`, `optional id_preci`, `integer(i4)`, `intent(in)`, `optional id_precj`, `character(len=*)`, `intent(in)`, `optional cd_type`, `integer(i4)`, `intent(in)`, `optional id_perio`, `integer(i4)`, `intent(in)`, `optional id_pivot`)

This function initialise mpp structure, given variable structure and optionally number of processor following I and J .

- If no total number of processor is defined (`id_nproc`), optimize the domain decomposition (look for the domain decomposition with the most land processor to remove)
- length of the overlap region (`id_preci`, `id_precj`) could be specify in I and J direction (default value is 1)

Author

J.Paul

Date

November, 2013 - Initial version

Parameters

in	<i>cd_file</i>	file name of one file composing mpp domain
in	<i>td_var</i>	variable structure
in	<i>id_niproc</i>	number of processors following i
in	<i>id_njproc</i>	number of processors following j
in	<i>id_nproc</i>	total number of processors
in	<i>id_preci</i>	i-direction overlap region
in	<i>id_precj</i>	j-direction overlap region
in	<i>cd_type</i>	type of the files (cdf, cdf4, dimg)
in	<i>id_perio</i>	NEMO periodicity index
in	<i>id_pivot</i>	NEMO pivot point index F(0),T(1)

Returns

mpp structure

The documentation for this interface was generated from the following file:

- src/mpp.f90

11.92 multi Module Reference

This module manage multi file structure.

Data Types

- interface [multi_copy](#)
- type [tmulti](#)

Public Member Functions

- type([tmulti](#)) function, public [multi_init](#) (cd_varfile)
This subroutine initialize multi file structure.
- subroutine, public [multi_clean](#) (td_multi)
This subroutine clean multi file strucutre.
- subroutine, public [multi_print](#) (td_multi)
This subroutine print some information about mpp strucutre.
- subroutine, public [multi__add_mpp](#) (td_multi, td_mpp)
This subroutine add file to multi file structure.

11.92.1 Detailed Description

This module manage multi file structure.

```
define type TMULTI:<br/>
```

```
TYPE(tmulti) :: tl_multi
```

to initialize a multi-file structure:

```
tl_multi=multi_init(cd_varfile(:))
```

- `cd_varfile` : array of variable with file path ('var1:file1','var2:file2')
file path could be replaced by a matrix of value.
separators used to defined matrix are:

- ',' for line
- '/' for row
- '\' for level

Example:

```
* 'var1:3,2,3/1,4,5'
* 3,2,3/1,4,5 =>  $\begin{pmatrix} 3 & 2 & 3 \\ 1 & 4 & 5 \end{pmatrix}$ 
```

to get the number of mpp file in mutli file structure:

- `tl_multi%i_nmpp`

to get the total number of variable in mutli file structure:

- `tl_multi%i_nvar`

Note

number of variable and number of file could differ cause several variable could be in the same file.

to get array of mpp structure in mutli file structure:

- `tl_multi%t_mpp(:)`

to print information about multi structure:

```
CALL multi_print(td_multi)
```

to clean multi file strucutre:

```
CALL multi_clean(td_multi)
```

- `td_multi` is multi file structure

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- use mpp file structure instead of file

November, 2014

- Fix memory leaks bug

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.92.2 Member Function/Subroutine Documentation

11.92.2.1 subroutine, public multi::multi__add_mpp (type(tmulti), intent(inout) *td_multi*, type(tmpp), intent(in) *td_mpp*)

This subroutine add file to multi file structure.

Author

J.Paul

Date

November, 2013 - Initial Version

October, 2014

- use mpp file structure instead of file

Parameters

<i>in, out</i>	<i>td_multi</i>	multi mpp file strcuture
<i>in</i>	<i>td_mpp</i>	mpp file strcuture

Returns

mpp file id in multi mpp file structure

11.92.2.2 subroutine, public multi::multi_clean (type(tmulti), intent(inout) *td_multi*)

This subroutine clean multi file strcutre.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_multi</i>	multi file structure
-----------	-----------------	----------------------

11.92.2.3 type(tmulti) function, public multi::multi_init (character(len=*), dimension(:), intent(in) *cd_varfile*)

This subroutine initialize multi file structure.

if variable name is 'all', add all the variable of the file in mutli file structure.

Note

if first character of filename is numeric, assume matrix is given as input.
create pseudo file named 'data-*.', with matrix read as variable value.

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- check if variable to be read is in file

January, 2016

- read variable dimensions

Parameters

<code>in</code>	<code>cd_varfile</code>	variable location information (from namelist)
-----------------	-------------------------	---

Returns

multi file structure

11.92.2.4 subroutine, public multi::multi_print (type(tmulti), intent(in) td_multi)

This subroutine print some information about mpp strucutre.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_multi</code>	multi file structure
-----------------	-----------------------	----------------------

The documentation for this module was generated from the following file:

- src/multi.f90

11.93 multi::multi_copy Interface Reference

Public Member Functions

- `type(tmulti)` function `multi__copy_unit` (`td_multi`)
This function copy multi mpp structure in another one.

11.93.1 Member Function/Subroutine Documentation**11.93.1.1 type(tmulti) function multi::multi_copy::multi__copy_unit (type(tmulti), intent(in) td_multi)**

This function copy multi mpp structure in another one.

file variable value are copied in a temporary array, so input and output file structure value do not point on the same "memory cell", and so on are independant.

Warning

do not use on the output of a function who create or read an attribute (ex: `tl_att=att_copy(att_init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_multi</code>	mpp structure
-----------------	-----------------------	---------------

Returns

copy of input multi structure

The documentation for this interface was generated from the following file:

- `src/multi.f90`

11.94 `date::operator(+)` Interface Reference

Public Member Functions

- TYPE(TDATE) function [date__addnday](#) (`td_date`, `dd_nday`)
This function add nday to a date: $date2 = date1 + nday$.

11.94.1 Member Function/Subroutine Documentation

11.94.1.1 TYPE(TDATE) function `date::operator(+):date__addnday (type(tdate), intent(in) td_date, real(dp), intent(in) dd_nday)`

This function add nday to a date: $date2 = date1 + nday$.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_date</i>	date strutcutre
in	<i>dd_nday</i>	number of day

Returns

date strutcutre of date + nday

The documentation for this interface was generated from the following file:

- src/date.f90

11.95 date::operator(-) Interface Reference

Public Member Functions

- TYPE(TDATE) function [date__subnday](#) (td_date, dd_nday)
This function substract nday to a date: date2 = date1 - nday.
- REAL(dp) function [date__diffdate](#) (td_date1, td_date2)
This function compute number of day between two dates: nday= date1 - date2.

11.95.1 Member Function/Subroutine Documentation

11.95.1.1 REAL(dp) function `date::operator(-)::date__diffdate (type(tdate), intent(in) td_date1, type(tdate), intent(in) td_date2)`

This function compute number of day between two dates: nday= date1 - date2.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_date1</i>	first date strutcutre
in	<i>td_date2</i>	second date strutcutre

Returns

nday

11.95.1.2 TYPE(TDATE) function `date::operator(-)::date__subnday (type(tdate), intent(in) td_date, real(dp), intent(in) dd_nday)`

This function substract nday to a date: date2 = date1 - nday.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_date</i>	date strutcutre
in	<i>dd_nday</i>	number of day

Returns

date strutcutre of date - nday

The documentation for this interface was generated from the following file:

- src/date.f90

11.96 fct::operator(/) Interface Reference**Public Member Functions**

- PURE CHARACTER(LEN=lc) function [fct__i1_cat](#) (cd_char, bd_val)
This function concatenate character and integer(1) (as character).
- PURE CHARACTER(LEN=lc) function [fct__i2_cat](#) (cd_char, sd_val)
This function concatenate character and integer(2) (as character).
- PURE CHARACTER(LEN=lc) function [fct__i4_cat](#) (cd_char, id_val)
This function concatenate character and integer(4) (as character).
- PURE CHARACTER(LEN=lc) function [fct__i8_cat](#) (cd_char, kd_val)
This function concatenate character and integer(8) (as character).
- PURE CHARACTER(LEN=lc) function [fct__r4_cat](#) (cd_char, rd_val)
This function concatenate character and real(4) (as character).
- PURE CHARACTER(LEN=lc) function [fct__r8_cat](#) (cd_char, dd_val)
This function concatenate character and real(8) (as character).
- PURE CHARACTER(LEN=lc) function [fct__l_cat](#) (cd_char, ld_val)
This function concatenate character and logical (as character).

11.96.1 Member Function/Subroutine Documentation

11.96.1.1 PURE CHARACTER(LEN=lc) function [fct::operator\(/\)::fct__i1_cat](#) (character(len=lc), intent(in) *cd_char*, integer(i1), intent(in) *bd_val*)

This function concatenate character and integer(1) (as character).

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>bd_val</i>	integer(1) variable value

Returns

string character

11.96.1.2 PURE CHARACTER(LEN=lc) function fct::operator(//)::fct_i2_cat (character(len=lc), intent(in) *cd_char*, integer(i2), intent(in) *sd_val*)

This function concatenate character and integer(2) (as character).

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>sd_val</i>	integer(2) variable value

Returns

string character

11.96.1.3 PURE CHARACTER(LEN=lc) function fct::operator(//)::fct_i4_cat (character(len=lc), intent(in) *cd_char*, integer(i4), intent(in) *id_val*)

This function concatenate character and integer(4) (as character).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>id_val</i>	integer(4) variable value

Returns

string character

11.96.1.4 PURE CHARACTER(LEN=lc) function fct::operator(/)::fct__i8_cat (character(len=lc), intent(in) *cd_char*, integer(i8), intent(in) *kd_val*)

This function concatenate character and integer(8) (as character).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>kd_val</i>	integer(8) variable value

Returns

string character

11.96.1.5 PURE CHARACTER(LEN=lc) function fct::operator(/)::fct__l_cat (character(len=lc), intent(in) *cd_char*, logical, intent(in) *ld_val*)

This function concatenate character and logical (as character).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>ld_val</i>	logical variable value

Returns

string character

11.96.1.6 PURE CHARACTER(LEN=lc) function fct::operator(/)::fct__r4_cat (character(len=lc), intent(in) *cd_char*, real(sp), intent(in) *rd_val*)

This function concatenate character and real(4) (as character).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>rd_val</i>	real(4) variable value

Returns

string character

11.96.1.7 PURE CHARACTER(LEN=lc) function fct::operator(/)::fct_r8_cat (character(len=lc), intent(in) *cd_char*, real(dp), intent(in) *dd_val*)

This function concatenate character and real(8) (as character).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>cd_char</i>	string character
in	<i>dd_val</i>	real(8) variable value

Returns

string character

The documentation for this interface was generated from the following file:

- src/function.f90

11.97 phycst Module Reference

This module defines physical constant.

Public Attributes

- real(dp), public **rday** = 24.*60.*60.
- real(dp), public **rsiyea**
- real(dp), public **rsiday**
- real(dp), parameter, public **dp_pi** = 3.14159274101257_dp
- real(dp), parameter, public **dp_eps** = 0.5 * EPSILON(1._dp)
- real(dp), parameter, public **dp_rearth** = 6371229._dp
- real(dp), parameter, public **dp_deg2rad** = dp_pi/180.0
- real(dp), parameter, public **dp_rad2deg** = 180.0/dp_pi
- real(dp), parameter, public **dp_day** = 24.*60.*60.
- real(dp), parameter, public **dp_siyea** = 365.25_dp * dp_day * 2._dp * dp_pi / 6.283076_dp
- real(dp), parameter, public **dp_siday** = dp_day / (1._dp + dp_day / dp_siyea)
- real(dp), parameter, public **dp_delta** = 1.e-5
- real(dp), parameter, public **dp_omega** = 2._dp * dp_pi / dp_siday

11.97.1 Detailed Description

This module defines physical constant.

Author

J.paul

Date

November, 2013 - Initial Version

September, 2015

- add physical constant to compute meshmask

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

The documentation for this module was generated from the following file:

- src/phycst.f90

11.98 boundary::seg_clean Interface Reference

Public Member Functions

- subroutine [seg_clean_unit](#) (td_seg)
This subroutine clean segment structure.
- subroutine [seg_clean_arr](#) (td_seg)
This subroutine clean segment structure.

11.98.1 Member Function/Subroutine Documentation

11.98.1.1 subroutine boundary::seg_clean::seg_clean_arr (type(tseg), dimension(:), intent(inout) td_seg)

This subroutine clean segment structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	td_seg	array of segment structure
---------	--------	----------------------------

11.98.1.2 subroutine boundary::seg__clean::seg__clean_unit (type(tseg), intent(inout) td_seg)

This subroutine clean segment structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	td_seg	segment structure
---------	--------	-------------------

The documentation for this interface was generated from the following file:

- src/boundary.f90

11.99 boundary::seg__copy Interface Reference

Public Member Functions

- type(tseg) function [seg__copy_unit](#) (td_seg)
This subroutine copy segment structure in another one.
- type(tseg) function, dimension(size(td_seg(:))) [seg__copy_arr](#) (td_seg)
This subroutine copy segment structure in another one.

11.99.1 Member Function/Subroutine Documentation

11.99.1.1 type(tseg) function, dimension(size(td_seg(:))) boundary::seg__copy::seg__copy_arr (type(tseg), dimension(:), intent(in) td_seg)

This subroutine copy segment structure in another one.

Warning

do not use on the output of a function who create or read a structure (ex: tl_seg=seg__copy(seg__init()) is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_seg</code>	segment structure
-----------------	---------------------	-------------------

Returns

copy of input array of segment structure

11.99.1.2 `type(tseg) function boundary::seg__copy::seg__copy_unit (type(tseg), intent(in) td_seg)`

This subroutine copy segment structure in another one.

Warning

do not use on the output of a function who create or read a structure (ex: `tl_seg=seg__copy(seg__init())` is forbidden). This will create memory leaks.
to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_seg</code>	segment structure
-----------------	---------------------	-------------------

Returns

copy of input segment structure

The documentation for this interface was generated from the following file:

- `src/boundary.f90`

11.100 `att::tatt` Type Reference

Public Attributes

- character(len=lc) `c_name` = "
attribute name
- integer(i4) `i_id` = 0
attribute id
- integer(i4) `i_type` = 0
attribute type
- integer(i4) `i_len` = 0
number of value store in attribute
- character(len=lc) `c_value` = 'none'

- *attribute value if type CHAR*
real(dp), dimension(:), pointer `d_value` => NULL()
attribute value if type SHORT,INT,FLOAT or DOUBLE

The documentation for this type was generated from the following file:

- src/attribute.f90

11.101 boundary::tbody Type Reference

boundary structure

Public Attributes

- character(len=lc) `c_card` = "
boundary cardinal
- logical `l_use` = .FALSE.
boundary use or not
- logical `l_nam` = .FALSE.
boundary get from namelist
- integer(i4) `i_nseg` = 0
number of segment in boundary
- type(`tseg`), dimension(:), pointer `t_seg` => NULL()
array of segment structure

11.101.1 Detailed Description

boundary structure

The documentation for this type was generated from the following file:

- src/boundary.f90

11.102 date::tdate Type Reference

Public Attributes

- integer(i4) `i_year` = 1858
year
- integer(i4) `i_month` = 11
month
- integer(i4) `i_day` = 17
day
- integer(i4) `i_hour` = 0
hour
- integer(i4) `i_min` = 0
min
- integer(i4) `i_sec` = 0
sec

- integer(i4) `i_dow` = 0
day of week
- integer(i4) `i_lday` = 0
last day of the month
- real(dp) `d_jd` = 0
julian day (origin : 1858/11/17 00:00:00)
- real(dp) `d_jc` = 0
CNES julian day or pseudo julian day with new date origin.
- integer(i8) `k_jdsec` = 0
number of seconds since julian day origin
- integer(i8) `k_jcsec` = 0
number of seconds since CNES or pseudo julian day origin

The documentation for this type was generated from the following file:

- src/date.f90

11.103 `dim::tdim` Type Reference

Public Attributes

- character(len=lc) `c_name` = ""
dimension name
- character(len=lc) `c_sname` = 'u'
dimension short name
- integer(i4) `i_id` = 0
dimension id
- integer(i4) `i_len` = 1
dimension length
- logical `l_uld` = .FALSE.
dimension unlimited or not
- logical `l_use` = .FALSE.
dimension used or not
- integer(i4) `i_2xyzt` = 0
indices to reshape array to ('x','y','z','t')
- integer(i4) `i_xyzt2` = 0
indices to reshape array from ('x','y','z','t')

The documentation for this type was generated from the following file:

- src/dimension.f90

11.104 `dom::tdom` Type Reference

Public Attributes

- type(tdim), dimension(ip_maxdim) `t_dim0`
global domain dimension
- type(tdim), dimension(ip_maxdim) `t_dim`

- sub domain dimension*
- integer(i4) `i_perio0`
NEMO periodicity index of global domain.
- integer(i4) `i_ew0`
East-West overlap of global domain.
- integer(i4) `i_perio`
NEMO periodicity index of sub domain.
- integer(i4) `i_pivot`
NEMO pivot point index F(0),T(1)
- integer(i4) `i_imin = 0`
i-direction sub-domain lower left point indice
- integer(i4) `i_imax = 0`
i-direction sub-domain upper right point indice
- integer(i4) `i_jmin = 0`
j-direction sub-domain lower left point indice
- integer(i4) `i_jmax = 0`
j-direction sub-domain upper right point indice
- integer(i4) `i_bdy = 0`
boundary index : 0 = no boundary 1 = north 2 = south 3 = east 4 = west
- integer(i4), dimension(2, 2) `i_ghost0 = 0`
array of ghost cell factor of global domain
- integer(i4), dimension(2, 2) `i_ghost = 0`
array of ghost cell factor of sub domain
- integer(i4), dimension(2) `i_iextra = 0`
i-direction extra point
- integer(i4), dimension(2) `i_jextra = 0`
j-direction extra point

The documentation for this type was generated from the following file:

- src/domain.f90

11.105 file::tfile Type Reference

Public Attributes

- character(len=lc) `c_name = ""`
file name
- character(len=lc) `c_type = ""`
type of the file (cdf, cdf4, dimg)
- integer(i4) `i_id = 0`
file id
- logical `l_wrt = .FALSE.`
read or write mode
- integer(i4) `i_nvar = 0`
number of variable
- type(tvar), dimension(:), pointer `t_var => NULL()`
file variables
- character(len=lc) `c_grid = 'ARAKAWA-C'`
grid type

- integer(i4) `i_ew` = -1
east-west overlap
- integer(i4) `i_perio` = -1
NEMO periodicity index.
- integer(i4) `i_pivot` = -1
NEMO pivot point index $F(0), T(1)$
- integer(i4) `i_depthid` = 0
variable id of depth
- integer(i4) `i_timeid` = 0
variable id of time
- integer(i4) `i_ndim` = 0
number of dimensions used in the file
- integer(i4) `i_natt` = 0
number of global attributes in the file
- integer(i4) `i_uldid` = 0
id of the unlimited dimension in the file
- logical `l_def` = .FALSE.
define mode or not
- type(tatt), dimension(:), pointer `t_att` => NULL()
global attributes
- type(tdim), dimension(ip_maxdim) `t_dim`
dimension structure
- integer(i4) `i_recl` = 0
record length (binary file)
- integer(i4) `i_n0d` = 0
number of scalar variable
- integer(i4) `i_n1d` = 0
number of 1D variable
- integer(i4) `i_n2d` = 0
number of 2D variable
- integer(i4) `i_n3d` = 0
number of 3D variable
- integer(i4) `i_rhd` = 0
record of the header infos (last record)
- integer(i4) `i_pid` = -1
processor id (start to 1)
- integer(i4) `i_impp` = 0
i-indices for mpp-subdomain left bottom
- integer(i4) `i_jmpp` = 0
j-indices for mpp-subdomain left bottom
- integer(i4) `i_lci` = 0
i-dimensions of subdomain
- integer(i4) `i_lcj` = 0
j-dimensions of subdomain
- integer(i4) `i_ldi` = 0
first indoor i-indices
- integer(i4) `i_ldj` = 0
first indoor j-indices
- integer(i4) `i_lei` = 0
last indoor i-indices
- integer(i4) `i_lej` = 0

- last indoor j-indices*
- logical `L_ctr` = `.FALSE.`
- domain is on border*
- logical `L_use` = `.FALSE.`
- domain is used*
- integer(i4) `i_iind` = 0
- i-direction indices*
- integer(i4) `i_jind` = 0
- j-direction indices*

The documentation for this type was generated from the following file:

- `src/file.f90`

11.106 interp::tinterp Type Reference

Public Attributes

- character(len=lc) `c_name` = "
interpolation method name
- character(len=lc) `c_factor` = "
interpolation factor
- character(len=lc) `c_divisor` = "
interpolation divisor

The documentation for this type was generated from the following file:

- `src/interp.f90`

11.107 mpp::tlay Type Reference

domain layout structure

Public Attributes

- integer(i4) `i_niproc` = 0
number of processors following i
- integer(i4) `i_njproc` = 0
number of processors following j
- integer(i4) `i_nland` = 0
number of land processors
- integer(i4) `i_nsea` = 0
number of sea processors
- integer(i4) `i_mean` = 0
mean sea point per proc
- integer(i4) `i_min` = 0
min sea point per proc
- integer(i4) `i_max` = 0
max sea point per proc

- integer(i4), dimension(:,:),
pointer `i_msk` => NULL()
sea/land processor mask
- integer(i4), dimension(:,:),
pointer `i_impp` => NULL()
i-indices for mpp-subdomain left bottom
- integer(i4), dimension(:,:),
pointer `i_jmpp` => NULL()
j-indices for mpp-subdomain left bottom
- integer(i4), dimension(:,:),
pointer `i_lci` => NULL()
i-dimensions of subdomain
- integer(i4), dimension(:,:),
pointer `i_lcj` => NULL()
j-dimensions of subdomain

11.107.1 Detailed Description

domain layout structure

The documentation for this type was generated from the following file:

- src/mpp.f90

11.108 logger::tlogger Type Reference

Public Attributes

- integer(i4) `i_id` = 0
log file id
- logical `l_use` = .TRUE.
use logger or not
- character(len=lc) `c_name`
log file name
- character(len=lc) `c_verbosity` = "warning"
verbosity choose
- character(len=lc) `c_verb` = ""
array of "verbosities" to used
- integer(i4) `i_nerror` = 0
number of error
- integer(i4) `i_nfatal` = 0
number of fatal error
- integer(i4) `i_maxerror` = 5
maximum number of error before stoping program

The documentation for this type was generated from the following file:

- src/logger.f90

11.109 mpp::tmpp Type Reference

Public Attributes

- character(len=lc) **c_name** = "
base name
- integer(i4) **i_id** = 0
mpp id
- integer(i4) **i_niproc** = 0
number of processors following i
- integer(i4) **i_njproc** = 0
number of processors following j
- integer(i4) **i_nproc** = 0
total number of processors used
- integer(i4) **i_preci** = 1
i-direction overlap region length
- integer(i4) **i_precj** = 1
j-direction overlap region length
- integer(i4) **i_ew** = -1
east-west overlap
- integer(i4) **i_perio** = -1
NEMO periodicity index.
- integer(i4) **i_pivot** = -1
NEMO pivot point index F(0),T(1)
- character(len=lc) **c_type** = "
type of the files (cdf, cdf4, dimg)
- character(len=lc) **c_dom** = "
type of domain (full, noextra, nooverlap)
- integer(i4) **i_ndim** = 0
number of dimensions used in mpp
- type(tdim), dimension(ip_maxdim) **t_dim**
global domain dimension
- type(tfile), dimension(:), pointer **t_proc** => NULL()
files/processors composing mpp

The documentation for this type was generated from the following file:

- src/mpp.f90

11.110 multi::tmulti Type Reference

Public Attributes

- integer(i4) **i_nmpp** = 0
number of mpp files
- integer(i4) **i_nvar** = 0
total number of variables
- type(tmpp), dimension(:), pointer **t_mpp** => NULL()
mpp files composing multi

The documentation for this type was generated from the following file:

- src/multi.f90

11.111 grid_hgr::tnamh Type Reference

Public Attributes

- character(len=lc) **c_coord**
- integer(i4) **i_perio**
- integer(i4) **i_mshhgr**
- real(dp) **d_ppglam0**
- real(dp) **d_ppgphi0**
- real(dp) **d_ppe1_deg**
- real(dp) **d_ppe2_deg**
- integer(i4) **i_cfg**
- logical **l_bench**

The documentation for this type was generated from the following file:

- src/grid_hgr.f90

11.112 grid_zgr::tnamz Type Reference

Public Attributes

- character(len=lc) **c_coord**
- integer(i4) **i_perio**
- logical **l_zco**
- logical **l_zps**
- logical **l_sco**
- logical **l_isfcav**
- logical **l_iscpl**
- logical **l_wd**
- integer(i4) **i_nlevel**
- real(dp) **d_ppsur**
- real(dp) **d_ppa0**
- real(dp) **d_ppa1**
- real(dp) **d_ppkth**
- real(dp) **d_ppacr**
- real(dp) **d_ppdzmin**
- real(dp) **d_pphmax**
- logical **l_dbletanh**
- real(dp) **d_ppa2**
- real(dp) **d_ppkth2**
- real(dp) **d_ppacr2**
- real(dp) **d_hmin**
- real(dp) **d_isfhmin**
- real(dp) **d_e3zps_min**
- real(dp) **d_e3zps_rat**
- logical **l_s_sh94**
- logical **l_s_sf12**
- real(dp) **d_sbot_min**
- real(dp) **d_sbot_max**
- real(dp) **d_rmax**
- real(dp) **d_hc**
- real(dp) **d_theta**

- real(dp) **d_thetb**
- real(dp) **d_bb**
- logical **l_sigcrit**
- real(dp) **d_alpha**
- real(dp) **d_efold**
- real(dp) **d_zs**
- real(dp) **d_zb_a**
- real(dp) **d_zb_b**
- integer(i4) **i_cla**
- real(dp) **d_wdmin1**
- real(dp) **d_wdmin2**
- real(dp) **d_wdld**
- logical **l_c1d**
- logical **l_e3_dep**

The documentation for this type was generated from the following file:

- src/grid_zgr.f90

11.113 boundary::tseg Type Reference

Public Attributes

- integer(i4) **i_index** = 0
segment index
- integer(i4) **i_width** = 0
segment width
- integer(i4) **i_first** = 0
segment first indice
- integer(i4) **i_last** = 0
segment last indices

The documentation for this type was generated from the following file:

- src/boundary.f90

11.114 var::tvar Type Reference

Public Attributes

- character(len=lc) **c_name** = ""
variable name
- character(len=lc) **c_point** = 'T'
ARAKAWA C-grid point name (T,U,V,F)
- integer(i4) **i_id** = 0
variable id
- integer(i4) **i_ew** = -1
east-west overlap
- real(dp), dimension(:,:,:),
pointer **d_value** => NULL()
variable value

- integer(i4) `i_type` = 0
variable type
- integer(i4) `i_natt` = 0
number of attributes
- integer(i4) `i_ndim` = 0
number of dimensions
- type(tatt), dimension(:), pointer `t_att` => NULL()
variable attributes
- type(tdim), dimension(ip_maxdim) `t_dim`
variable dimension
- logical `l_file` = .FALSE.
variable read in a file
- logical `l_use` = .TRUE.
variable to be used
- character(len=lc) `c_stdname` = "
variable standard name
- character(len=lc) `c_longname` = "
variable long name
- character(len=lc) `c_units` = "
variable units
- character(len=lc) `c_axis` = "
variable axis
- real(dp) `d_scf` = 1.
scale factor
- real(dp) `d_ofs` = 0.
offset
- real(dp) `d_fill` = 0.
fill value ! NF90_FILL_DOUBLE
- real(dp) `d_min` = dp_fill
minimum value
- real(dp) `d_max` = dp_fill
maximum value
- character(len=lc) `c_unt` = "
new variables units (linked to units factor)
- real(dp) `d_unf` = 1._dp
units factor
- logical `l_contiguous` = .FALSE.
use contiguous storage or not
- logical `l_shuffle` = .FALSE.
shuffle filter is turned on or not
- logical `l_fletcher32` = .FALSE.
fletcher32 filter is turned on or not
- integer(i4) `i_deflvl` = 0
deflate level from 0 to 9, 0 indicates no deflation is in use
- integer(i4), dimension(ip_maxdim) `i_chunksz` = (/1,1,1,1/)
chunk size
- integer(i4) `i_rec` = 0
record number
- character(len=lc), dimension(2) `c_interp` = "
interpolation method
- character(len=lc), dimension(1) `c_extrap` = "

- *extrapolation method*
- character(len=lc), dimension(5) `c_filter` = "
filter method

The documentation for this type was generated from the following file:

- src/variable.f90

11.115 var Module Reference

This module manage variable structure.

Data Types

- type `tvar`
- interface `var_add_att`
- interface `var_add_dim`
- interface `var_add_value`
- interface `var_clean`
- interface `var_copy`
- interface `var_del_att`
- interface `var_init`
- interface `var_print`

Public Member Functions

- type(`tvar`) function, public `var_concat` (`td_var1`, `td_var2`, `DIM`)
This function concatenate variable value following DIM direction.
- subroutine, public `var_move_att` (`td_var`, `td_att`)
This subroutine move an attribute structure from variable structure.
- subroutine, public `var_del_dim` (`td_var`, `td_dim`)
This subroutine delete a dimension structure in a variable structure.
- subroutine, public `var_move_dim` (`td_var`, `td_dim`)
This subroutine move a dimension structure in variable structure.
- subroutine, public `var_del_value` (`td_var`)
This subroutine remove variable value in a variable structure.
- INTEGER(i4) function, public `var_get_index` (`td_var`, `cd_name`, `cd_stdname`)
This function return the variable index, in a array of variable structure, given variable name or standard name.
- INTEGER(i4) function, public `var_get_id` (`td_var`, `cd_name`, `cd_stdname`)
This function return the variable id, given variable name or standard name.
- integer(i4) function,
dimension(`td_var%``td_dim`(1)%`i_len`,`td_var%``td_dim`(2)%`i_len`,`td_var%``td_dim`(3)%`i_len`),
public `var_get_mask` (`td_var`)
This function return the mask 3D of variable, given variable structure.
- subroutine, public `var_chg_fillvalue` (`td_var`, `dd_fill`)
This subroutine change FillValue of the variable to standard NETCDF FillValue.
- subroutine, public `var_def_extra` (`cd_file`)
*This subroutine read variable configuration file. And save global array of variable structure with extra information:
`tg_varextra`.*
- subroutine, public `var_chg_extra` (`cd_varinfo`)

This subroutine add variable information get from namelist in global array of variable structure with extra information: tg_varextra.

- subroutine, public [var_clean_extra](#) ()

This subroutine clean global array of variable structure with extra information: tg_varextra.

- subroutine, public [var_read_matrix](#) (td_var, cd_matrix)

This subroutine read matrix value from character string in namelist and fill variable structure value.

- type(tdim) function, dimension(ip_maxdim),
public [var_max_dim](#) (td_var)

This function search and save the biggest dimensions use in an array of variable structure.

- subroutine, public [var_limit_value](#) (td_var)

This subroutine forced minimum and maximum value of variable, with value of variable structure attribute d_min and d_max.

- subroutine, public [var_chg_unit](#) (td_var)

This subroutine replace unit name of the variable, and apply unit factor to the value of this variable.

- subroutine, public [var_check_dim](#) (td_var)

This subroutine check variable dimension expected, as defined in file 'variable.cfg'.

- subroutine, public [var_reorder](#) (td_var, cd_dimorder)

This subroutine reshape variable value and dimension in variable structure.

- integer(i4) function, public [var_get_unit](#) (td_var)

This function get the next unused unit in array of variable structure.

- type(tdate) function, public [var_to_date](#) (td_var)

This function convert a time variable structure in date structure.

- subroutine, public [var_get_dummy](#) (cd_dummy)

This subroutine fill dummy variable array.

- logical function, public [var_is_dummy](#) (td_var)

This function check if variable is defined as dummy variable in configuraton file.

Public Attributes

- type([tvar](#)), dimension(:),
allocatable, public [tg_varextra](#)

array of variable structure with extra information. fill when running [var_def_extra](#)()

11.115.1 Detailed Description

This module manage variable structure.

```
define type TVAR:<br/>
```

```
TYPE(tvar) :: tl_var
```

Note

the variable value inside structure will always be 4D array of real(8).

However the variable value could be initialised with array of real(4), real(8), integer(4) or integer(8).

to initialise a variable structure:

```
tl_var=var_init( cd_name, [value,] [id_start, [id_count,]] [id_type,] [td_dim,] [td_att]... )
```

- cd_name is the variable name
- value is a 1D,2D,3D or 4D array, see [var_init](#) for more information [optional]

- `id_start` is a integer(4) 1D array of index from which the data values will be read [optional]
- `id_count` is a integer(4) 1D array of the number of indices selected along each dimension [optional]
- `id_type` is the type of the variable to be used [optional]
- `td_dim` is the array of dimension structure [optional]
- `td_att` is the array of attribute structure [optional] Note:
- others optionals arguments could be added, see [var_init](#).
- to put scalar variable (OD), use `td_dim` with all dimension unused (`td_dim(:)|_use=.FALSE.`)

to print information about variable structure:

```
CALL var_print(td_var [,ld_more])
```

- `td_var` is the variable structure
- `ld_more` to print more information about variable

to clean variable structure:

```
CALL var_clean(tl_var)
```

to copy variable structure in another one (using different memory cell):

```
tl_var2=var_copy(tl_var1)
```

Note

as we use pointer for the value array of the variable structure, the use of the assignment operator (=) to copy variable structure create a pointer on the same array. This is not the case with this copy function.

to get variable name:

- `tl_var%c_name`

to get grid point of the variable:

- `tl_var%c_point`

to get EW overlap:

- `tl_var%i_ew`

to get variable value:

- `tl_var%d_value(:, :, :)`

to get the type number (based on NETCDF type constants) of the variable (as define initially or read in file):

- `tl_var%i_type`

to get variable id (read from a file):

- `tl_var%i_id`

Variable dimension

to get the number of dimension used in the variable:

- `tl_var%i_ndim`

to get the array of dimension structure (4 elts) associated to the variable:

- `tl_var%t_dim(:)`

Variable attributes

Note

attribue value are always character or real(8) 1D array.

to get the number of attributes of the variable:

- `tl_var%i_natt`

to get the array of attribute structure associated to the variable:

- `tl_var%t_att(:)`

Some attribute are highlight, to be easily used. to get variable standard name:

- `tl_var%c_stdname`

to get variable longname:

- `tl_var%c_longname`

to get variable units:

- `tl_var%c_units`

to get variable axis:

- `tl_var%c_axis`

to get variable scale factor:

- `tl_var%d_scf`

to get variable add offset:

- `tl_var%d_ofs`

to get variable FillValue:

- `tl_var%d_fill`

to add value to a variable structure:

```
CALL var_add_value(tl_var, value, [id_type,] [id_start, [id_count]])
```

- value : 4D array of value (real(4), real(8), integer(1), integer(2), integer(4), integer(8))
- id_type is the type of the variable to be used (default is the type of array value)
- id_start : 1D array of the index in the variable from which the data values will be read (integer(4), optional)
- id_count : 1D array of the number of indices selected along each dimension (integer(4), optional)

to add attribute to a variable structure:

```
CALL var_add_att(tl_var, td_att)
```

- td_att is an attribute structure, or array of attribute structure

to add dimension to a variable structure:

```
CALL var_add_dim(tl_var, td_dim)
```

- td_dim is a dimension structure, or array of dimension structure

to delete value of a variable structure:

```
CALL var_del_value(tl_var)
```

to delete one attribute of a variable structure:

```
CALL var_del_att(tl_var, td_att)
```

- td_att is an attribute structure or

```
CALL var_del_att(tl_var, cd_name)
```

- cd_name is attribute name

to delete one dimension of a variable structure:

```
CALL var_del_dim(tl_var, td_dim)
```

- td_dim is a dimension structure

to overwrite one attribute structure in variable structure:

```
CALL var_move_att(tl_var, td_att)
```

- td_att is an attribute structure

to overwrite one dimension structure in variable structure:

```
CALL var_move_dim(tl_var, td_dim)
```

- td_dim is a dimension structure

to get the mask of a variable structure, (based on its FillValue):

```
mask(:, :)=var_get_mask(tl_var)
```

to change FillValue to standard NETCDF Fill Value:

```
CALL var_chg_FillValue(tl_var, [dd_fill])
```

- `dd_fill` is the FillValue to be used [optional]

to concatenate two variables:

```
tl_var=var_concat(tl_var1, tl_var2, [dim])
```

- `tl_var1` : variable structure
- `tl_var2` : variable structure
- `DIM` : number of the dimension following which concatenate (1=>I, 2=>J, 3=>Z, 4=>T) [optional, default=4]

to forced min and max value of a variable:

define min and max value of the variable:

```
tl_var%d_min=min
```

```
tl_var%d_max=max
```

then

```
CALL var_limit_value( tl_var )
```

- `min` and `max` : real(8) value

to get the biggest dimensions use in a array of variable:

```
tl_dim(:)=var_max_dim(tl_var(:))
```

- `tl_var(:)` : array of variable structure
- `tl_dim(:)` : array (4 elts) of dimension structure

to reorder dimension of a variable (default 'x','y','z','t'):

```
CALL var_reorder( td_var, cd_dimorder )
```

- `td_var` is variable structure
- `cd_dimorder` string character(LEN=4) of dimension order to be used (example: 'yxzt') [optional]

to get variable index, in an array of variable structure:

```
il_index=var_get_index( td_var, cd_name )
```

- `td_var` array of variable structure
- `cd_name` variable name

to get variable id, read from a file:

```
il_id=var_get_id( td_var, cd_name )
```


- `td_var` array of variable structure
- `cd_name` variable name

to get free variable unit in an array of variable structure:

```
il_unit=var_get_unit(td_var)
```

- `td_var` array of variable structure

to convert time variable structure in date structure:

```
tl_date=var_to_date(td_var)
```

- `td_var` is time variable structure
- `tl_date` is date structure

to read matrix value from character string in namelist

```
CALL var_read_matrix(td_var, cd_matrix)
```

- `td_var` is variable structure
- `cd_matrix` is matrix value

to read variable configuration file ('variable.cfg') and fill global array of variable structure:

```
CALL var_def_extra( cd_file )
```

- `cd_file` is filename

to add variable information get from namelist, in global array of variable structure:

```
CALL var_chg_extra( cd_varinfo )
```

- `cd_varinfo` is variable information from namelist

to clean global array of variable structure:

```
CALL var_clean_extra( )
```

to check variable dimension expected, as defined in file 'variable.cfg':


```
CALL var_check_dim( td_var )
```

- `td_var` is variable structure

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add var_reorder

November, 2014

- Fix memory leaks bug

June, 2015

- change way to get variable information in namelist

July, 2015

- add subroutine var_chg_unit to change unit of output variable

Spetember, 2015

- manage useless (dummy) variable

October, 2016

- add subroutine to clean global array of extra information.
- define logical for variable to be used

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.115.2 Member Function/Subroutine Documentation**11.115.2.1 subroutine, public var::var_check_dim (type(tvar), intent(inout) td_var)**

This subroutine check variable dimension expected, as defined in file 'variable.cfg'.

compare dimension used in variable structure with string character axis from configuration file.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
----------------	---------------	--------------------

11.115.2.2 subroutine, public var::var_chg_extra (character(len=*), dimension(:), intent(in) cd_varinfo)

This subroutine add variable information get from namelist in global array of variable structure with extra information: tg_varextra.

string character format must be :

"varname:int=interp;flt=filter;ext=extrap;min=min;max=max"

you could specify only interpolation, filter or extrapolation method, whatever the order. you could find more information about available method in [interp](#), [filter](#), and [extrap](#) module.

Examples: cn_varinfo='Bathymetry:flt=2*hamming(2,3);min=10.' cn_varinfo='votemper:int=cubic;ext=dist_weight;max=40.'

Warning

variable should be define in `tg_varextra` (ie in configuration file, to be able to add information from namelist

Note

If you do not specify a method which is required, default one is apply.

Author

J.Paul

Date

November, 2013 - Initial Version

July, 2015

- get unit and unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_varinfo</code>	variable information from namelist
-----------------	-------------------------	------------------------------------

11.115.2.3 subroutine, public var::`var_chg_fillvalue` (`type(tvar)`, `intent(inout) td_var`, `real(dp)`, `intent(in)`, optional `dd_fill`)

This subroutine change FillValue of the variable to standard NETCDF FillValue.

optionally, you could specify a dummy `_FillValue` to be used

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	array of variable structure
<code>in</code>	<code>dd_fill</code>	<code>_FillValue</code> to be used

11.115.2.4 subroutine, public var::`var_chg_unit` (`type(tvar)`, `intent(inout) td_var`)

This subroutine replace unit name of the variable, and apply unit factor to the value of this variable.

new unit name (unt) and unit factor (unf) are read from the namelist.

Note

the variable value should be already read.

Author

J.Paul

Date

June, 2015 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
----------------	---------------	--------------------

11.115.2.5 subroutine, public var::var_clean_extra ()

This subroutine clean global array of variable structure with extra information: *tg_varextra*.

Author

J.Paul

Date

October, 2016 - Initial Version

11.115.2.6 type(tvar) function, public var::var_concat (type(tvar), intent(in) *td_var1*, type(tvar), intent(in) *td_var2*, integer(*i4*), intent(in), optional *DIM*)

This function concatenate variable value following DIM direction.

By default variable are concatenate following time dimension. To concatenate following another dimension, specify DIM=x where x is the dimension number (*jp_1*, *jp_J*, *jp_K*, *jp_L*).

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_var1</i>	variable structure
<i>in</i>	<i>td_var2</i>	variable structure
<i>in</i>	<i>DIM</i>	dimension following which concatenate

Returns

variable structure

11.115.2.7 subroutine, public var::var_def_extra (character(len=*), intent(in) *cd_file*)

This subroutine read variable configuration file. And save global array of variable structure with extra information: *tg_varextra*.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- new namelist format to get extra information (interpolation,...)

Parameters

<i>in</i>	<i>cd_file</i>	configuration file of variable
-----------	----------------	--------------------------------

11.115.2.8 subroutine, public var::var_del_dim (type(tvar), intent(inout) *td_var*, type(tdim), intent(in) *td_dim*)

This subroutine delete a dimension structure in a variable structure.

Warning

delete variable value too.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.115.2.9 subroutine, public var::var_del_value (type(tvar), intent(inout) *td_var*)

This subroutine remove variable value in a variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
----------------	---------------	--------------------

11.115.2.10 subroutine, public var::var_get_dummy (character(len=*), intent(in) *cd_dummy*)

This subroutine fill dummy variable array.

Author

J.Paul

Date

September, 2015 - Initial Version

Parameters

in	<i>cd_dummy</i>	dummy configuration file
----	-----------------	--------------------------

11.115.2.11 **INTEGER(i4) function, public var::var_get_id (type(tvar), dimension(:), intent(in) *td_var*, character(len=*), intent(in) *cd_name*, character(len=*), intent(in), optional *cd_stdname*)**

This function return the variable id, given variable name or standard name.

Author

J.Paul

Date

November, 2013 - Initial Version
July, 2015

- check long name

Parameters

in	<i>td_var</i>	array of variable structure
in	<i>cd_name</i>	variable name
in	<i>cd_stdname</i>	variable standard name

Returns

variable id in array of variable structure (0 if not found)

11.115.2.12 **INTEGER(i4) function, public var::var_get_index (type(tvar), dimension(:), intent(in) *td_var*, character(len=*), intent(in) *cd_name*, character(len=*), intent(in), optional *cd_stdname*)**

This function return the variable index, in a array of variable structure, given variable name or standard name.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in	<i>td_var</i>	array of variable structure
in	<i>cd_name</i>	variable name
in	<i>cd_stdname</i>	variable standard name

Returns

variable index in array of variable structure (0 if not found)

11.115.2.13 `integer(i4) function, dimension(td_var%t_dim(1)%i_len, td_var%t_dim(2)%i_len, td_var%t_dim(3)%i_len), public var::var_get_mask (type(tvar), intent(in) td_var)`

This function return the mask 3D of variable, given variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	array of variable structure
-----------------	---------------------	-----------------------------

Returns

variable mask(3D)

11.115.2.14 `integer(i4) function, public var::var_get_unit (type(tvar), dimension(:), intent(in) td_var)`

This function get the next unused unit in array of variable structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	array of variable structure
-----------------	---------------------	-----------------------------

Returns

free variable id

11.115.2.15 `logical function, public var::var_is_dummy (type(tvar), intent(in) td_var)`

This function check if variable is defined as dummy variable in configuraton file.

Author

J.Paul

Date

September, 2015 - Initial Version

Parameters

<i>in</i>	<i>td_var</i>	variable structure
-----------	---------------	--------------------

Returns

true if variable is dummy variable

11.115.2.16 subroutine, public var::var_limit_value (type(tvar), intent(inout) *td_var*)

This subroutine forced minimum and maximum value of variable, with value of variable structure attribute *d_min* and *d_max*.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
----------------	---------------	--------------------

11.115.2.17 type(tdim) function, dimension(ip_maxdim), public var::var_max_dim (type(tvar), dimension(:), intent(in) *td_var*)

This function search and save the biggest dimensions use in an array of variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in</i>	<i>td_var</i>	array of variable structure
-----------	---------------	-----------------------------

Returns

array of dimension

11.115.2.18 subroutine, public var::var_move_att (type(tvar), intent(inout) *td_var*, type(tatt), intent(in) *td_att*)

This subroutine move an attribute structure from variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>td_att</i>	attribute structure

11.115.2.19 subroutine, public var::var_move_dim (type(tvar), intent(inout) *td_var*, type(tdim), intent(in) *td_dim*)

This subroutine move a dimension structure in variable structure.

Warning

- dimension order could be changed
- delete variable value

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>td_dim</i>	dimension structure

11.115.2.20 subroutine, public var::var_read_matrix (type(tvar), intent(inout) *td_var*, character(len=*) , intent(in) *cd_matrix*)

This subroutine read matrix value from character string in namelist and fill variable structure value.

to split matrix, separator use are:

- ';' for line
- '/' for row
- '\' for level

Example:

$$3,2,3/1,4,5 => \begin{pmatrix} 3 & 2 & 3 \\ 1 & 4 & 5 \end{pmatrix}$$

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>cd_matrix</code>	matrix value

11.115.2.21 subroutine, public var::var_reorder (type(tvar), intent(inout) *td_var*, character(len=ip_maxdim), intent(in), optional *cd_dimorder*)

This subroutine reshape variable value and dimension in variable structure.

output dimension will be ordered as defined in input array of dimension. Optionally you could specify output dimension order with string character of dimension.

Author

J.Paul

Date

August, 2014 - Initial Version

July 2015

- do not use `dim_disorder` anymore

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>cd_dimorder</code>	string character of dimension order to be used

11.115.2.22 type(tdate) function, public var::var_to_date (type(tvar), intent(in) *td_var*)

This function convert a time variable structure in date structure.

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	time variable structure
-----------------	---------------------	-------------------------

Returns

date structure

The documentation for this module was generated from the following file:

- `src/variable.f90`

11.116 var::var_add_att Interface Reference

Public Member Functions

- subroutine `var__add_att_unit` (`td_var`, `td_att`)

This subroutine add an attribute structure in a variable structure.

- subroutine `var__add_att_arr` (td_var, td_att)

This subroutine add an array of attribute structure in a variable structure.

11.116.1 Member Function/Subroutine Documentation

11.116.1.1 subroutine `var::var_add_att::var__add_att_arr` (type(tvar), intent(inout) *td_var*, type(tatt), dimension(:), intent(in) *td_att*)

This subroutine add an array of attribute structure in a variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add all element of the array in the same time

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>td_att</i>	array of attribute structure

11.116.1.2 subroutine `var::var_add_att::var__add_att_unit` (type(tvar), intent(inout) *td_var*, type(tatt), intent(in) *td_att*)

This subroutine add an attribute structure in a variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- use `var__add_att_arr` subroutine

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>td_att</i>	attribute structure

The documentation for this interface was generated from the following file:

- `src/variable.f90`

11.117 var::var_add_dim Interface Reference

Public Member Functions

- subroutine `var__add_dim_unit` (td_var, td_dim)

This subroutine add one dimension in a variable structure.

- subroutine `var__add_dim_arr` (td_var, td_dim)

This subroutine add an array of dimension structure in a variable structure.

11.117.1 Member Function/Subroutine Documentation

11.117.1.1 subroutine `var::var_add_dim::var__add_dim_arr` (`type(tvar)`, `intent(inout) td_var`, `type(tdim)`, `dimension(:)`, `intent(in) td_dim`)

This subroutine add an array of dimension structure in a variable structure.

- number of dimension in variable can't be greater than 4
- dimension can't be already uses in variable structure

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>td_dim</code>	dimension structure

11.117.1.2 subroutine `var::var_add_dim::var__add_dim_unit` (`type(tvar)`, `intent(inout) td_var`, `type(tdim)`, `intent(in) td_dim`)

This subroutine add one dimension in a variable structure.

- number of dimension in variable can't be greater than 4
- dimension can't be already uses in variable structure

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>td_dim</code>	dimension structure

The documentation for this interface was generated from the following file:

- `src/variable.f90`

11.118 `var::var_add_value` Interface Reference

Public Member Functions

- subroutine `var__add_value_dp` (`td_var`, `dd_value`, `id_type`, `id_start`, `id_count`)
This subroutine add a 4D array of real(8) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')
- subroutine `var__add_value_rp` (`td_var`, `rd_value`, `id_type`, `id_start`, `id_count`)

This subroutine add a 4D array of real(4) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

- subroutine `var__add_value_i1` (td_var, bd_value, id_type, id_start, id_count)

This subroutine add a 4D array of integer(1) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

- subroutine `var__add_value_i2` (td_var, sd_value, id_type, id_start, id_count)

This subroutine add a 4D array of integer(2) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

- subroutine `var__add_value_i4` (td_var, id_value, id_type, id_start, id_count)

This subroutine add a 4D array of integer(4) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

- subroutine `var__add_value_i8` (td_var, kd_value, id_type, id_start, id_count)

This subroutine add a 4D array of integer(8) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

11.118.1 Member Function/Subroutine Documentation

11.118.1.1 subroutine `var::var_add_value::var__add_value_dp` (type(tvar), intent(inout) *td_var*, real(dp), dimension(:,:,:,:), intent(in) *dd_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of real(8) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default real(8)), and indices of the variable where value will be written with start and count array.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>dd_value</i>	array of variable value
in	<i>id_type</i>	type of the variable to be used (default real(8))
in	<i>id_start</i>	start indices of the variable where data values will be written
in	<i>id_count</i>	number of indices selected along each dimension

11.118.1.2 subroutine `var::var_add_value::var__add_value_i1` (type(tvar), intent(inout) *td_var*, integer(i1), dimension(:,:,:,:), intent(in) *bd_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of integer(1) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default integer(1)), and indices of the variable where value will be written with start and count array.

Note

variable type is forced to BYTE

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variabele structure
<i>in</i>	<i>bd_value</i>	array of variable value
<i>in</i>	<i>id_type</i>	type of the variable to be used (default integer(1))
<i>in</i>	<i>id_start</i>	start indices of the variable where data values will be read
<i>in</i>	<i>id_count</i>	number of indices selected along each dimension

11.118.1.3 subroutine var::var_add_value::var__add_value_i2 (type(tvar), intent(inout) *td_var*, integer(i2), dimension(:, :, :, :), intent(in) *sd_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of integer(2) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default integer(2)), and indices of the variable where value will be written with start and count array.

Note

variable type is forced to SHORT

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variabele structure
<i>in</i>	<i>sd_value</i>	array of variable value
<i>in</i>	<i>id_type</i>	type of the variable to be used (default integer(2))
<i>in</i>	<i>id_start</i>	start indices of the variable where data values will be read
<i>in</i>	<i>id_count</i>	number of indices selected along each dimension

11.118.1.4 subroutine var::var_add_value::var__add_value_i4 (type(tvar), intent(inout) *td_var*, integer(i4), dimension(:, :, :, :), intent(in) *id_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of integer(4) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default integer(4)), and indices of the variable where value will be written with start and count array.

Note

variable type is forced to INT

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variabele structure
<i>in</i>	<i>id_value</i>	array of variable value
<i>in</i>	<i>id_type</i>	type of the variable to be used (default integer(4))
<i>in</i>	<i>id_start</i>	start indices of the variable where data values will be read
<i>in</i>	<i>id_count</i>	number of indices selected along each dimension

11.118.1.5 subroutine var::var_add_value::var_add_value_i8 (type(tvar), intent(inout) *td_var*, integer(i8), dimension(:, :, :, :), intent(in) *kd_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of integer(8) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default integer(4)), and indices of the variable where value will be written with start and count array.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>kd_value</i>	array of variable value
<i>in</i>	<i>id_type</i>	type of the variable to be used (default integer(8))
<i>in</i>	<i>id_start</i>	start indices of the variable where data values will be read
<i>in</i>	<i>id_count</i>	number of indices selected along each dimension

11.118.1.6 subroutine var::var_add_value::var_add_value_rp (type(tvar), intent(inout) *td_var*, real(sp), dimension(:, :, :, :), intent(in) *rd_value*, integer(i4), intent(in), optional *id_type*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*)

This subroutine add a 4D array of real(4) value in a variable structure. Dimension of the array must be ordered as ('x','y','z','t')

Optionally, you could specify the type of the variable to be used (default real(4)), and indices of the variable where value will be written with start and count array.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>rd_value</i>	array of variable value
in	<i>id_type</i>	type of the variable to be used (default real(4))
in	<i>id_start</i>	start indices of the variable where data values will be written
in	<i>id_count</i>	number of indices selected along each dimension

The documentation for this interface was generated from the following file:

- src/variable.f90

11.119 var::var_clean Interface Reference

Public Member Functions

- subroutine [var__clean_unit](#) (td_var)
This subroutine clean variable structure.
- subroutine [var__clean_arr_1d](#) (td_var)
This subroutine clean 1D array of variable structure.
- subroutine [var__clean_arr_2d](#) (td_var)
This subroutine clean 2D array of variable structure.
- subroutine [var__clean_arr_3d](#) (td_var)
This subroutine clean 3D array of variable structure.

11.119.1 Member Function/Subroutine Documentation

11.119.1.1 subroutine `var::var_clean::var__clean_arr_1d (type(tvar), dimension(:), intent(inout) td_var)`

This subroutine clean 1D array of variable structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

in, out	<i>td_var</i>	array of variable strucutre
---------	---------------	-----------------------------

11.119.1.2 subroutine var::var_clean::var__clean_arr_2d (type(tvar), dimension(:,:), intent(inout) *td_var*)

This subroutine clean 2D array of variable structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	array of variable strucutre
----------------	---------------	-----------------------------

11.119.1.3 subroutine var::var_clean::var__clean_arr_3d (type(tvar), dimension(:, :, :), intent(inout) *td_var*)

This subroutine clean 3D array of variable structure.

Author

J.Paul

Date

September, 2014 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	array of variable strucutre
----------------	---------------	-----------------------------

11.119.1.4 subroutine var::var_clean::var__clean_unit (type(tvar), intent(inout) *td_var*)

This subroutine clean variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable strucutre
----------------	---------------	--------------------

The documentation for this interface was generated from the following file:

- src/variable.f90

11.120 var::var_copy Interface Reference

Public Member Functions

- `type(tvar)` function `var__copy_unit` (`td_var`)
This subroutine copy variable structure in another one.
- `type(tvar)` function, `dimension(size(td_var(:)))` `var__copy_arr` (`td_var`)
This subroutine copy a array of variable structure in another one.

11.120.1 Member Function/Subroutine Documentation

11.120.1.1 `type(tvar)` function, `dimension(size(td_var(:)))` `var::var_copy::var__copy_arr` (`type(tvar)`, `dimension(:)`, `intent(in)` `td_var`)

This subroutine copy a array of variable structure in another one.

see `var__copy_unit`

Warning

do not use on the output of a function who create or read an structure (ex: `tl_var=var_copy(var_init())` is forbidden). This will create memory leaks.
 to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version
 November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

<code>in</code>	<code>td_var</code>	array of variable structure
-----------------	---------------------	-----------------------------

Returns

copy of input array of variable structure

11.120.1.2 `type(tvar)` function `var::var_copy::var__copy_unit` (`type(tvar)`, `intent(in)` `td_var`)

This subroutine copy variable structure in another one.

variable value are copied in a temporary array, so input and output variable structure value do not point on the same "memory cell", and so are independant.

Warning

do not use on the output of a function who create or read an structure (ex: `tl_var=var_copy(var_init())` is forbidden). This will create memory leaks.
 to avoid infinite loop, do not use any function inside this subroutine

Author

J.Paul

Date

November, 2013 - Initial Version

November, 2014

- use function instead of overload assignment operator (to avoid memory leak)

Parameters

in	td_var	variable structure
----	--------	--------------------

Returns

copy of input variable structure

The documentation for this interface was generated from the following file:

- src/variable.f90

11.121 var::var_del_att Interface Reference

Public Member Functions

- subroutine [var__del_att_name](#) (td_var, cd_name)
This subroutine delete an attribute from variable structure.
- subroutine [var__del_att_str](#) (td_var, td_att)
This subroutine delete an attribute from variable structure.

11.121.1 Member Function/Subroutine Documentation

11.121.1.1 subroutine var::var_del_att::var__del_att_name (type(tvar), intent(inout) td_var, character(len=*) intent(in) cd_name)

This subroutine delete an attribute from variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- define local attribute structure to avoid mistake with pointer

Parameters

in, out	td_var	variable structure
---------	--------	--------------------

in	<i>cd_name</i>	attribute name
----	----------------	----------------

11.121.1.2 subroutine `var::var_del_att::var__del_att_str (type(tvar), intent(inout) td_var, type(tatt), intent(in) td_att)`

This subroutine delete an attribute from variable structure.

Author

J.Paul

Date

November, 2013- Initial Version

February, 2015

- delete highlight attribute too, when attribute is deleted

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>td_att</i>	attribute structure

The documentation for this interface was generated from the following file:

- src/variable.f90

11.122 var::var_init Interface Reference

Public Member Functions

- TYPE(TVAR) function `var__init` (*cd_name*, *id_type*, *td_dim*, *td_att*, *dd_fill*, *cd_units*, *cd_axis*, *cd_stdname*, *cd_longname*, *cd_point*, *id_id*, *id_ew*, *dd_scf*, *dd_ofs*, *id_rec*, *dd_min*, *dd_max*, *ld_contiguous*, *ld_shuffle*, *ld_fletcher32*, *id_deflvl*, *id_chunksz*, *cd_interp*, *cd_extrap*, *cd_filter*, *cd_unt*, *dd_unf*)

This function initialize a variable structure, given variable name.

- TYPE(TVAR) function `var__init_dp` (*cd_name*, *dd_value*, *id_start*, *id_count*, *id_type*, *td_dim*, *td_att*, *dd_fill*, *cd_units*, *cd_axis*, *cd_stdname*, *cd_longname*, *cd_point*, *id_id*, *id_ew*, *dd_scf*, *dd_ofs*, *id_rec*, *dd_min*, *dd_max*, *ld_contiguous*, *ld_shuffle*, *ld_fletcher32*, *id_deflvl*, *id_chunksz*, *cd_interp*, *cd_extrap*, *cd_filter*, *cd_unt*, *dd_unf*)

This function initialize a variable structure, with a real(8) 4D array of value.

- TYPE(TVAR) function `var__init_1d_dp` (*cd_name*, *dd_value*, *id_start*, *id_count*, *id_type*, *td_dim*, *td_att*, *dd_fill*, *cd_units*, *cd_axis*, *cd_stdname*, *cd_longname*, *cd_point*, *id_id*, *id_ew*, *dd_scf*, *dd_ofs*, *id_rec*, *dd_min*, *dd_max*, *ld_contiguous*, *ld_shuffle*, *ld_fletcher32*, *id_deflvl*, *id_chunksz*, *cd_interp*, *cd_extrap*, *cd_filter*, *cd_unt*, *dd_unf*)

This function initialize a variable structure, with a real(8) 1D array of value.

- TYPE(TVAR) function `var__init_2d_dp` (*cd_name*, *dd_value*, *id_start*, *id_count*, *id_type*, *td_dim*, *td_att*, *dd_fill*, *cd_units*, *cd_axis*, *cd_stdname*, *cd_longname*, *cd_point*, *id_id*, *id_ew*, *dd_scf*, *dd_ofs*, *id_rec*, *dd_min*, *dd_max*, *ld_contiguous*, *ld_shuffle*, *ld_fletcher32*, *id_deflvl*, *id_chunksz*, *cd_interp*, *cd_extrap*, *cd_filter*, *cd_unt*, *dd_unf*)

This function initialize a variable structure, with a real(8) 2D array of value. optionally could be added:

- TYPE(TVAR) function `var__init_3d_dp` (*cd_name*, *dd_value*, *id_start*, *id_count*, *id_type*, *td_dim*, *td_att*, *dd_fill*, *cd_units*, *cd_axis*, *cd_stdname*, *cd_longname*, *cd_point*, *id_id*, *id_ew*, *dd_scf*, *dd_ofs*, *id_rec*, *dd_min*, *dd_max*, *ld_contiguous*, *ld_shuffle*, *ld_fletcher32*, *id_deflvl*, *id_chunksz*, *cd_interp*, *cd_extrap*, *cd_filter*, *cd_unt*, *dd_unf*)

This function initialize a variable structure, with a real(8) 3D array of value.

- TYPE(TVAR) function `var__init_sp` (cd_name, rd_value, id_start, id_count, id_type, td_dim, td_att, rd_fill, cd__units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a real(4) 4D array of value.
- TYPE(TVAR) function `var__init_1d_sp` (cd_name, rd_value, id_start, id_count, id_type, td_dim, td_att, rd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a real(4) 1D array of value.
- TYPE(TVAR) function `var__init_2d_sp` (cd_name, rd_value, id_start, id_count, id_type, td_dim, td_att, rd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a real(4) 2D array of value.
- TYPE(TVAR) function `var__init_3d_sp` (cd_name, rd_value, id_start, id_count, id_type, td_dim, td_att, rd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a real(4) 3D array of value.
- TYPE(TVAR) function `var__init_i1` (cd_name, bd_value, id_start, id_count, id_type, td_dim, td_att, bd_fill, cd__units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(1) 4D array of value.
- TYPE(TVAR) function `var__init_1d_i1` (cd_name, bd_value, id_start, id_count, id_type, td_dim, td_att, bd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(1) 1D array of value.
- TYPE(TVAR) function `var__init_2d_i1` (cd_name, bd_value, id_start, id_count, id_type, td_dim, td_att, bd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(1) 2D array of value.
- TYPE(TVAR) function `var__init_3d_i1` (cd_name, bd_value, id_start, id_count, id_type, td_dim, td_att, bd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(1) 3D array of value.
- TYPE(TVAR) function `var__init_i2` (cd_name, sd_value, id_start, id_count, id_type, td_dim, td_att, sd_fill, cd__units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(2) 4D array of value.
- TYPE(TVAR) function `var__init_1d_i2` (cd_name, sd_value, id_start, id_count, id_type, td_dim, td_att, sd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(2) 1D array of value.
- TYPE(TVAR) function `var__init_2d_i2` (cd_name, sd_value, id_start, id_count, id_type, td_dim, td_att, sd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(2) 2D array of value.
- TYPE(TVAR) function `var__init_3d_i2` (cd_name, sd_value, id_start, id_count, id_type, td_dim, td_att, sd_fill, cd_units, cd_axis, cd_stdname, cd_longname, cd_point, id_id, id_ew, dd_scf, dd_ofs, id_rec, dd_min, dd_max, ld_contiguous, ld_shuffle, ld_fletcher32, id_deflvl, id_chunksz, cd_interp, cd_extrap, cd_filter, cd_unt, dd_unf)

This function initialize a variable structure, with a integer(2) 3D array of value.

This function initialize a variable structure, with a integer(2) 3D array of value.

- TYPE(TVAR) function `var__init_i4` (`cd_name`, `id_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `id_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(4) 4D array of value.

- TYPE(TVAR) function `var__init_1d_i4` (`cd_name`, `id_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `id_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(4) 1D array of value.

- TYPE(TVAR) function `var__init_2d_i4` (`cd_name`, `id_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `id_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(4) 2D array of value.

- TYPE(TVAR) function `var__init_3d_i4` (`cd_name`, `id_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `id_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(4) 3D array of value.

- TYPE(TVAR) function `var__init_i8` (`cd_name`, `kd_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `kd_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(8) 4D array of value.

- TYPE(TVAR) function `var__init_1d_i8` (`cd_name`, `kd_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `kd_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(8) 1D array of value.

- TYPE(TVAR) function `var__init_2d_i8` (`cd_name`, `kd_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `kd_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(8) 2D array of value.

- TYPE(TVAR) function `var__init_3d_i8` (`cd_name`, `kd_value`, `id_start`, `id_count`, `id_type`, `td_dim`, `td_att`, `kd_fill`, `cd_units`, `cd_axis`, `cd_stdname`, `cd_longname`, `cd_point`, `id_id`, `id_ew`, `dd_scf`, `dd_ofs`, `id_rec`, `dd_min`, `dd_max`, `ld_contiguous`, `ld_shuffle`, `ld_fletcher32`, `id_deflvl`, `id_chunksz`, `cd_interp`, `cd_extrap`, `cd_filter`, `cd_unt`, `dd_unf`)

This function initialize a variable structure, with a integer(8) 3D array of value.

11.122.1 Member Function/Subroutine Documentation

- 11.122.1.1 TYPE(TVAR) function `var::var_init::var__init` (`character(len=*)`, `intent(in)` `cd_name`, `integer(i4)`, `intent(in)`, optional `id_type`, `type(td_dim)`, `dimension(:)`, `intent(in)`, optional `td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, optional `td_att`, `real(dp)`, `intent(in)`, optional `dd_fill`, `character(len=*)`, `intent(in)`, optional `cd_units`, `character(len=*)`, `intent(in)`, optional `cd_axis`, `character(len=*)`, `intent(in)`, optional `cd_stdname`, `character(len=*)`, `intent(in)`, optional `cd_longname`, `character(len=*)`, `intent(in)`, optional `cd_point`, `integer(i4)`, `intent(in)`, optional `id_id`, `integer(i4)`, `intent(in)`, optional `id_ew`, `real(dp)`, `intent(in)`, optional `dd_scf`, `real(dp)`, `intent(in)`, optional `dd_ofs`, `integer(i4)`, `intent(in)`, optional `id_rec`, `real(dp)`, `intent(in)`, optional `dd_min`, `real(dp)`, `intent(in)`, optional `dd_max`, `logical`, `intent(in)`, optional `ld_contiguous`, `logical`, `intent(in)`, optional `ld_shuffle`, `logical`, `intent(in)`, optional `ld_fletcher32`, `integer(i4)`, `intent(in)`, optional `id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, optional `id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, optional `cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, optional `cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, optional `cd_filter`, `character(len=*)`, `intent(in)`, optional `cd_unt`, `real(dp)`, `intent(in)`, optional `dd_unf`)

This function initialize a variable structure, given variable name.

Optionally you could add 1D,2D,3D or 4D array of value, see var__init_1D_dp, var__init_2D_dp... for more information.

you could also add more information with the following optional arguments:

- id_type : integer(4) variable type, (as defined by NETCDF type constants).
- td_dim : array of dimension structure.
- td_att : array of attribute structure.
- dd_fill : real(8) variable FillValue. if none NETCDF FillValue will be used.
- cd_units : string character of units.
- cd_axis : string character of axis expected to be used
- cd_stdname : string character of variable standard name.
- cd_longname : string character of variable long name.
- cd_point : one character for ARAKAWA C-grid point name (T,U,V,F).
- id_id : variable id (read from a file).
- id_ew : number of point composing east west wrap band.
- dd_unf : real(8) value for units factor attribute.
- dd_scf : real(8) value for scale factor attribute.
- dd_ofs : real(8) value for add offset attribute.
- id_rec : record id (for rstdimg file).
- dd_min : real(8) value for minimum value.
- dd_max : real(8) value for maximum value.
- ld_contiguous : use contiguous storage or not (for netcdf4).
- ld_shuffle : shuffle filter is turned on or not (for netcdf4).
- ld_fletcher32 : fletcher32 filter is turned on or not (for netcdf4).
- id_deflvl : deflate level from 0 to 9, 0 indicates no deflation is in use (for netcdf4).
- id_chunksz : chunk size (for netcdf4).
- cd_interp : a array of character defining interpolation method.
- cd_extrap : a array of character defining extrapolation method.
- cd_filter : a array of character defining filtering method.
- cd_unt : a string character to define output unit
- dd_unf : real(8) factor applied to change unit

Note

most of these optionals arguments will be inform automatically, when reading variable from a file, or using configuration file variable.cfg.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- Bug fix: conversion of the FillValue type (float case)

June, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>dd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.2 TYPE(TVAR) function var::var_init::var__init_1d_dp (character(len=*) , intent(in) *cd_name*, real(dp), dimension(:), intent(in) *dd_value*, integer(i4), intent(in), optional *id_start*, integer(i4), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(dp), intent(in), optional *dd_fill*, character(len=*) , intent(in), optional *cd_units*, character(len=*) , intent(in), optional *cd_axis*, character(len=*) , intent(in), optional *cd_stdname*, character(len=*) , intent(in), optional *cd_longname*, character(len=*) , intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*) , dimension(2), intent(in), optional *cd_interp*, character(len=*) , dimension(1), intent(in), optional *cd_extrap*, character(len=*) , dimension(5), intent(in), optional *cd_filter*, character(len=*) , intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(8) 1D array of value.

Optionally could be added:

- dimension structure.
- attribute structure. Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

November, 2016

- allow to add scalar value

Parameters

in	<i>cd_name</i>	variable name
in	<i>dd_value</i>	1D array of real(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>dd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not

in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.3 TYPE(TVAR) function var::var_init::var__init_1d_i1 (character(len=*), intent(in) *cd_name*, integer(i1), dimension(:), intent(in) *bd_value*, integer(i4), intent(in), optional *id_start*, integer(i4), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i1), intent(in), optional *bd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(1) 1D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>bd_value</i>	1D array of integer(1) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>bd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.4 **TYPE(TVAR) function** `var::var_init::var_init_1d_i2` (`character(len=*)`, `intent(in) cd_name`, `integer(i2)`, `dimension(:)`, `intent(in) sd_value`, `integer(i4)`, `intent(in)`, `optional id_start`, `integer(i4)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i2)`, `intent(in)`, `optional sd_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional ld_contiguous`, `logical`, `intent(in)`, `optional ld_shuffle`, `logical`, `intent(in)`, `optional ld_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unt`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a integer(2) 1D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>sd_value</i>	1D array of integer(2) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>sd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)

<i>in</i>	<i>dd_unf</i>	units factor
-----------	---------------	--------------

Returns

variable structure

11.122.1.5 TYPE(TVAR) function var::var_init::var__init_1d_i4 (character(len=*), intent(in) *cd_name*, integer(i4), dimension(:), intent(in) *id_value*, integer(i4), intent(in), optional *id_start*, integer(i4), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i4), intent(in), optional *id_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvt*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(4) 1D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<i>in</i>	<i>cd_name</i>	variable name
<i>in</i>	<i>id_value</i>	1D array of integer(4) value
<i>in</i>	<i>id_start</i>	index in the variable from which the data values will be read
<i>in</i>	<i>id_count</i>	number of indices selected along each dimension

in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>id_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.6 TYPE(TVAR) function var::var_init::var__init_1d_i8 (character(len=*), intent(in) *cd_name*, integer(i8), dimension(:), intent(in) *kd_value*, integer(i4), intent(in), optional *id_start*, integer(i4), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i8), intent(in), optional *kd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(8) 1D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	: variable name
in	<i>kd_value</i>	: 1D array of integer(8) value
in	<i>id_start</i>	: index in the variable from which the data values will be read
in	<i>id_count</i>	: number of indices selected along each dimension
in	<i>id_type</i>	: variable type
in	<i>td_dim</i>	: array of dimension structure
in	<i>td_att</i>	: array of attribute structure
in	<i>kd_fill</i>	: fill value
in	<i>cd_units</i>	: units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	: variable standard name
in	<i>cd_longname</i>	: variable long name
in	<i>cd_point</i>	: point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	: variable id
in	<i>id_ew</i>	: east west wrap
in	<i>dd_scf</i>	: scale factor
in	<i>dd_ofs</i>	: add offset
in	<i>id_rec</i>	: record id (for rstdimg file)
in	<i>dd_min</i>	: minimum value
in	<i>dd_max</i>	: maximum value
in	<i>ld_contiguous</i>	: use contiguous storage or not
in	<i>ld_shuffle</i>	: shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	: fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	: deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	: chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.7 TYPE(TVAR) function var::var_init::var__init_1d_sp (character(len=*), intent(in) *cd_name*, real(sp), dimension(:), intent(in) *rd_value*, integer(i4), intent(in), optional *id_start*, integer(i4), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(sp), intent(in), optional *rd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvt*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(4) 1D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>rd_value</i>	1D array of real(4) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure

in	<i>td_att</i>	array of attribute structure
in	<i>rd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.8 TYPE(TVAR) function var::var_init::var_init_2d_dp (character(len=*), intent(in) *cd_name*, real(dp), dimension(:,:), intent(in) *dd_value*, integer(i4), dimension(:), intent(in), optional *id_start*, integer(i4), dimension(:), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(dp), intent(in), optional *dd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(8) 2D array of value. optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

February, 2015

- bug fix: array initialise with dimension array not only one value

June, 2015

- add interp, extrap, and filter argument
- Bux fix: dimension array initialise not only one value

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>dd_value</i>	1D array of real(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>dd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.9 TYPE(TVAR) function var::var_init::var__init_2d_i1 (character(len=*), intent(in) *cd_name*, integer(i1), dimension(:,:), intent(in) *bd_value*, integer(i4), dimension(:), intent(in), optional *id_start*, integer(i4), dimension(:), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i1), intent(in), optional *bd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(1) 2D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>bd_value</i>	2D array of integer(1) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>bd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used

in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.10 TYPE(TVAR) function `var::var_init::var_init_2d_i2 (character(len=*), intent(in) cd_name, integer(i2), dimension(:,:), intent(in) sd_value, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count, integer(i4), intent(in), optional id_type, type(tdim), dimension(:), intent(in), optional td_dim, type(tatt), dimension(:), intent(in), optional td_att, integer(i2), intent(in), optional sd_fill, character(len=*), intent(in), optional cd_units, character(len=*), intent(in), optional cd_axis, character(len=*), intent(in), optional cd_stdname, character(len=*), intent(in), optional cd_longname, character(len=*), intent(in), optional cd_point, integer(i4), intent(in), optional id_id, integer(i4), intent(in), optional id_ew, real(dp), intent(in), optional dd_scf, real(dp), intent(in), optional dd_ofs, integer(i4), intent(in), optional id_rec, real(dp), intent(in), optional dd_min, real(dp), intent(in), optional dd_max, logical, intent(in), optional ld_contiguous, logical, intent(in), optional ld_shuffle, logical, intent(in), optional ld_fletcher32, integer(i4), intent(in), optional id_deflvl, integer(i4), dimension(ip_maxdim), intent(in), optional id_chunksz, character(len=*), dimension(2), intent(in), optional cd_interp, character(len=*), dimension(1), intent(in), optional cd_extrap, character(len=*), dimension(5), intent(in), optional cd_filter, character(len=*), intent(in), optional cd_unt, real(dp), intent(in), optional dd_unf)`

This function initialize a variable structure, with a integer(2) 2D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>sd_value</i>	2D array of integer(2) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>sd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.11 TYPE(TVAR) function `var::var_init::var__init_2d_i4` (`character(len=*)`, `intent(in) cd_name`, `integer(i4)`, `dimension(:,:)`, `intent(in) id_value`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i4)`, `intent(in)`, `optional id_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unit`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a integer(4) 2D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	variable name
<code>in</code>	<code>id_value</code>	2D array of integer(4) value
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	variable type
<code>in</code>	<code>td_dim</code>	array of dimension structure

in	<i>td_att</i>	array of attribute structure
in	<i>id_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.12 TYPE(TVAR) function `var::var_init::var_init_2d_i8 (character(len=*), intent(in) cd_name, integer(i8), dimension(:,:), intent(in) kd_value, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count, integer(i4), intent(in), optional id_type, type(tdim), dimension(:), intent(in), optional td_dim, type(tatt), dimension(:), intent(in), optional td_att, integer(i8), intent(in), optional kd_fill, character(len=*), intent(in), optional cd_units, character(len=*), intent(in), optional cd_axis, character(len=*), intent(in), optional cd_stdname, character(len=*), intent(in), optional cd_longname, character(len=*), intent(in), optional cd_point, integer(i4), intent(in), optional id_id, integer(i4), intent(in), optional id_ew, real(dp), intent(in), optional dd_scf, real(dp), intent(in), optional dd_ofs, integer(i4), intent(in), optional id_rec, real(dp), intent(in), optional dd_min, real(dp), intent(in), optional dd_max, logical, intent(in), optional ld_contiguous, logical, intent(in), optional ld_shuffle, logical, intent(in), optional ld_fletcher32, integer(i4), intent(in), optional id_deflvl, integer(i4), dimension(ip_maxdim), intent(in), optional id_chunksz, character(len=*), dimension(2), intent(in), optional cd_interp, character(len=*), dimension(1), intent(in), optional cd_extrap, character(len=*), dimension(5), intent(in), optional cd_filter, character(len=*), intent(in), optional cd_unt, real(dp), intent(in), optional dd_unf)`

This function initialize a variable structure, with a integer(8) 2D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>kd_value</i>	2D array of integer(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>kd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.13 TYPE(TVAR) function var::var_init::var__init_2d_sp (character(len=*), intent(in) *cd_name*, real(sp), dimension(:,:), intent(in) *rd_value*, integer(i4), dimension(:), intent(in), optional *id_start*, integer(i4), dimension(:), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(sp), intent(in), optional *rd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(4) 2D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 2 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	: variable name
in	<i>rd_value</i>	: 2D array of real(4) value
in	<i>id_start</i>	: index in the variable from which the data values will be read
in	<i>id_count</i>	: number of indices selected along each dimension
in	<i>id_type</i>	: variable type
in	<i>td_dim</i>	: array of dimension structure

in	<i>td_att</i>	: array of attribute structure
in	<i>rd_fill</i>	: fill value
in	<i>cd_units</i>	: units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	: variable standard name
in	<i>cd_longname</i>	: variable long name
in	<i>cd_point</i>	: point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	: variable id
in	<i>id_ew</i>	: east west wrap
in	<i>dd_scf</i>	: scale factor
in	<i>dd_ofs</i>	: add offset
in	<i>id_rec</i>	: record id (for rstdimg file)
in	<i>dd_min</i>	: minimum value
in	<i>dd_max</i>	: maximum value
in	<i>ld_contiguous</i>	: use contiguous storage or not
in	<i>ld_shuffle</i>	: shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	: fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	: deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	: chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.14 TYPE(TVAR) function `var::var_init::var_init_3d_dp (character(len=*), intent(in) cd_name, real(dp), dimension(:, :, :), intent(in) dd_value, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count, integer(i4), intent(in), optional id_type, type(tdim), dimension(:), intent(in), optional td_dim, type(tatt), dimension(:), intent(in), optional td_att, real(dp), intent(in), optional dd_fill, character(len=*), intent(in), optional cd_units, character(len=*), intent(in), optional cd_axis, character(len=*), intent(in), optional cd_stdname, character(len=*), intent(in), optional cd_longname, character(len=*), intent(in), optional cd_point, integer(i4), intent(in), optional id_id, integer(i4), intent(in), optional id_ew, real(dp), intent(in), optional dd_scf, real(dp), intent(in), optional dd_ofs, integer(i4), intent(in), optional id_rec, real(dp), intent(in), optional dd_min, real(dp), intent(in), optional dd_max, logical, intent(in), optional ld_contiguous, logical, intent(in), optional ld_shuffle, logical, intent(in), optional ld_fletcher32, integer(i4), intent(in), optional id_deflvl, integer(i4), dimension(ip_maxdim), intent(in), optional id_chunksz, character(len=*), dimension(2), intent(in), optional cd_interp, character(len=*), dimension(1), intent(in), optional cd_extrap, character(len=*), dimension(5), intent(in), optional cd_filter, character(len=*), intent(in), optional cd_unt, real(dp), intent(in), optional dd_unf)`

This function initialize a variable structure, with a real(8) 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>dd_value</i>	1D array of real(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>dd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.15 TYPE(TVAR) function `var::var_init::var__init_3d_i1` (`character(len=*)`, `intent(in) cd_name`, `integer(i1)`, `dimension(:, :, :)`, `intent(in) bd_value`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i1)`, `intent(in)`, `optional bd_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unit`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a `integer(1)` 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	variable name
<code>in</code>	<code>bd_value</code>	3D array of <code>integer(1)</code> value
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	variable type
<code>in</code>	<code>td_dim</code>	array of dimension structure

in	<i>td_att</i>	array of attribute structure
in	<i>bd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.16 TYPE(TVAR) function `var::var_init::var_init_3d_i2 (character(len=*), intent(in) cd_name, integer(i2), dimension(:, :, :), intent(in) sd_value, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count, integer(i4), intent(in), optional id_type, type(tdim), dimension(:), intent(in), optional td_dim, type(tatt), dimension(:), intent(in), optional td_att, integer(i2), intent(in), optional sd_fill, character(len=*), intent(in), optional cd_units, character(len=*), intent(in), optional cd_axis, character(len=*), intent(in), optional cd_stdname, character(len=*), intent(in), optional cd_longname, character(len=*), intent(in), optional cd_point, integer(i4), intent(in), optional id_id, integer(i4), intent(in), optional id_ew, real(dp), intent(in), optional dd_scf, real(dp), intent(in), optional dd_ofs, integer(i4), intent(in), optional id_rec, real(dp), intent(in), optional dd_min, real(dp), intent(in), optional dd_max, logical, intent(in), optional ld_contiguous, logical, intent(in), optional ld_shuffle, logical, intent(in), optional ld_fletcher32, integer(i4), intent(in), optional id_deflvl, integer(i4), dimension(ip_maxdim), intent(in), optional id_chunksz, character(len=*), dimension(2), intent(in), optional cd_interp, character(len=*), dimension(1), intent(in), optional cd_extrap, character(len=*), dimension(5), intent(in), optional cd_filter, character(len=*), intent(in), optional cd_unt, real(dp), intent(in), optional dd_unf)`

This function initialize a variable structure, with a integer(2) 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>sd_value</i>	3D array of integer(2) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>sd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.17 TYPE(TVAR) function `var::var_init::var__init_3d_i4` (`character(len=*)`, `intent(in) cd_name`, `integer(i4)`, `dimension(:, :, :)`, `intent(in) id_value`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i4)`, `intent(in)`, `optional id_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unit`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a integer(4) 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	variable name
<code>in</code>	<code>id_value</code>	3D array of integer(4) value
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	variable type
<code>in</code>	<code>td_dim</code>	array of dimension structure

in	<i>td_att</i>	array of attribute structure
in	<i>id_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.18 TYPE(TVAR) function `var::var_init::var_init_3d_i8 (character(len=*), intent(in) cd_name, integer(i8), dimension(:, :, :), intent(in) kd_value, integer(i4), dimension(:), intent(in), optional id_start, integer(i4), dimension(:), intent(in), optional id_count, integer(i4), intent(in), optional id_type, type(tdim), dimension(:), intent(in), optional td_dim, type(tatt), dimension(:), intent(in), optional td_att, integer(i8), intent(in), optional kd_fill, character(len=*), intent(in), optional cd_units, character(len=*), intent(in), optional cd_axis, character(len=*), intent(in), optional cd_stdname, character(len=*), intent(in), optional cd_longname, character(len=*), intent(in), optional cd_point, integer(i4), intent(in), optional id_id, integer(i4), intent(in), optional id_ew, real(dp), intent(in), optional dd_scf, real(dp), intent(in), optional dd_ofs, integer(i4), intent(in), optional id_rec, real(dp), intent(in), optional dd_min, real(dp), intent(in), optional dd_max, logical, intent(in), optional ld_contiguous, logical, intent(in), optional ld_shuffle, logical, intent(in), optional ld_fletcher32, integer(i4), intent(in), optional id_deflvl, integer(i4), dimension(ip_maxdim), intent(in), optional id_chunksz, character(len=*), dimension(2), intent(in), optional cd_interp, character(len=*), dimension(1), intent(in), optional cd_extrap, character(len=*), dimension(5), intent(in), optional cd_filter, character(len=*), intent(in), optional cd_unt, real(dp), intent(in), optional dd_unf)`

This function initialize a variable structure, with a integer(8) 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>kd_value</i>	2D array of integer(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>kd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.19 TYPE(TVAR) function `var::var_init::var__init_3d_sp` (`character(len=*)`, `intent(in) cd_name`, `real(sp)`, `dimension(:, :, :)`, `intent(in) rd_value`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(:)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `real(sp)`, `intent(in)`, `optional rd_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvl`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unt`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a real(4) 3D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

array of 3 dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	: variable name
<code>in</code>	<code>rd_value</code>	: 2D array of real(4) value
<code>in</code>	<code>id_start</code>	: index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	: number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	: variable type
<code>in</code>	<code>td_dim</code>	: array of dimension structure

in	<i>td_att</i>	: array of attribute structure
in	<i>rd_fill</i>	: fill value
in	<i>cd_units</i>	: units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	: variable standard name
in	<i>cd_longname</i>	: variable long name
in	<i>cd_point</i>	: point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	: variable id
in	<i>id_ew</i>	: east west wrap
in	<i>dd_scf</i>	: scale factor
in	<i>dd_ofs</i>	: add offset
in	<i>id_rec</i>	: record id (for rstdimg file)
in	<i>dd_min</i>	: minimum value
in	<i>dd_max</i>	: maximum value
in	<i>ld_contiguous</i>	: use contiguous storage or not
in	<i>ld_shuffle</i>	: shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	: fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	: deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	: chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.20 TYPE(TVAR) function `var::var_init::var_init_dp` (character(len=*), intent(in) *cd_name*, real(dp), dimension(:,:,:), intent(in) *dd_value*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(dp), intent(in), optional *dd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(8) 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>dd_value</i>	4D array of real(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>dd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.21 TYPE(TVAR) function `var::var_init::var__init_i1` (`character(len=*)`, `intent(in) cd_name`, `integer(i1)`, `dimension(:,::,::,::)`, `intent(in) bd_value`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i1)`, `intent(in)`, `optional bd_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvt`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unt`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a `integer(1)` 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	variable name
<code>in</code>	<code>bd_value</code>	4D array of <code>integer(1)</code> value
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	variable type

in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>bd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.22 TYPE(TVAR) function `var::var_init::var__init_i2` (character(len=*), intent(in) *cd_name*, integer(i2), dimension(:,:,:), intent(in) *sd_value*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i2), intent(in), optional *sd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(2) 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>sd_value</i>	4D array of integer(2) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>sd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.23 TYPE(TVAR) function `var::var_init::var__init_i4` (`character(len=*)`, `intent(in) cd_name`, `integer(i4)`, `dimension(:, :, :, :)`, `intent(in) id_value`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_start`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_count`, `integer(i4)`, `intent(in)`, `optional id_type`, `type(tdim)`, `dimension(:)`, `intent(in)`, `optional td_dim`, `type(tatt)`, `dimension(:)`, `intent(in)`, `optional td_att`, `integer(i4)`, `intent(in)`, `optional id_fill`, `character(len=*)`, `intent(in)`, `optional cd_units`, `character(len=*)`, `intent(in)`, `optional cd_axis`, `character(len=*)`, `intent(in)`, `optional cd_stdname`, `character(len=*)`, `intent(in)`, `optional cd_longname`, `character(len=*)`, `intent(in)`, `optional cd_point`, `integer(i4)`, `intent(in)`, `optional id_id`, `integer(i4)`, `intent(in)`, `optional id_ew`, `real(dp)`, `intent(in)`, `optional dd_scf`, `real(dp)`, `intent(in)`, `optional dd_ofs`, `integer(i4)`, `intent(in)`, `optional id_rec`, `real(dp)`, `intent(in)`, `optional dd_min`, `real(dp)`, `intent(in)`, `optional dd_max`, `logical`, `intent(in)`, `optional id_contiguous`, `logical`, `intent(in)`, `optional id_shuffle`, `logical`, `intent(in)`, `optional id_fletcher32`, `integer(i4)`, `intent(in)`, `optional id_deflvt`, `integer(i4)`, `dimension(ip_maxdim)`, `intent(in)`, `optional id_chunksz`, `character(len=*)`, `dimension(2)`, `intent(in)`, `optional cd_interp`, `character(len=*)`, `dimension(1)`, `intent(in)`, `optional cd_extrap`, `character(len=*)`, `dimension(5)`, `intent(in)`, `optional cd_filter`, `character(len=*)`, `intent(in)`, `optional cd_unt`, `real(dp)`, `intent(in)`, `optional dd_unf`)

This function initialize a variable structure, with a `integer(4)` 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

<code>in</code>	<code>cd_name</code>	variable name
<code>in</code>	<code>id_value</code>	4D array of <code>integer(4)</code> value
<code>in</code>	<code>id_start</code>	index in the variable from which the data values will be read
<code>in</code>	<code>id_count</code>	number of indices selected along each dimension
<code>in</code>	<code>id_type</code>	variable type

in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>id_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.24 TYPE(TVAR) function `var::var_init::var__init_i8` (character(len=*), intent(in) *cd_name*, integer(i8), dimension(:,:,:), intent(in) *kd_value*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, integer(i8), intent(in), optional *kd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *ld_contiguous*, logical, intent(in), optional *ld_shuffle*, logical, intent(in), optional *ld_fletcher32*, integer(i4), intent(in), optional *id_deflvl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a integer(8) 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>kd_value</i>	4D array of integer(8) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type
in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>kd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

11.122.1.25 TYPE(TVAR) function var::var_init::var__init_sp (character(len=*), intent(in) *cd_name*, real(sp), dimension(:, :, :, :), intent(in) *rd_value*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_start*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_count*, integer(i4), intent(in), optional *id_type*, type(tdim), dimension(:), intent(in), optional *td_dim*, type(tatt), dimension(:), intent(in), optional *td_att*, real(sp), intent(in), optional *rd_fill*, character(len=*), intent(in), optional *cd_units*, character(len=*), intent(in), optional *cd_axis*, character(len=*), intent(in), optional *cd_stdname*, character(len=*), intent(in), optional *cd_longname*, character(len=*), intent(in), optional *cd_point*, integer(i4), intent(in), optional *id_id*, integer(i4), intent(in), optional *id_ew*, real(dp), intent(in), optional *dd_scf*, real(dp), intent(in), optional *dd_ofs*, integer(i4), intent(in), optional *id_rec*, real(dp), intent(in), optional *dd_min*, real(dp), intent(in), optional *dd_max*, logical, intent(in), optional *id_contiguous*, logical, intent(in), optional *id_shuffle*, logical, intent(in), optional *id_fletcher32*, integer(i4), intent(in), optional *id_deflvtl*, integer(i4), dimension(ip_maxdim), intent(in), optional *id_chunksz*, character(len=*), dimension(2), intent(in), optional *cd_interp*, character(len=*), dimension(1), intent(in), optional *cd_extrap*, character(len=*), dimension(5), intent(in), optional *cd_filter*, character(len=*), intent(in), optional *cd_unt*, real(dp), intent(in), optional *dd_unf*)

This function initialize a variable structure, with a real(4) 4D array of value.

optionally could be added:

- dimension structure.
- attribute structure.

Dimension structure is needed to put value in variable structure. If none is given, we assume array is ordered as ('x','y','z','t') and we use array size as length dimension.

indices in the variable where value will be written could be specify if start and count array are given. Dimension structure is needed in that case.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- add interp, extrap, and filter argument

July, 2015

- add unit factor (to change unit)

Parameters

in	<i>cd_name</i>	variable name
in	<i>rd_value</i>	4D array of real(4) value
in	<i>id_start</i>	index in the variable from which the data values will be read
in	<i>id_count</i>	number of indices selected along each dimension
in	<i>id_type</i>	variable type

in	<i>td_dim</i>	array of dimension structure
in	<i>td_att</i>	array of attribute structure
in	<i>rd_fill</i>	fill value
in	<i>cd_units</i>	units
in	<i>cd_axis</i>	axis expected to be used
in	<i>cd_stdname</i>	variable standard name
in	<i>cd_longname</i>	variable long name
in	<i>cd_point</i>	point on Arakawa-C grid (T,U,V,F)
in	<i>id_id</i>	variable id
in	<i>id_ew</i>	east west wrap
in	<i>dd_scf</i>	scale factor
in	<i>dd_ofs</i>	add offset
in	<i>id_rec</i>	record id (for rstdimg file)
in	<i>dd_min</i>	minimum value
in	<i>dd_max</i>	maximum value
in	<i>ld_contiguous</i>	use contiguous storage or not
in	<i>ld_shuffle</i>	shuffle filter is turned on or not
in	<i>ld_fletcher32</i>	fletcher32 filter is turned on or not
in	<i>id_deflvl</i>	deflate level from 0 to 9, 0 indicates no deflation is in use
in	<i>id_chunksz</i>	chunk size
in	<i>cd_interp</i>	interpolation method
in	<i>cd_extrap</i>	extrapolation method
in	<i>cd_filter</i>	filter method
in	<i>cd_unt</i>	new units (linked to units factor)
in	<i>dd_unf</i>	units factor

Returns

variable structure

The documentation for this interface was generated from the following file:

- src/variable.f90

11.123 var::var_print Interface Reference**Public Member Functions**

- subroutine [var__print_unit](#) (td_var, ld_more)
This subroutine print variable information.
- subroutine [var__print_arr](#) (td_var)
This subroutine print informations of an array of variables.

11.123.1 Member Function/Subroutine Documentation

11.123.1.1 subroutine [var::var_print::var__print_arr](#) (type(tvar), dimension(:), intent(in) td_var)

This subroutine print informations of an array of variables.

Author

J.Paul

Date

June, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	array of variables structure
-----------------	---------------------	------------------------------

11.123.1.2 subroutine `var::var_print::var__print_unit` (`type(tvar)`, `intent(in) td_var`, `logical`, `intent(in)`, `optional ld_more`)

This subroutine print variable information.

If `ld_more` is TRUE (default), print information about variable dimensions and variable attributes.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>ld_more</code>	print more information about variable

The documentation for this interface was generated from the following file:

- `src/variable.f90`

11.124 vgrid Module Reference

This module manage vertical grid.

Public Member Functions

- subroutine, public `vgrid_zgr_z` (`dd_gdepw`, `dd_gdept`, `dd_e3w`, `dd_e3t`, `dd_e3w_1d`, `dd_e3t_1d`, `dd_ppkth`, `dd_ppkth2`, `dd_ppacr`, `dd_ppacr2`, `dd_ppdzmin`, `dd_pphmax`, `dd_ppa0`, `dd_ppa1`, `dd_ppa2`, `dd_ppsur`)

This subroutine set the depth of model levels and the resulting vertical scale factors.

- subroutine `vgrid_zgr_bat` (`dd_bathy`, `dd_gdepw`, `dd_hmin`, `dd_fill`)

This subroutine.

- subroutine, public `vgrid_zgr_zps` (`id_mbathy`, `dd_bathy`, `id_jpkmax`, `dd_gdepw`, `dd_e3t`, `dd_e3zps_min`, `dd_e3zps_rat`, `dd_fill`)

This subroutine set the depth and vertical scale factor in partial step z-coordinate case.

- subroutine, public `vgrid_zgr_bat_ctl` (`id_mbathy`, `id_jpkmax`, `id_jpk`)

This subroutine check the bathymetry in levels.

- `type(tvar)` function, `dimension(ip_npoint)`,
public `vgrid_get_level` (`td_bathy`, `cd_namelist`, `td_dom`, `id_nlevel`)

This function compute bathy level in T,U,V,F point, and return them as array of variable structure.

11.124.1 Detailed Description

This module manage vertical grid.

to set the depth of model levels and the resulting vertical scale

factors:

```
CALL vgrid_zgr_z(dd_gdepw(:), dd_gdept(:), dd_e3w(:), dd_e3t(:),
                dd_ppkth, dd_ppkth2, dd_ppacr, dd_ppacr2,
                dd_ppdzmin, dd_pphmax,
                dd_ppa0, dd_ppa1, dd_ppa2, dd_ppsur)
```

- dd_gdepw is array of depth value on W point
- dd_gdept is array of depth value on T point
- dd_e3w is array of vertical mesh size on W point
- dd_e3t is array of vertical mesh size on T point
- dd_ppkth see NEMO documentation
- dd_ppkth2 see NEMO documentation
- dd_ppacr see NEMO documentation
- dd_ppdzmin see NEMO documentation
- dd_pphmax see NEMO documentation
- dd_ppa1 see NEMO documentation
- dd_ppa2 see NEMO documentation
- dd_ppa0 see NEMO documentation
- dd_ppsur see NEMO documentation

to set the depth and vertical scale factor in partial step z-coordinate

case:

```
CALL vgrid_zgr_zps(id_mbathy(:, :), dd_bathy(:, :), id_jpkmax, dd_gdepw(:),
                  dd_e3t(:), dd_e3zps_min, dd_e3zps_rat)
```

- id_mbathy is array of bathymetry level
- dd_bathy is array of bathymetry
- id_jpkmax is the maximum number of level to be used
- dd_gdepw is array of vertical mesh size on W point
- dd_e3t is array of vertical mesh size on T point
- dd_e3zps_min see NEMO documentation
- dd_e3zps_rat see NEMO documentation

to check the bathymetry in levels:

```
CALL vgrid_zgr_bat_ctl(id_mbathy, id_jpkmax, id_jpk)
```

- id_mbathy is array of bathymetry level

- `id_jpkmax` is the maximum number of level to be used
- `id_jpk` is the number of level

to compute bathy level in T,U,V,F point from Bathymetry file:

```
tl_level(:)=vgrid_get_level(td_bathy, [cd_namelist,] [td_dom,] [id_nlevel])
```

- `td_bathy` is Bathymetry file structure
- `cd_namelist` is namelist [optional]
- `td_dom` is domain structure [optional]
- `id_nlevel` is number of level to be used [optional]

Author

J.Paul

Date

November, 2013 - Initial Version

Spetember, 2014

- add header

June, 2015 - update subroutine with NEMO 3.6

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

11.124.2 Member Function/Subroutine Documentation

11.124.2.1 `type(tvar) function, dimension(ip_npoint), public vgrid::vgrid_get_level (type(tmpp), intent(in) td_bathy, character(len=*) , intent(in), optional cd_namelist, type(tdom), intent(in), optional td_dom, integer(i4), intent(in), optional id_nlevel)`

This function compute bathy level in T,U,V,F point, and return them as array of variable structure.

Bathymetry is read on Bathymetry file, then bathy level is computed on T point, and finally fit to U,V,F point.

you could specify :

- namelist where find parameter to set the depth of model levels (default use GLORYS 75 levels parameters)
- domain structure to specify on e area to work on
- number of level to be used

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_bathy</i>	Bathymetry file structure
in	<i>cd_namelist</i>	namelist
in	<i>td_dom</i>	domain structure
in	<i>id_nlevel</i>	number of level to be used

Returns

array of level on T,U,V,F point (variable structure)

11.124.2.2 subroutine vgrid::vgrid_zgr_bat (real(dp), dimension(:,:), intent(inout) *dd_bathy*, real(dp), dimension(:), intent(in) *dd_gdepw*, real(dp), intent(in) *dd_hmin*, real(dp), intent(in), optional *dd_fill*)

This subroutine.

Todo add subroutine description

Parameters

in, out	<i>dd_bathy</i>	
in	<i>dd_gdepw</i>	
in	<i>dd_hmin</i>	
in	<i>dd_fill</i>	

11.124.2.3 subroutine, public vgrid::vgrid_zgr_bat_ctl (integer(i4), dimension(:,:), intent(inout) *id_mbathy*, integer(i4), intent(inout) *id_jpkmax*, integer(i4), intent(inout) *id_jpk*)

This subroutine check the bathymetry in levels.

** Method : The array mbathy is checked to verified its consistency with the model options. in particular: mbathy must have at least 1 land grid-points ($mbathy \leq 0$) along closed boundary. mbathy must be cyclic IF $jperio=1$. mbathy must be lower or equal to $jpk-1$. isolated ocean grid points are suppressed from mbathy since they are only connected to remaining ocean through vertical diffusion. C A U T I O N : mbathy will be modified during the initializa- tion phase to become the number of non-zero w-levels of a water column, with a minimum value of 1.

** Action : - update mbathy: level bathymetry (in level index)

- update bathy : meter bathymetry (in meters)

Author

G.Madec

Date

Marsh, 2008 - Original code

Parameters

in	<i>id_mbathy</i>	
----	------------------	--

in	<i>id_jpkmax</i>	
in	<i>id_jpk</i>	

11.124.2.4 subroutine, public vgrid::vgrid_zgr_z (real(dp), dimension(:), intent(inout) *dd_gdepw*, real(dp), dimension(:), intent(inout) *dd_gdept*, real(dp), dimension(:), intent(inout) *dd_e3w*, real(dp), dimension(:), intent(inout) *dd_e3t*, real(dp), dimension(:), intent(inout) *dd_e3w_1d*, real(dp), dimension(:), intent(inout) *dd_e3t_1d*, real(dp), intent(in) *dd_ppkth*, real(dp), intent(in) *dd_ppkth2*, real(dp), intent(in) *dd_ppacr*, real(dp), intent(in) *dd_ppacr2*, real(dp), intent(in) *dd_ppdzmin*, real(dp), intent(in) *dd_pphmax*, real(dp), intent(in) *dd_ppa0*, real(dp), intent(in) *dd_ppa1*, real(dp), intent(in) *dd_ppa2*, real(dp), intent(in) *dd_ppsur*)

This subroutine set the depth of model levels and the resulting vertical scale factors.

** Method : z-coordinate system (use in all type of coordinate) The depth of model levels is defined from an analytical function the derivative of which gives the scale factors. both depth and scale factors only depend on k (1d arrays). <> w-level: $gdepw = fsdep(k)$ <> $e3w(k) = dk(fsdep)(k) = fse3(k)$ <> t-level: $gdept = fsdep(k+0.5)$ <> $e3t(k) = dk(fsdep)(k+0.5) = fse3(k+0.5)$ <>

** Action : - *gdept*, *gdepw* : depth of T- and W-point (m) <>

- *e3t*, *e3w* : scale factors at T- and W-levels (m) <>

Author

G. Madec

Date

Marsh,2008 - F90: Free form and module

Note

Reference : Marti, Madec & Delecluse, 1992, JGR, 97, No8, 12,763-12,766.

Parameters

in, out	<i>dd_gdepw</i>	
in, out	<i>dd_gdept</i>	
in, out	<i>dd_e3w</i>	
in, out	<i>dd_e3t</i>	
in	<i>dd_ppkth</i>	
in	<i>dd_ppkth2</i>	
in	<i>dd_ppacr</i>	
in	<i>dd_ppacr2</i>	
in	<i>dd_ppdzmin</i>	
in	<i>dd_pphmax</i>	
in	<i>dd_ppa1</i>	
in	<i>dd_ppa2</i>	
in	<i>dd_ppa0</i>	
in	<i>dd_ppsur</i>	

11.124.2.5 subroutine, public vgrid::vgrid_zgr_zps (integer(i4), dimension(:, :), intent(out) *id_mbathy*, real(dp), dimension(:, :), intent(inout) *dd_bathy*, integer(i4), intent(inout) *id_jpkmax*, real(dp), dimension(:), intent(in) *dd_gdepw*, real(dp), dimension(:), intent(in) *dd_e3t*, real(dp), intent(in) *dd_e3zps_min*, real(dp), intent(in) *dd_e3zps_rat*, real(dp), intent(in), optional *dd_fill*)

This subroutine set the depth and vertical scale factor in partial step z-coordinate case.

** Method : Partial steps : computes the 3D vertical scale factors of T-, U-, V-, W-, UW-, VW and F-points that are associated with a partial step representation of bottom topography.

The reference depth of model levels is defined from an analytical function the derivative of which gives the reference vertical scale factors. From depth and scale factors reference, we compute there new value with partial steps on 3d arrays (i, j, k).

w-level:

- $gdepw_ps(i,j,k) = fsdep(k)$
- $e3w_ps(i,j,k) = dk(fsdep)(k) = fse3(i,j,k)$ t-level:
- $gdept_ps(i,j,k) = fsdep(k+0.5)$
- $e3t_ps(i,j,k) = dk(fsdep)(k+0.5) = fse3(i,j,k+0.5)$

With the help of the bathymetric file (bathymetry_depth_ORCA_R2.nc), we find the mbathy index of the depth at each grid point. This leads us to three cases:

- $bathy = 0 \Rightarrow mbathy = 0$
- $1 < mbathy < jpkm1$
- $bathy > gdepw(jpk) \Rightarrow mbathy = jpkm1$

Then, for each case, we find the new depth at t- and w- levels and the new vertical scale factors at t-, u-, v-, w-, uw-, vw- and f-points.

This routine is given as an example, it must be modified following the user s desiderata. nevertheless, the output as well as the way to compute the model levels and scale factors must be respected in order to insure second order accuracy schemes.

Warning

- gdept, gdepw and e3 are positives
- gdept_ps, gdepw_ps and e3_ps are positives

Author

A. Bozec, G. Madec

Date

February, 2009 - F90: Free form and module
February, 2009

- A. de Miranda : rigid-lid + islands

Note

Reference : Pacanowsky & Gnanadesikan 1997, Mon. Wea. Rev., 126, 3248-3270.

Parameters

<i>in, out</i>	<i>id_mbathy</i>
----------------	------------------

in, out	<i>dd_bathy</i>	
in, out	<i>id_jpkmax</i>	
in	<i>dd_gdepw</i>	
in	<i>dd_e3t</i>	
in	<i>dd_e3zps_min</i>	
in	<i>dd_e3zps_rat</i>	
in	<i>dd_fill</i>	

The documentation for this module was generated from the following file:

- src/vgrid.f90

Chapter 12

File Documentation

12.1 src/create_bathy.f90 File Reference

This program creates fine grid bathymetry file.

Functions/Subroutines

- program [create_bathy](#)
- type(tvar) function [create_bathy_matrix](#) (td_var, td_coord)
This function create variable, filled with matrix value.
- type(tvar) function [create_bathy_extract](#) (td_var, td_mpp, td_coord)
This function extract variable from file over coordinate domain and return variable structure.
- type(tvar) function [create_bathy_get_var](#) (td_var, td_mpp, id_imin, id_jmin, id_imax, id_jmax, id_offset, id_rho)
This function get coarse grid variable, interpolate variable, and return variable structure over fine grid.
- subroutine [create_bathy_interp](#) (td_var, id_rho, id_offset, id_iext, id_jext)
This subroutine interpolate variable.
- subroutine [create_bathy_check_depth](#) (td_mpp, td_depth)
This subroutine get depth variable value in an open mpp structure and check if agree with already input depth variable.
- subroutine [create_bathy_check_time](#) (td_mpp, td_time)
This subroutine get date and time in an open mpp structure and check if agree with date and time already read.

12.1.1 Detailed Description

This program creates fine grid bathymetry file.


12.1.2 method

Bathymetry could be extracted from fine grid Bathymetry file, interpolated from coarse grid Bathymetry file, or manually written.

12.1.3 how to

to create fine grid bathymetry file:

```
./SIREN/bin/create_bathy create_bathy.nam
```



Note

you could find a template of the namelist in templates directory.

create_bathy.nam contains 7 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- coarse grid namelist (namcrs)
- fine grid namelist (namfin)
- variable namelist (namvar)
- nesting namelist (namnst)
- output namelist (namout)

logger namelist (namlog):

- cn_logfile : log filename
- cn_verbosity : verbosity ('trace','debug','info', 'warning','error','fatal','none')
- in_maxerror : maximum number of error allowed

config namelist (namcfg):

- cn_varcfg : variable configuration file (see ./SIREN/cfg/variable.cfg)
- cn_dimcfg : dimension configuration file. defines dimension allowed (see ./SIREN/cfg/dimension.cfg).
- cn_dumcfg : useless (dummy) configuration file, for useless dimension or variable (see ./SIREN/cfg/dummy.cfg).

coarse grid namelist (namcrs):

- cn_coord0 : coordinate file
- in_perio0 : NEMO periodicity index (see Model Boundary Condition in [NEMO documentation](#))

fine grid namelist (namfin):

- `cn_coord1` : coordinate file
- `in_perio1` : periodicity index
- `In_fillclosed` : fill closed sea or not (default is .TRUE.)

variable namelist (namvar):

- `cn_varfile` : list of variable, and corresponding file.
`cn_varfile` is the path and filename of the file where find variable.

Note

`cn_varfile` could be a matrix of value, if you want to filled manually variable value.
the variable array of value is split into equal subdomain.
Each subdomain is filled with the corresponding value of the matrix.
separators used to defined matrix are:

- ‘;’ for line
- ‘/’ for row Example:
 $3,2,3/1,4,5 \Rightarrow \begin{pmatrix} 3 & 2 & 3 \\ 1 & 4 & 5 \end{pmatrix}$

Examples:

- ‘Bathymetry:gridT.nc’
 - ‘Bathymetry:5000,5000,5000/5000,3000,5000/5000,5000,5000’
- `cn_varinfo` : list of variable and extra information about request(s) to be used.
each elements of `cn_varinfo` is a string character (separated by ‘;’).
it is composed of the variable name follow by ‘:’, then request(s) to be used on this variable.
request could be:
 - `int` = interpolation method
 - `ext` = extrapolation method
 - `flt` = filter method
 - `min` = minimum value
 - `max` = maximum value
 - `unt` = new units
 - `unf` = unit scale factor (linked to new units)
 requests must be separated by ‘;’.
order of requests does not matter.

informations about available method could be find in [interp](#), [extrap](#) and [filter](#) modules.

Example: ‘Bathymetry: flt=2*hamming(2,3); min=0’

Note

If you do not specify a method which is required, default one is apply.

Warning

variable name must be **Bathymetry** here.

nesting namelist (namnst):

- `in_rhoi` : refinement factor in i-direction
- `in_rhoj` : refinement factor in j-direction

Note

coarse grid indices will be deduced from fine grid coordinate file.

output namelist (namout):

- `cn_fileout` : output bathymetry file

Author

J.Paul

12.1.4 Function/Subroutine Documentation**12.1.4.1 program `create_bathy` ()****Date**

November, 2013 - Initial Version

September, 2014

- add header for user
- Bug fix, compute offset depending of grid point

June, 2015

- extrapolate all land points.
- allow to change unit.

September, 2015

- manage useless (dummy) variable, attributes, and dimension

January, 2016

- add `create_bathy_check_depth` as in `create_boundary`
- add `create_bathy_check_time` as in `create_boundary`

February, 2016

- do not closed sea for east-west cyclic domain

October, 2016

- dimension to be used select from configuration file

Todo • check `tl_multi` is not empty

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.1.4.2 subroutine `create_bathy::create_bathy_check_depth` (`type(tmpp)`, `intent(in) td_mpp`, `type(tvar)`, `intent(inout) td_depth`)

This subroutine get depth variable value in an open mpp structure and check if agree with already input depth variable.

Author

J.Paul

Date

January, 2016 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in, out	<i>td_depth</i>	depth variable structure

12.1.4.3 subroutine create_bathy::create_bathy_check_time (type(tmpp), intent(in) *td_mpp*, type(tvar), intent(inout) *td_time*)

This subroutine get date and time in an open mpp structure and check if agree with date and time already read.

Author

J.Paul

Date

January, 2016 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in, out	<i>td_time</i>	time variable structure

12.1.4.4 type(tvar) function create_bathy::create_bathy_extract (type(tvar), intent(in) *td_var*, type(tmpp), intent(in) *td_mpp*, type(tmpp), intent(in) *td_coord*)

This function extract variable from file over coordinate domain and return variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_mpp</i>	mpp file structure
in	<i>td_coord</i>	coordinate file structure

Returns

variable structure

12.1.4.5 type(tvar) function create_bathy::create_bathy_get_var (type(tvar), intent(in) *td_var*, type(tmpp), intent(in) *td_mpp*, integer(i4), intent(in) *id_imin*, integer(i4), intent(in) *id_jmin*, integer(i4), intent(in) *id_imax*, integer(i4), intent(in) *id_jmax*, integer(i4), dimension(:,:), intent(in) *id_offset*, integer(i4), dimension(:), intent(in) *id_rho*)

This function get coarse grid variable, interpolate variable, and return variable structure over fine grid.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_mpp</i>	mpp file structure
in	<i>id_imin</i>	i-direction lower left corner indice
in	<i>id_imax</i>	i-direction upper right corner indice
in	<i>id_jmin</i>	j-direction lower left corner indice
in	<i>id_jmax</i>	j-direction upper right corner indice
in	<i>id_offset</i>	offset between fine grid and coarse grid
in	<i>id_rho</i>	array of refinement factor

Returns

variable structure

12.1.4.6 subroutine `create_bathy::create_bathy_interp` (type(tvar), intent(inout) *td_var*, integer(i4), dimension(:), intent(in) *id_rho*, integer(i4), dimension(:,:), intent(in) *id_offset*, integer(i4), intent(in), optional *id_jext*, integer(i4), intent(in), optional *id_jext*)

This subroutine interpolate variable.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>id_rho</i>	array of refinement factor
in	<i>id_offset</i>	array of offset between fine and coarse grid
in	<i>id_jext</i>	i-direction size of extra bands (default=im_minext)
in	<i>id_jext</i>	j-direction size of extra bands (default=im_minext)

12.1.4.7 type(tvar) function `create_bathy::create_bathy_matrix` (type(tvar), intent(in) *td_var*, type(tmpp), intent(in) *td_coord*)

This function create variable, filled with matrix value.

A variable is create with the same name that the input variable, and with dimension of the coordinate file.

Then the variable array of value is split into equal subdomain. Each subdomain is filled with the corresponding value of the matrix.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_coord</i>	coordinate file structure

Returns

variable structure

12.2 src/create_boundary.F90 File Reference

This program creates boundary files.

Functions/Subroutines

- program [create_boundary](#)
- subroutine [create__boundary](#) (cd_namelist)
 - This subroutine create boundary files.*
- type(tdom) function, dimension(ip_npoint) [create_boundary_get_dom](#) (td_bathy1, td_bdy, id_seg)
 - This subroutine compute boundary domain for each grid point (T,U,V,F)*
- subroutine [create_boundary_get_coord](#) (td_coord1, td_dom1, cd_point, td_lon1, td_lat1)
 - This subroutine get coordinates over boundary domain.*
- subroutine [create_boundary_interp](#) (td_var, id_rho, id_offset, id_iext, id_jext)
 - This subroutine interpolate variable on boundary.*
- type(tvar) function [create_boundary_matrix](#) (td_var, td_dom, id_nlevel)
 - This function create variable, filled with matrix value.*
- subroutine [create_boundary_use_mask](#) (td_var, td_mask)
 - This subroutine use mask to filled land point with _FillValue.*
- type(tvar) function, dimension(ip_npoint) [create_boundary_get_level](#) (td_level, td_dom)
 - This function extract level over domain on each grid point, and return array of variable structure.*
- subroutine [create_boundary_check_depth](#) (td_var, td_mpp, id_nlevel, td_depth)
 - This subroutine check if variable need depth dimension, get depth variable value in an open mpp structure and check if agree with already input depth variable.*
- subroutine [create_boundary_check_time](#) (td_var, td_mpp, td_time)
 - This subroutine check if variable need time dimension, get date and time in an open mpp structure and check if agree with date and time already read.*

12.2.1 Detailed Description

This program creates boundary files.

12.2.2 method

Variables are read from coarse grid standard output, extracted or interpolated on fine grid. Variables could also be manually written.


Note

method could be different for each variable.

12.2.3 how to

to create boundaries files:

```
./SIREN/bin/create_boundary create_boundary.nam
```



Note

you could find a template of the namelist in templates directory.

create_boundary.nam contains 9 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- coarse grid namelist (namcrs)
- fine grid namelist (namfin)
- variable namelist (namvar)
- nesting namelist (namnst)
- boundary namelist (nambdy)
- vertical grid namelist (namzgr)
- output namelist (namout)

logger namelist (namlog):

- cn_logfile : log filename

- `cn_verbosity` : verbosity ('trace','debug','info', 'warning','error','fatal','none')
- `in_maxerror` : maximum number of error allowed

config namelist (namcfg):

- `cn_varcfg` : variable configuration file (see `./SIREN/cfg/variable.cfg`)
- `cn_dimcfg` : dimension configuration file. define dimensions allowed (see `./SIREN/cfg/dimension.cfg`).
- `cn_dumcfg` : useless (dummy) configuration file, for useless dimension or variable (see `./SIREN/cfg/dummy.cfg`).

coarse grid namelist (namcrs):

- `cn_coord0` : coordinate file
- `in_perio0` : NEMO periodicity index (see Model Boundary Condition in [NEMO documentation](#))

fine grid namelist (namfin):

- `cn_coord1` : coordinate file
- `cn_bathy1` : bathymetry file
- `in_perio1` : periodicity index

vertical grid namelist (namzgr):

- `dn_ppsur` :
- `dn_ppa0` :
- `dn_ppa1` :
- `dn_ppa2` :
- `dn_ppkth` :
- `dn_ppkth2` :
- `dn_ppacr` :
- `dn_ppacr2` :
- `dn_ppdzmin` :
- `dn_pphmax` :
- `in_nlevel` : number of vertical level

partial step namelist (namzps):

- `dn_e3zps_min` :
- `dn_e3zps_rat` :

variable namelist (namvar):

- `cn_varfile` : list of variable, and associated file
`cn_varfile` is the path and filename of the file where find variable.

Note

cn_varfile could be a matrix of value, if you want to filled manually variable value.
 the variable array of value is split into equal subdomain.
 Each subdomain is filled with the corresponding value of the matrix.
 separators used to defined matrix are:

- ';' for line
- '/' for row
- '\ ' for level

Example:

$$3,2,3/1,4,5 \Rightarrow \begin{pmatrix} 3 & 2 & 3 \\ 1 & 4 & 5 \end{pmatrix}$$

Warning

the same matrix is used for all boundaries.

Examples:

- 'votemper:gridT.nc', 'vozocrtx:gridU.nc'
- 'votemper:10\25', 'vozocrtx:gridU.nc'

- *cn_varinfo* : list of variable and extra information about request(s) to be used (separated by ';').
 each elements of *cn_varinfo* is a string character.
 it is composed of the variable name follow by ':', then request(s) to be used on this variable.
 request could be:

- int = interpolation method
 - ext = extrapolation method
 - flt = filter method
 - min = minimum value
 - max = maximum value
 - unt = new units
 - unf = unit scale factor (linked to new units)
- requests must be separated by ';'.
 order of requests does not matter.

informations about available method could be find in [interp](#), [extrap](#) and [filter](#).

Example: 'votemper:int=linear;flt=hann;ext=dist_weight', 'vosaline:int=cubic'

Note

If you do not specify a method which is required, default one is apply.

nesting namelist (namnst):

- in_rhoi : refinement factor in i-direction
- in_rhoj : refinement factor in j-direction

boundary namelist (nambdy):

- In_north : use north boundary
- In_south : use south boundary
- In_east : use east boundary

- In_west : use west boundary
- cn_north : north boundary indices on fine grid *cn_north* is a string character defining boundary segmentation. segments are separated by '|'.

each segments of the boundary is composed of:


- indice of velocity (orthogonal to boundary .ie. for north boundary, J-indice).
- indice of segment start (I-indice for north boundary)
- indice of segment end (I-indice for north boundary)
indices must be separated by ':' .
- optionally, boundary size could be added between '(' and ')' in the definition of the first segment.

Note

boundary width is the same for all segments of one boundary.

Examples:

- cn_north='index1,first1:last1(width)'
- cn_north='index1(width),first1:last1|index2,first2:last2'



- cn_south : south boundary indices on fine grid
- cn_east : east boundary indices on fine grid
- cn_west : west boundary indices on fine grid
- In_oneseg : force to use only one segment for each boundary or not

output namelist (namout):

- cn_fileout : fine grid boundary basename (cardinal point and segment number will be automatically added)
- dn_dayofs : date offset in day (change only output file name)
- In_extrap : extrapolate land point or not

Examples:

- cn_fileout='boundary.nc'
if time_counter (16/07/2015 00h) is read on input file (see varfile), west boundary will be named boundary_west_y2015m07d16
- dn_dayofs=-2.
if you use day offset you get boundary_west_y2015m07d14

Author

J.Paul

12.2.4 Function/Subroutine Documentation**12.2.4.1 subroutine create_boundary::create__boundary (character(len=lc), intent(in) cd_namelist)**

This subroutine create boundary files.

Parameters

in	cd_namelist
----	-------------

Author

J.Paul

Date

January, 2016 - Initial Version

Parameters

in	cd_namelist	namelist file
----	-------------	---------------

12.2.4.2 program create_boundary ()**Date**

November, 2013 - Initial Version

September, 2014

- add header for user
- take into account grid point to compute boundaries
- reorder output dimension for north and south boundaries

June, 2015

- extrapolate all land points, and add ln_extrap in namelist.
- allow to change unit.

July, 2015

- add namelist parameter to shift date of output file name.

September, 2015

- manage useless (dummy) variable, attributes, and dimension
- allow to run on multi processors with key_mpp_mpi

January, 2016

- same process use for variable extracted or interpolated from input file.

October, 2016

- dimension to be used select from configuration file

Todo

- rewrite using meshmask instead of bathymetry and coordinates files.

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.2.4.3 subroutine create_boundary::create_boundary_check_depth (type(tvar), intent(in) *td_var*, type(tmpp), intent(in) *td_mpp*, integer(i4), intent(in) *id_nlevel*, type(tvar), intent(inout) *td_depth*)

This subroutine check if variable need depth dimension, get depth variable value in an open mpp structure and check if agree with already input depth variable.

Author

J.Paul

Date

November, 2014 - Initial Version

January, 2016

- check if variable need/use depth dimension

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_mpp</i>	mpp structure
in	<i>id_nlevel</i>	mpp structure
in, out	<i>td_depth</i>	depth variable structure

12.2.4.4 subroutine create_boundary::create_boundary_check_time (type(tvar), intent(in) *td_var*, type(tmpp), intent(in) *td_mpp*, type(tvar), intent(inout) *td_time*)

This subroutine check if variable need time dimension, get date and time in an open mpp structure and check if agree with date and time already read.

Author

J.Paul

Date

November, 2014 - Initial Version

January, 2016

- check if variable need/use time dimension

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_mpp</i>	mpp structure
in, out	<i>td_time</i>	time variable structure

12.2.4.5 subroutine create_boundary::create_boundary_get_coord (type(tmpp), intent(in) *td_coord1*, type(tdom), intent(in) *td_dom1*, character(len=*), intent(in) *cd_point*, type(tvar), intent(out) *td_lon1*, type(tvar), intent(out) *td_lat1*)

This subroutine get coordinates over boundary domain.

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- take into account grid point

Parameters

in	<i>td_coord1</i>	coordinates file structure
in	<i>td_dom1</i>	boundary domain structure
in	<i>cd_point</i>	grid point
out	<i>td_lon1</i>	longitude variable structure
out	<i>td_lat1</i>	latitude variable structure

12.2.4.6 `type(tdom)` function, `dimension(ip_npoint)` `create_boundary::create_boundary_get_dom` (`type(tmpp)`, `intent(in) td_bathy1`, `type(tbdy)`, `intent(in) td_bdy`, `integer(i4)`, `intent(in) id_seg`)

This subroutine compute boundary domain for each grid point (T,U,V,F)

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- take into account grid point to compute boundary indices

Parameters

in	<i>td_bathy1</i>	file structure
in	<i>td_bdy</i>	boundary structure
in	<i>id_seg</i>	segment indice

Returns

array of domain structure

12.2.4.7 `type(tvar)` function, `dimension(ip_npoint)` `create_boundary::create_boundary_get_level` (`type(tvar)`, `dimension(:)`, `intent(in) td_level`, `type(tdom)`, `dimension(:)`, `intent(in) td_dom`)

This function extract level over domain on each grid point, and return array of variable structure.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_level</i>	array of level variable structure
in	<i>td_dom</i>	array of domain structure

Returns

array of variable structure

12.2.4.8 subroutine `create_boundary::create_boundary_interp` (`type(tvar)`, `intent(inout) td_var`, `integer(i4)`, `dimension(:)`, `intent(in) id_rho`, `integer(i4)`, `dimension(:,:)`, `intent(in) id_offset`, `integer(i4)`, `intent(in)`, `optional id_iext`, `integer(i4)`, `intent(in)`, `optional id_jext`)

This subroutine interpolate variable on boundary.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>id_rho</code>	array of refinement factor
<code>in</code>	<code>id_offset</code>	array of offset between fine and coarse grid
<code>in</code>	<code>id_iext</code>	i-direction size of extra bands (default= <code>im_minext</code>)
<code>in</code>	<code>id_jext</code>	j-direction size of extra bands (default= <code>im_minext</code>)

12.2.4.9 `type(tvar)` function `create_boundary::create_boundary_matrix` (`type(tvar)`, `intent(in) td_var`, `type(tdom)`, `intent(in) td_dom`, `integer(i4)`, `intent(in) id_nlevel`)

This function create variable, filled with matrix value.

A variable is create with the same name that the input variable, and with dimension of the coordinate file. Then the variable array of value is split into equal subdomain. Each subdomain is fill with the associated value of the matrix.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>td_dom</code>	domain structure
<code>in</code>	<code>id_nlevel</code>	number of levels

Returns

variable structure

12.2.4.10 subroutine `create_boundary::create_boundary_use_mask` (`type(tvar)`, `intent(inout) td_var`, `type(tvar)`, `intent(in) td_mask`)

This subroutine use mask to filled land point with `_FillValue`.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<code>in, out</code>	<code>td_var</code>	variable structure
<code>in</code>	<code>td_mask</code>	mask variable structure

12.3 src/create_coord.f90 File Reference

This program creates fine grid coordinate file.

Functions/Subroutines

- program [create_coord](#)
- integer(i4) function,
dimension(2, 2, ip_npoint) [create_coord_get_offset](#) (id_rho)
This function compute offset over Arakawa grid points, given refinement factor.
- subroutine [create_coord_interp](#) (td_var, id_rho, id_offset, id_iext, id_jext)
This subroutine interpolate variable, given refinement factor.

12.3.1 Detailed Description

This program creates fine grid coordinate file.

12.3.2 method

All variables from the input coordinates coarse grid file, are extracted and interpolated to create fine grid coordinates files.

Note

interpolation method could be different for each variable.

12.3.3 how to

to create fine grid coordinates files:

```
./SIREN/bin/create_coord create_coord.nam
```

Note

you could find a template of the namelist in templates directory.

create_coord.nam contains 6 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- coarse grid namelist (namcrs)
- variable namelist (namvar)
- nesting namelist (namnst)
- output namelist (namout)

logger namelist (namlog):

- cn_logfile : log filename
- cn_verbosity : verbosity ('trace','debug','info', 'warning','error','fatal','none')
- in_maxerror : maximum number of error allowed

config namelist (namcfg):

- cn_varcfg : variable configuration file (see ./SIREN/cfg/variable.cfg)
- cn_dimcfg : dimension configuration file. define dimensions allowed (see ./SIREN/cfg/dimension.cfg).
- cn_dumcfg : useless (dummy) configuration file, for useless dimension or variable (see ./SIREN/cfg/dummy.cfg).

coarse grid namelist (namcrs):

- cn_coord0 : coordinate file
- in_perio0 : NEMO periodicity index (see Model Boundary Condition in [NEMO documentation](#))

variable namelist (namvar):

- cn_varinfo : list of variable and extra information about request(s) to be used.
each elements of *cn_varinfo* is a string character (separated by ',').
it is composed of the variable name follow by ':', then request(s) to be used on this variable.
request could be:
 - int = interpolation method
 - ext = extrapolation method
 requests must be separated by ';'.
order of requests does not matter.

informations about available method could be find in [interp](#), [extrap](#) and [filter](#) modules.

Example: 'glamt: int=linear; ext=dist_weight', 'e1t: int=cubic/rho'

Note


If you do not specify a method which is required, default one is applied.

nesting namelist (namnst):

you could define sub domain with coarse grid indices or with coordinates.

- in_imin0 : i-direction lower left point indice of coarse grid subdomain to be used
- in_imax0 : i-direction upper right point indice of coarse grid subdomain to be used
- in_jmin0 : j-direction lower left point indice of coarse grid subdomain to be used
- in_jmax0 : j-direction upper right point indice of coarse grid subdomain to be used
- rn_lonmin0 : lower left longitude of coarse grid subdomain to be used
- rn_lonmax0 : upper right longitude of coarse grid subdomain to be used
- rn_latmin0 : lower left latitude of coarse grid subdomain to be used
- rn_latmax0 : upper right latitude of coarse grid subdomain to be used

- `in_rhoi` : refinement factor in i-direction
- `in_rhoj` : refinement factor in j-direction



- *output namelist (namout)*:
 - `cn_fileout` : output coordinate file name

Author

J.Paul

12.3.4 Function/Subroutine Documentation

12.3.4.1 program `create_coord` ()

Date

November, 2013 - Initial Version

September, 2014

- add header for user
- compute offset considering grid point
- add global attributes in output file

September, 2015

- manage useless (dummy) variable, attributes, and dimension

September, 2016

- allow to use coordinate to define subdomain

October, 2016

- dimension to be used select from configuration file

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.3.4.2 `integer(i4) function, dimension(2,2,ip_npoint) create_coord::create_coord_get_offset (integer(i4), dimension(:), intent(in) id_rho)`

This function compute offset over Arakawa grid points, given refinement factor.

Author

J.Paul

Date

August, 2014 - Initial Version

Parameters

<i>in</i>	<i>id_rho</i>	array of refinement factor
-----------	---------------	----------------------------

Returns

array of offset

12.3.4.3 `subroutine create_coord::create_coord_interp (type(tvar), intent(inout) td_var, integer(i4), dimension(:), intent(in) id_rho, integer(i4), dimension(:,:), intent(in) id_offset, integer(i4), intent(in), optional id_jext, integer(i4), intent(in), optional id_jext)`

This subroutine interpolate variable, given refinement factor.

Optionally, you could specify number of points to be extrapolated in i- and j-direction.

variable mask is first computed (using `_FillValue`) and interpolated.

variable is then extrapolated, and interpolated.

Finally interpolated mask is applied on refined variable.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

<i>in, out</i>	<i>td_var</i>	variable structure
<i>in</i>	<i>id_rho</i>	array of refinement factor
<i>in</i>	<i>id_offset</i>	offset between fine grid and coarse grid
<i>in</i>	<i>id_jext</i>	number of points to be extrapolated in i-direction
<i>in</i>	<i>id_jext</i>	number of points to be extrapolated in j-direction

Todo check if mask is really needed

12.4 src/create_meshmask.f90 File Reference

This program creates the NetCDF [file\(s\)](#) which contain(s) all the ocean domain informations. It allows to create the `domain_cfg.nc` file needed to run NEMO, or the `mesh_mask` [file\(s\)](#).

Functions/Subroutines

- program [create_meshmask](#)
- subroutine [create__mask](#) (td_nam, jpi, jpj, jpk, ld_domcfg)

This subroutine compute land/ocean mask arrays at tracer points, horizontal velocity points (u & v), vorticity points (f) and barotropic stream function points (b).
- type(tatt) function, dimension(ip_maxatt) [create__gloatt](#) (cd_bathy, cd_coord, cd_isfdep, td_namh, td_namz)

this function create array of global attributes.

12.4.1 Detailed Description

This program creates the NetCDF [file\(s\)](#) which contain(s) all the ocean domain informations. It allows to create the domain_cfg.nc file needed to run NEMO, or the mesh_mask [file\(s\)](#).

12.4.2 method

Bathymetry (and optionally ice shelf draft) is read on input file.

Horizontal grid-point position and scale factors, and the coriolis factor are read in coordinates file or computed.

Vertical coordinate is defined, and the bathymetry recomputed to fit the vertical grid.

Finally the masks from the bathymetry are computed.

All the arrays generated, are written in one to three [file\(s\)](#) depending on output option.

Note

the file contain depends on the vertical coordinate used (z-coord, partial steps, s-coord)

12.4.3 how to

to create domain_cfg or meshmask file:

```
./SIREN/bin/create_meshmask create_meshmask.nam
```

Note

you could find a template of the namelist in templates directory.

create_meshmask.nam contains 13 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- input files namelist (namin)
- horizontal grid namelist (namhgr)
- vertical grid namelist (namzgr)
- minimum depth namelist (namdmin)
- vertical coordinate namelist (namzco)
- partial step namelist (namzps)
- sigma or hybrid namelist (namsco)

- lateral boundary condition namelist (namlbc)
- wetting and dryong namelist (namwd)
- grid namelist (namgrd)
- output namelist (namout)

logger namelist (namlog):

- cn_logfile : log filename
- cn_verbosity : verbosity ('trace','debug','info', 'warning','error','fatal','none')
- in_maxerror : maximum number of error allowed

config namelist (namcfg):

- cn_varcfg : variable configuration file (see ./SIREN/cfg/variable.cfg).
- cn_dimcfg : dimension configuration file. define dimensions allowed (see ./SIREN/cfg/dimension.cfg).
- cn_dumcfg : useless (dummy) configuration file, for useless dimension or variable (see ./SIREN/cfg/dummy.cfg).

input files namelist (namin):

- cn_bathy : Bathymetry file
- cn_varbathy : Bathymetry variable name
- cn_coord : coordinate file (in_mshhgr=0)
- cn_isfdep : lceshelf draft (ln_isfcav=true)
- cn_varisfdep : lceshelf draft variable name (ln_isfcav=true)
- in_perio : NEMO periodicity
- ln_closea :

horizontal grid namelist (namhgr):

- in_mshhgr : type of horizontal mesh
 - 0: curvilinear coordinate on the sphere read in coordinate.nc
 - 1: geographical mesh on the sphere with regular grid-spacing
 - 2: f-plane with regular grid-spacing
 - 3: beta-plane with regular grid-spacing
 - 4: Mercator grid with T/U point at the equator
 - 5: beta-plane with regular grid-spacing and rotated domain (GYRE configuration)
- dn_ppglam0 : longitude of first row and column T-point (in_mshhgr = 1 or 4)
- dn_ppgphi0 : latitude of first row and column T-point (in_mshhgr = 1 or 4)
- dn_ppe1_deg : zonal grid-spacing (degrees) (in_mshhgr = 1,2,3 or 4)
- dn_ppe2_deg : meridional grid-spacing (degrees) (in_mshhgr = 1,2,3 or 4)

vertical grid namelist (namzgr):

- In_zco : z-coordinate - full steps
- In_zps : z-coordinate - partial steps
- In_sco : s- or hybrid z-s-coordinate
- In_isfcav : ice shelf cavities
- In_iscpl : coupling with ice sheet
- In_wd : Wetting/drying activation
- in_nlevel : number of vertical level

depth namelist (namdmin):

- dn_hmin : minimum ocean depth (>0) or minimum number of ocean levels (<0)
- dn_isfhmin : threshold to discriminate grounded ice to floating ice

vertical coordinate namelist (namzco):

- dn_ppsur : coefficient to compute vertical grid
- dn_ppa0 : coefficient to compute vertical grid
- dn_ppa1 : coefficient to compute vertical grid
- dn_ppkth : coefficient to compute vertical grid
- dn_ppacr : coefficient to compute vertical grid
- In_dbletanh : use double tanh function for vertical coordinates
- dn_ppa2 : double tanh function parameter
- dn_ppkth2 : double tanh function parameter
- dn_ppacr2 : double tanh function parameter
- dn_ppdzmin : minimum vertical spacing
- dn_pphmax : maximum depth

Note

If *ppa1* and *ppa0* and *ppsur* are undefined NEMO will compute them from *ppdzmin* , *pphmax*, *ppkth*, *ppacr*

this namelist is also needed to define partial steps, sigma or hybrid coordinate.

- *partial step namelist (namzps):*

- dn_e3zps_min : minimum thickness of partial step level (meters)
- dn_e3zps_rat : minimum thickness ratio of partial step level

- *sigma or hybrid namelist (namsco):*

- In_s_sh94 : use hybrid s-sig Song and Haidvogel 1994 stretching function fssig1
- In_s_sf12 : use hybrid s-z-sig Siddorn and Furner 2012 stretching function fgamma
- dn_sbot_min : minimum depth of s-bottom surface (>0) (m)
- dn_sbot_max : maximum depth of s-bottom surface (= ocean depth) (>0) (m)

- dn_hc : Critical depth for transition from sigma to stretched coordinates Song and Haidvogel 1994 stretching additional parameters
 - * dn_rmax : maximum cut-off r-value allowed ($0 < dn_rmax < 1$)
 - * dn_theta : surface control parameter ($0 \leq dn_theta \leq 20$)
 - * dn_thetb : bottom control parameter ($0 \leq dn_thetb \leq 1$)
 - * dn_bb : stretching parameter (dn_bb=0; top only, dn_bb =1; top and bottom) Siddorn and Furner stretching additional parameters
 - * ln_sigcrit : switching to sigma (T) or Z (F) at $H < H_c$
 - * dn_alpha : stretchin parameter (> 1 surface; < 1 bottom)
 - * dn_efold : e-fold length scale for transition region
 - * dn_zs : Surface cell depth (Zs) (m) Bottom cell (Zb) (m) = $H * rn_zb_a + rn_zb_b'$
 - * dn_zb_a : Bathymetry multiplier for Zb
 - * dn_zb_b : Offset for Zb
- *_lateral boundary condition namelist (namlbc)_:*
 - rn_shlat : lateral boundary conditions at the coast (modify fmask)
 - * shlat = 0 : free slip
 - * $0 < shlat < 2$: partial slip
 - * shlat = 2 : no slip
 - * shlat > 2 : strong slip for more information see Boundary Condition at the Coast in [NEMO documentation](#))
- *wetting and drying namelist (namwd):*
 - dn_wdmin1 : minimum water depth on dried cells
 - dn_wdmin2 : tollerance of minimum water depth on dried cells
 - dn_wdld : land elevation below which wetting/drying
- *grid namelist (namgrd):*
 - in_cfg : inverse resolution of the configuration ($1/4^\circ \Rightarrow 4$)
 - ln_bench : GYRE (in_mshhgr = 5) used as Benchmark.
=> forced the resolution to be about 100 km
 - ln_c1d : use configuration 1D
 - ln_e3_dep : vertical scale factors =T: e3.=dk[depth] =F: old definition
- *output namelist (namout):*
 - cn_domcfg : output file name
 - in_msh : number of output file and contain (0-9)
 - in_nproc : number of processor to be used
 - in_niproc : i-direction number of processor
 - in_njproc : j-direction numebr of processor

Note

- if in_msh = 0 : write '**domain_cfg.nc**' file.
- if $MOD(in_msh, 3) = 1$: write '**mesh_mask.nc**' file.
- if $MOD(in_msh, 3) = 2$: write '**mesh.nc**' and '**mask.nc**' files.
- if $MOD(in_msh, 3) = 0$: write '**mesh_hgr.nc**', '**mesh_zgr.nc**' and '**mask.nc**' files.
For huge size domain, use option 2 or 3 depending on your vertical coordinate.
- if in_msh ≤ 3 : write full 3D arrays for e3[tuvw] and gdep[tuvw]

- if $3 < in_msh \leq 6$: write full 3D arrays for $e3[tuvw]$ and 2D arrays corresponding to the depth of the bottom t - and w -points
- if $6 < in_msh \leq 9$: write 2D arrays corresponding to the depth and the thickness ($e3[tw]_{ps}$) of the bottom points

Author

J.Paul

12.4.4 Function/Subroutine Documentation

12.4.4.1 `type(tatt) function, dimension(ip_maxatt) create_meshmask::create__gloatt (character(len=*), intent(in) cd_bathy, character(len=*), intent(in) cd_coord, character(len=*), intent(in) cd_isfdep, type(tnamh), intent(in) td_namh, type(tnamz), intent(in) td_namz)`

this function create array of global attributes.

Author

J.Paul

Date

October, 2016 - initial release

Parameters

<i>in</i>	<i>cd_bathy</i>	
<i>in</i>	<i>cd_coord</i>	
<i>in</i>	<i>cd_isfdep</i>	
<i>in</i>	<i>td_namh</i>	
<i>in</i>	<i>td_namz</i>	

12.4.4.2 `subroutine create_meshmask::create__mask (type(tnamh), intent(in) td_nam, integer(i4), intent(in) jpi, integer(i4), intent(in) jpj, integer(i4), intent(in) jpk, logical, intent(in) ld_domcfg)`

This subroutine compute land/ocean mask arrays at tracer points, horizontal velocity points (u & v), vorticity points (f) and barotropic stream function points (b).

**** Method :** The ocean/land mask is computed from the basin bathymetry in level ($mbathy$) which is defined or read in `dommba`. $mbathy$ equals 0 over continental T-point and the number of ocean level over the ocean.

At a given position (ji,jj,jk) the ocean/land mask is given by:

- t -point :
 - 0. IF $mbathy(ji ,jj) \leq 0$
 - 1. IF $mbathy(ji ,jj) \geq jk$
- u -point :
 - 0. IF $mbathy(ji ,jj)$ or $mbathy(ji+1, jj) \leq 0$
 - 1. IF $mbathy(ji ,jj)$ and $mbathy(ji+1, jj) \geq jk$.
- v -point :
 - 0. IF $mbathy(ji ,jj)$ or $mbathy(ji ,jj+1) \leq 0$

- 1. IF mbathy(ji ,jj) and mbathy(ji ,jj+1) >= jk.
- f-point :
 - 0. IF mbathy(ji ,jj) or mbathy(ji ,jj+1) or mbathy(ji+1,jj) or mbathy(ji+1,jj+1) =< 0
 - 1. IF mbathy(ji ,jj) and mbathy(ji ,jj+1) and mbathy(ji+1,jj) and mbathy(ji+1,jj+1) >= jk.
- b-point : the same definition as for f-point of the first ocean level (surface level) but with 0 along coastlines.
- tmask_i : interior ocean mask at t-point, i.e. excluding duplicated rows/lines due to cyclic or North Fold boundaries as well as MPP halos.

Warning

do not set the lateral friction through the value of fmask along the coast and topography.

Note

If nperio not equal to 0, the land/ocean mask arrays are defined with the proper value at lateral domain boundaries, but bmask. indeed, bmask defined the domain over which the barotropic stream function is computed. this domain cannot contain identical columns because the matrix associated with the barotropic stream function equation is then no more invertible. therefore bmask is set to 0 along lateral domain boundaries even IF nperio is not zero.

In case of open boundaries (lk_bdy=T):

- tmask is set to 1 on the points to be computed bay the open boundaries routines.
- bmask is set to 0 on the open boundaries.

** Action :

- tmask : land/ocean mask at t-point (=0. or 1.)
- umask : land/ocean mask at u-point (=0. or 1.)
- vmask : land/ocean mask at v-point (=0. or 1.)
- fmask : land/ocean mask at f-point (=0. or 1.)
- bmask : land/ocean mask at barotropic stream function point (=0. or 1.) and set to 0 along lateral boundaries
- tmask_i : interior ocean mask

Author

J.Paul

Date

September, 2015 - rewrite from dom_msk
October, 2016

- do not use anymore special case for ORCA grid

Parameters

in	<i>td_nam</i>	
in	<i>jpi</i>	
in	<i>npj</i>	
in	<i>npk</i>	

12.4.4.3 program create_meshmask ()

Date

September, 2015 - Initial Version (based on domhgr.F90, domzgr.F90, domwri.F90)

October, 2016

- update from trunk (revision 6961): add wetting and drying, ice sheet coupling..

October, 2016

- dimension to be used select from configuration file
- do not use anymore special case for ORCA grid
- allow to write domain_cfg file

November, 2016

- choose vertical scale factors (e3.=dk[depth] or old definition)

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.5 src/create_restart.f90 File Reference

This program creates restart file.

Functions/Subroutines

- program [create_restart](#)
- type(tvar) function [create_restart_matrix](#) (td_var, td_coord, id_nlevel, id_xghost)
This function create variable, filled with matrix value.
- subroutine [create_restart_mask](#) (td_var, td_mask)
This subroutine use mask to filled land point with _FillValue.
- subroutine [create_restart_interp](#) (td_var, id_rho, id_offset, id_iext, id_jext)
This subroutine interpolate variable.
- subroutine [create_restart_check_depth](#) (td_mpp, td_depth)
This subroutine get depth variable value in an open mpp structure and check if agree with already input depth variable.
- subroutine [create_restart_check_time](#) (td_mpp, td_time)
This subroutine get date and time in an open mpp structure and check if agree with date and time already read.

12.5.1 Detailed Description

This program creates restart file.

12.5.2 method

Variables could be extracted from fine grid file, interpolated from coarse grid file or restart file. Variables could also be manually written.

Then they are split over new layout.

Note

method could be different for each variable.

12.5.3 how to

to create restart file:

```
./SIREN/bin/create_restart create_restart.nam
```

Note

you could find a template of the namelist in templates directory.

create_restart.nam contains 9 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- coarse grid namelist (namcrs)
- fine grid namelist (namfin)
- vertical grid namelist (namzgr)
- partial step namelist (namzps)
- variable namelist (namvar)
- nesting namelist (namnst)
- output namelist (namout)

logger namelist (namlog):

- cn_logfile : log filename
- cn_verbosity : verbosity ('trace','debug','info', 'warning','error','fatal','none')
- in_maxerror : maximum number of error allowed

config namelist (namcfg):

- cn_varcfg : variable configuration file (see ./SIREN/cfg/variable.cfg)
- cn_dimcfg : dimension configuration file. define dimensions allowed (see ./SIREN/cfg/dimension.cfg).
- cn_dumcfg : useless (dummy) configuration file, for useless dimension or variable (see ./SIREN/cfg/dummy.cfg).

_coarse grid namelist (namcrs):

- cn_coord0 : coordinate file

- `in_perio0` : NEMO periodicity index (see Model Boundary Condition in [NEMO documentation](#))

fine grid namelist (namfin):

- `cn_coord1` : coordinate file
- `cn_bathy1` : bathymetry file
- `in_perio1` : NEMO periodicity index

vertical grid namelist (namzgr):

- `dn_ppsur` : coefficient to compute vertical grid
- `dn_ppa0` : coefficient to compute vertical grid
- `dn_ppa1` : coefficient to compute vertical grid
- `dn_ppa2` : double tanh function parameter
- `dn_ppkth` : coefficient to compute vertical grid
- `dn_ppkth2` : double tanh function parameter
- `dn_ppacr` : coefficient to compute vertical grid
- `dn_ppacr2` : double tanh function parameter
- `dn_ppdzmin` : minimum vertical spacing
- `dn_pphmax` : maximum depth
- `in_nlevel` : number of vertical level

Note

If `ppa1` and `ppa0` and `ppsur` are undefined NEMO will compute them from `ppdzmin` , `pphmax`, `ppkth`, `ppacr`

- *partial step namelist (namzps):*
 - `dn_e3zps_min` : minimum thickness of partial step level (meters)
 - `dn_e3zps_rat` : minimum thickness ratio of partial step level
- *variable namelist (namvar):*
 - `cn_varfile` : list of variable, and associated file
`cn_varfile` is the path and filename of the file where find variable.

Note

`cn_varfile` could be a matrix of value, if you want to filled manually variable value.
the variable array of value is split into equal subdomain.
Each subdomain is filled with the corresponding value of the matrix.
separators used to defined matrix are:

- * `'` for line
- * `'/'` for row
- * `'\'` for level

Example:

$$3,2,3/1,4,5 \Rightarrow \begin{pmatrix} 3 & 2 & 3 \\ 1 & 4 & 5 \end{pmatrix}$$

Examples:

- * `'votemper:gridT.nc'`, `'vozocrtx:gridU.nc'`

* 'votemper:10\25', 'vozocrtx:gridU.nc'

to get all variable from one file:

* 'all:restart.dimg'

– `cn_varinfo` : list of variable and extra information about request(s) to be used.

each elements of `cn_varinfo` is a string character (separated by ';').

it is composed of the variable name follow by ':', then request(s) to be used on this variable.

request could be:

- * int = interpolation method
- * ext = extrapolation method
- * flt = filter method
- * min = minimum value
- * max = maximum value
- * unt = new units
- * unf = unit scale factor (linked to new units)

requests must be separated by ','.

order of requests does not matter.

informations about available method could be find in [interp](#), [extrap](#) and [filter](#).

Example: 'votemper: int=linear; flt=hann; ext=dist_weight', 'vosaline: int=cubic'

Note

If you do not specify a method which is required, default one is apply.

- *nesting namelist (namnst)*:

– `in_rhoi` : refinement factor in i-direction

– `in_rhoj` : refinement factor in j-direction

Note

coarse grid indices will be computed from fine grid coordinate file.

- *output namelist (namout)*:

– `cn_fileout` : output file

– `ln_extrap` : extrapolate land point or not

– `in_niproc` : number of processor in i-direction

– `in_njproc` : number of processor in j-direction

– `in_nproc` : total number of processor to be used

– `cn_type` : output format ('dimg', 'cdf')

Author

J.Paul

12.5.4 Function/Subroutine Documentation

12.5.4.1 program create_restart ()

Date

November, 2013 - Initial Version

September, 2014

- add header for user
- offset computed considering grid point
- add attributes in output variable

June, 2015

- extrapolate all land points, and add `In_extrap` in namelist.
- allow to change unit.

September, 2015

- manage useless (dummy) variable, attributes, and dimension

October, 2016

- dimension to be used select from configuration file

Todo • rewrite using meshmask instead of bathymetry and coordinates files

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.5.4.2 subroutine `create_restart::create_restart_check_depth` (type(`tmpp`), intent(in) `td_mpp`, type(`tvar`), intent(inout) `td_depth`)

This subroutine get depth variable value in an open mpp structure and check if agree with already input depth variable.

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

<code>in</code>	<code>td_mpp</code>	mpp structure
<code>in, out</code>	<code>td_depth</code>	depth variable structure

12.5.4.3 subroutine `create_restart::create_restart_check_time` (type(`tmpp`), intent(in) `td_mpp`, type(`tvar`), intent(inout) `td_time`)

This subroutine get date and time in an open mpp structure and check if agree with date and time already read.

Author

J.Paul

Date

November, 2014 - Initial Version

Parameters

in	<i>td_mpp</i>	mpp structure
in, out	<i>td_time</i>	time variable structure

12.5.4.4 subroutine `create_restart::create_restart_interp` (`type(tvar)`, `intent(inout) td_var`, `integer(i4)`, `dimension(:)`, `intent(in) id_rho`, `integer(i4)`, `dimension(:,:)`, `intent(in) id_offset`, `integer(i4)`, `intent(in)`, optional `id_iext`, `integer(i4)`, `intent(in)`, optional `id_jext`)

This subroutine interpolate variable.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- do not use level anymore (for extrapolation)

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>id_rho</i>	array of refinement factor
in	<i>id_offset</i>	array of offset between fine and coarse grid
in	<i>id_iext</i>	i-direction size of extra bands (default= <code>im_minext</code>)
in	<i>id_jext</i>	j-direction size of extra bands (default= <code>im_minext</code>)

12.5.4.5 subroutine `create_restart::create_restart_mask` (`type(tvar)`, `intent(inout) td_var`, `type(tvar)`, `dimension(:)`, `intent(in) td_mask`)

This subroutine use mask to filled land point with `_FillValue`.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>td_mask</i>	mask variable structure

12.5.4.6 `type(tvar)` function `create_restart::create_restart_matrix` (`type(tvar)`, `intent(in) td_var`, `type(tmpp)`, `intent(in) td_coord`, `integer(i4)`, `intent(in) id_nlevel`, `integer(i4)`, `dimension(:,:)`, `intent(in) id_xghost`)

This function create variable, filled with matrix value.

A variable is create with the same name that the input variable, and with dimension of the coordinate file.

Then the variable array of value is split into equal subdomain. Each subdomain is filled with the associated value of the matrix.

Author

J.Paul

Date

November, 2013 - Initial Version

June, 2015

- do not use level anymore

Parameters

in	<i>td_var</i>	variable structure
in	<i>td_coord</i>	coordinate file structure
in	<i>id_nlevel</i>	number of vertical level
in	<i>id_xghost</i>	ghost cell array

Returns

variable structure

12.6 src/merge_bathy.f90 File Reference

This program merges bathymetry file at boundaries.

Functions/Subroutines

- program [merge_bathy](#)
- subroutine [merge_bathy_get_boundary](#) (td_bathy0, td_bathy1, td_bdy, id_rho, id_ncrs, dd_refined, dd_weight, dd_fill)
 - This subroutine compute refined bathymetry on boundary from coarse grid.*
- subroutine [merge_bathy_interp](#) (td_var, id_rho, id_offset, id_iext, id_jext)
 - This subroutine interpolate variable.*

12.6.1 Detailed Description

This program merges bathymetry file at boundaries.

12.6.2 method

Coarse grid Bathymetry is interpolated on fine grid (nearest interpolation method is used). Then fine Bathymetry and refined coarse bathymetry are merged at boundaries.

$$BathyFine = Weight * BathyCoarse + (1 - Weight) * BathyFine$$

The weight function used is :

$$Weight = 0.5 + 0.5 * \cos\left(\frac{\pi * dist}{width}\right)$$

with

- dist : number of point to border
- width : boundary size

12.6.3 how to

to merge bathymetry file:

```
./SIREN/bin/merge_bathy merge_bathy.nam
```

Note

you could find a template of the namelist in templates directory.

merge_bathy.nam contains 7 namelists:

- logger namelist (namlog)
- config namelist (namcfg)
- coarse grid namelist (namcrs)
- fine grid namelist (namfin)

12.6.4 Function/Subroutine Documentation

12.6.4.1 program merge_bathy ()

```
- nesting namelist (namnst)
- boundary namelist (nambdy)
- output namelist (namout)
```

```
* <em>logger namelist (namlog)</em>:
- cn_logfile : logger filename
- cn_verbosity : verbosity ('trace', 'debug', 'info',
```

```
'warning', 'error', 'fatal', 'none')
```

- in_maxerror : maximum number of error allowed

config namelist (namcfg):

- cn_varcfg : variable configuration file (see ./SIREN/cfg/variable.cfg)
- cn_dimcfg : dimension configuration file. define dimensions allowed (see ./SIREN/cfg/dimension.cfg).
- cn_dumcfg : useless (dummy) configuration file, for useless dimension or variable (see ./SIREN/cfg/dummy.cfg).

coarse grid namelist (namcrs):

- cn_bathy0 : bathymetry file
- in_perio0 : NEMO periodicity index (see Model Boundary Condition in [NEMO documentation](#))

fine grid namelist (namfin):

- cn_bathy1 : bathymetry file
- in_perio1 : NEMO periodicity index * *nesting namelist (namnst):*
- in_rhoi : refinement factor in i-direction
- in_rhoj : refinement factor in j-direction

boundary namelist (nambdy):

- In_north : use north boundary or not
- In_south : use south boundary or not
- In_east : use east boundary or not
- In_west : use west boundary or not
- cn_north : north boundary indices on fine grid
cn_north is a string character defining boundary segmentation.
 segments are separated by '|'.
 each segments of the boundary is composed of:
 - indice of velocity (orthogonal to boundary .ie. for north boundary, J-indice).
 - indice of segment start (I-indice for north boundary)
 - indice of segment end (I-indice for north boundary)
 indices must be separated by ':' .
 - optionally, boundary size could be added between '(' and ')' in the first segment defined.

Note

boundary size is the same for all segments of one boundary.

Examples:

- cn_north='index1,first1:last1(width)'
- cn_north='index1(width),first1:last1|index2,first2:last2'
- cn_south : south boundary indices on fine grid
- cn_east : east boundary indices on fine grid
- cn_west : west boundary indices on fine grid
- in_ncrs : number of point(s) with coarse value save at boundaries
- In_oneseg: use only one segment for each boundary or not

output namelist (namout):

- cn_fileout : merged bathymetry file

Author

J.Paul

Date

November, 2013 - Initial Version

September, 2014

- add header for user

July, 2015

- extrapolate all land points
- add attributes with boundary string character (as in namelist)

September, 2015

- manage useless (dummy) variable, attributes, and dimension

October, 2016

- allow to choose the number of boundary point with coarse grid value.
- dimension to be used select from configuration file

Note

Software governed by the CeCILL licence (NEMOGCM/NEMO_CeCILL.txt)

12.6.4.2 subroutine merge_bathy::merge_bathy_get_boundary (type(tmpp), intent(in) *td_bathy0*, type(tmpp), intent(in) *td_bathy1*, type(tbdy), intent(in) *td_bdy*, integer(i4), dimension(:), intent(in) *id_rho*, integer(i4), intent(in) *id_ncrs*, real(dp), dimension(:,:,:), intent(inout) *dd_refined*, real(dp), dimension(:,:,:), intent(inout) *dd_weight*, real(dp), intent(in) *dd_fill*)

This subroutine compute refined bathymetry on boundary from coarse grid.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in	<i>td_bathy0</i>	coarse grid bathymetry file structure
in	<i>td_bathy1</i>	fine grid bathymetry file structure
in	<i>td_bdy</i>	boundary structure
in	<i>id_rho</i>	array of refinement factor
in	<i>id_ncrs</i>	number of point with coarse value save at boundaries
in, out	<i>dd_refined</i>	array of refined bathymetry
in, out	<i>dd_weight</i>	array of weight
in	<i>dd_fill</i>	fillValue

12.6.4.3 subroutine merge_bathy::merge_bathy_interp (type(tvar), intent(inout) *td_var*, integer(i4), dimension(:), intent(in) *id_rho*, integer(i4), dimension(:,:), intent(in) *id_offset*, integer(i4), intent(in), optional *id_iext*, integer(i4), intent(in), optional *id_jext*)

This subroutine interpolate variable.

Author

J.Paul

Date

November, 2013 - Initial Version

Parameters

in, out	<i>td_var</i>	variable structure
in	<i>id_rho</i>	array of refinement factor
in	<i>id_offset</i>	array of offset between fine and coarse grid
in	<i>id_iext</i>	i-direction size of extra bands (default=im_minext)
in	<i>id_jext</i>	j-direction size of extra bands (default=im_minext)

Index

- att, 37
 - att_get_dummy, 39
 - att_get_id, 39
 - att_get_index, 40
 - att_is_dummy, 40
- att::att_clean, 41
 - att_clean_arr, 41
 - att_clean_unit, 41
- att::att_copy, 41
 - att_copy_arr, 42
 - att_copy_unit, 42
- att::att_init, 43
 - att_init_c, 43
 - att_init_dp, 44
 - att_init_dp_0d, 44
 - att_init_i1, 45
 - att_init_i1_0d, 45
 - att_init_i2, 46
 - att_init_i2_0d, 46
 - att_init_i4, 46
 - att_init_i4_0d, 47
 - att_init_i8, 47
 - att_init_i8_0d, 48
 - att_init_sp, 48
 - att_init_sp_0d, 49
- att::att_print, 49
 - att_print_arr, 49
 - att_print_unit, 50
- att::tatt, 250
- att_clean_arr
 - att::att_clean, 41
- att_clean_unit
 - att::att_clean, 41
- att_copy_arr
 - att::att_copy, 42
- att_copy_unit
 - att::att_copy, 42
- att_init_c
 - att::att_init, 43
- att_init_dp
 - att::att_init, 44
- att_init_dp_0d
 - att::att_init, 44
- att_init_i1
 - att::att_init, 45
- att_init_i1_0d
 - att::att_init, 45
- att_init_i2
 - att::att_init, 46
- att_init_i2_0d
 - att::att_init, 46
- att_init_i4
 - att::att_init, 46
- att_init_i4_0d
 - att::att_init, 47
- att_init_i8
 - att::att_init, 47
- att_init_i8_0d
 - att::att_init, 48
- att_init_sp
 - att::att_init, 48
- att_init_sp_0d
 - att::att_init, 49
- att_print_arr
 - att::att_print, 49
- att_print_unit
 - att::att_print, 50
- att_get_dummy
 - att, 39
- att_get_id
 - att, 39
- att_get_index
 - att, 40
- att_is_dummy
 - att, 40
- boundary, 50
 - boundary_check, 53
 - boundary_check_corner, 54
 - boundary_get_indices, 54
 - boundary_set_filename, 55
 - boundary_swap, 55
- boundary::boundary_clean, 56
 - boundary_clean_arr, 56
 - boundary_clean_unit, 56
- boundary::boundary_copy, 56
 - boundary_copy_arr, 57
 - boundary_copy_unit, 57
- boundary::boundary_init, 58
 - boundary_init_wrapper, 58
- boundary::boundary_print, 59
 - boundary_print_arr, 59
 - boundary_print_unit, 59
- boundary::seg_clean, 248
 - seg_clean_arr, 248
 - seg_clean_unit, 248
- boundary::seg_copy, 249
 - seg_copy_arr, 249
 - seg_copy_unit, 250

- boundary::tbody, 251
- boundary::tseg, 259
- boundary__clean_arr
 - boundary::boundary_clean, 56
- boundary__clean_unit
 - boundary::boundary_clean, 56
- boundary__copy_arr
 - boundary::boundary_copy, 57
- boundary__copy_unit
 - boundary::boundary_copy, 57
- boundary__init_wrapper
 - boundary::boundary_init, 58
- boundary__print_arr
 - boundary::boundary_print, 59
- boundary__print_unit
 - boundary::boundary_print, 59
- boundary_check
 - boundary, 53
- boundary_check_corner
 - boundary, 54
- boundary_get_indices
 - boundary, 54
- boundary_set_filename
 - boundary, 55
- boundary_swap
 - boundary, 55
- create__boundary
 - create_boundary.F90, 346
- create__gloatt
 - create_meshmask.f90, 358
- create__mask
 - create_meshmask.f90, 358
- create_bathy
 - create_bathy.f90, 338
- create_bathy.f90
 - create_bathy, 338
 - create_bathy_check_depth, 338
 - create_bathy_check_time, 339
 - create_bathy_extract, 339
 - create_bathy_get_var, 339
 - create_bathy_interp, 340
 - create_bathy_matrix, 340
- create_bathy_check_depth
 - create_bathy.f90, 338
- create_bathy_check_time
 - create_bathy.f90, 339
- create_bathy_extract
 - create_bathy.f90, 339
- create_bathy_get_var
 - create_bathy.f90, 339
- create_bathy_interp
 - create_bathy.f90, 340
- create_bathy_matrix
 - create_bathy.f90, 340
- create_boundary
 - create_boundary.F90, 346
- create_boundary.F90
 - create__boundary, 346
 - create_boundary, 346
 - create_boundary_check_depth, 346
 - create_boundary_check_time, 347
 - create_boundary_get_coord, 347
 - create_boundary_get_dom, 348
 - create_boundary_get_level, 348
 - create_boundary_interp, 348
 - create_boundary_matrix, 349
 - create_boundary_use_mask, 349
- create_boundary_check_depth
 - create_boundary.F90, 346
- create_boundary_check_time
 - create_boundary.F90, 347
- create_boundary_get_coord
 - create_boundary.F90, 347
- create_boundary_get_dom
 - create_boundary.F90, 348
- create_boundary_get_level
 - create_boundary.F90, 348
- create_boundary_interp
 - create_boundary.F90, 348
- create_boundary_matrix
 - create_boundary.F90, 349
- create_boundary_use_mask
 - create_boundary.F90, 349
- create_coord
 - create_coord.f90, 352
- create_coord.f90
 - create_coord, 352
 - create_coord_get_offset, 352
 - create_coord_interp, 353
- create_coord_get_offset
 - create_coord.f90, 352
- create_coord_interp
 - create_coord.f90, 353
- create_meshmask
 - create_meshmask.f90, 360
- create_meshmask.f90
 - create__gloatt, 358
 - create__mask, 358
 - create_meshmask, 360
- create_restart
 - create_restart.f90, 363
- create_restart.f90
 - create_restart, 363
 - create_restart_check_depth, 364
 - create_restart_check_time, 364
 - create_restart_interp, 365
 - create_restart_mask, 365
 - create_restart_matrix, 365
- create_restart_check_depth
 - create_restart.f90, 364
- create_restart_check_time
 - create_restart.f90, 364
- create_restart_interp
 - create_restart.f90, 365
- create_restart_mask
 - create_restart.f90, 365

create_restart_matrix
 create_restart.f90, 365

date, 60
 date_leapyear, 62
 date_now, 63
 date_print, 63
 date_today, 63

date::date_init, 64
 date__init_fmtdate, 64
 date__init_jd, 64
 date__init_nsec, 65
 date__init_ymd, 65

date::operator(+), 242
 date__addnday, 242

date::operator(-), 243
 date__diffdate, 243
 date__subnday, 243

date::tdate, 251

date__addnday
 date::operator(+), 242

date__diffdate
 date::operator(-), 243

date__init_fmtdate
 date::date_init, 64

date__init_jd
 date::date_init, 64

date__init_nsec
 date::date_init, 65

date__init_ymd
 date::date_init, 65

date__subnday
 date::operator(-), 243

date_leapyear
 date, 62

date_now
 date, 63

date_print
 date, 63

date_today
 date, 63

dim, 66
 dim_def_extra, 70
 dim_disorder, 70
 dim_fill_unused, 70
 dim_get_dummy, 71
 dim_get_id, 71
 dim_get_index, 71
 dim_init, 72
 dim_is_dummy, 73
 dim_reorder, 73

dim::dim_clean, 74
 dim__clean_arr, 74
 dim__clean_unit, 74

dim::dim_copy, 75
 dim__copy_arr, 75
 dim__copy_unit, 75

dim::dim_print, 76
 dim__print_arr, 76
 dim__print_unit, 77

dim::dim_reorder_2xyzt, 77
 dim__reorder_2xyzt_c, 77
 dim__reorder_2xyzt_i4, 78
 dim__reorder_2xyzt_l, 78

dim::dim_reorder_xyzt2, 79
 dim__reorder_xyzt2_c, 79
 dim__reorder_xyzt2_i4, 79
 dim__reorder_xyzt2_l, 80

dim::dim_reshape_2xyzt, 81
 dim__reshape_2xyzt_dp, 81

dim::dim_reshape_xyzt2, 81
 dim__reshape_xyzt2_dp, 82

dim::tdim, 252

dim__clean_arr
 dim::dim_clean, 74

dim__clean_unit
 dim::dim_clean, 74

dim__copy_arr
 dim::dim_copy, 75

dim__copy_unit
 dim::dim_copy, 75

dim__print_arr
 dim::dim_print, 76

dim__print_unit
 dim::dim_print, 77

dim__reorder_2xyzt_c
 dim::dim_reorder_2xyzt, 77

dim__reorder_2xyzt_i4
 dim::dim_reorder_2xyzt, 78

dim__reorder_2xyzt_l
 dim::dim_reorder_2xyzt, 78

dim__reorder_xyzt2_c
 dim::dim_reorder_xyzt2, 79

dim__reorder_xyzt2_i4
 dim::dim_reorder_xyzt2, 79

dim__reorder_xyzt2_l
 dim::dim_reorder_xyzt2, 80

dim__reshape_2xyzt_dp
 dim::dim_reshape_2xyzt, 81

dim__reshape_xyzt2_dp
 dim::dim_reshape_xyzt2, 82

dim_def_extra
 dim, 70

dim_disorder
 dim, 70

dim_fill_unused
 dim, 70

dim_get_dummy
 dim, 71

dim_get_id
 dim, 71

dim_get_index
 dim, 71

dim_init
 dim, 72

dim_is_dummy
 dim, 73

- dim_reorder
 - dim, 73
- dom, 82
 - dom__init_file, 86
 - dom_add_extra, 86
 - dom_clean, 87
 - dom_clean_extra, 87
 - dom_del_extra, 87
 - dom_print, 88
- dom::dom_copy, 88
 - dom__copy_unit, 88
- dom::dom_init, 89
 - dom__init_file, 89
 - dom__init_mpp, 90
- dom::tdom, 252
- dom__copy_unit
 - dom::dom_copy, 88
- dom__init_file
 - dom, 86
 - dom::dom_init, 89
- dom__init_mpp
 - dom::dom_init, 90
- dom_add_extra
 - dom, 86
- dom_clean
 - dom, 87
- dom_clean_extra
 - dom, 87
- dom_del_extra
 - dom, 87
- dom_print
 - dom, 88
- extrap, 90
 - extrap_add_extrabands, 92
 - extrap_del_extrabands, 92
- extrap::extrap_detect, 93
 - extrap__detect_wrapper, 93
- extrap::extrap_fill_value, 94
 - extrap__fill_value_wrapper, 94
- extrap__detect_wrapper
 - extrap::extrap_detect, 93
- extrap__fill_value_wrapper
 - extrap::extrap_fill_value, 94
- extrap_add_extrabands
 - extrap, 92
- extrap_del_extrabands
 - extrap, 92
- fct, 95
 - fct_basename, 97
 - fct_concat, 98
 - fct_dirname, 98
 - fct_err, 99
 - fct_getunit, 99
 - fct_is_num, 99
 - fct_is_real, 100
 - fct_lower, 100
 - fct_pause, 100
 - fct_split, 101
 - fct_upper, 101
- fct::fct_str, 102
 - fct__i1_str, 102
 - fct__i2_str, 102
 - fct__i4_str, 103
 - fct__i8_str, 103
 - fct__l_str, 104
 - fct__r4_str, 104
 - fct__r8_str, 104
- fct::operator(/), 244
 - fct__i1_cat, 244
 - fct__i2_cat, 245
 - fct__i4_cat, 245
 - fct__i8_cat, 245
 - fct__l_cat, 246
 - fct__r4_cat, 246
 - fct__r8_cat, 247
- fct__i1_cat
 - fct::operator(/), 244
- fct__i1_str
 - fct::fct_str, 102
- fct__i2_cat
 - fct::operator(/), 245
- fct__i2_str
 - fct::fct_str, 102
- fct__i4_cat
 - fct::operator(/), 245
- fct__i4_str
 - fct::fct_str, 103
- fct__i8_cat
 - fct::operator(/), 245
- fct__i8_str
 - fct::fct_str, 103
- fct__l_cat
 - fct::operator(/), 246
- fct__l_str
 - fct::fct_str, 104
- fct__r4_cat
 - fct::operator(/), 246
- fct__r4_str
 - fct::fct_str, 104
- fct__r8_cat
 - fct::operator(/), 247
- fct__r8_str
 - fct::fct_str, 104
- fct_basename
 - fct, 97
- fct_concat
 - fct, 98
- fct_dirname
 - fct, 98
- fct_err
 - fct, 99
- fct_getunit
 - fct, 99
- fct_is_num
 - fct, 99

- fct_is_real
 - fct, 100
- fct_lower
 - fct, 100
- fct_pause
 - fct, 100
- fct_split
 - fct, 101
- fct_upper
 - fct, 101
- file, 105
 - file_add_att, 108
 - file_add_dim, 109
 - file_add_suffix, 109
 - file_add_var, 109
 - file_check_var_dim, 110
 - file_del_dim, 110
 - file_get_id, 111
 - file_get_type, 111
 - file_get_unit, 111
 - file_init, 112
 - file_move_att, 112
 - file_move_dim, 113
 - file_move_var, 113
 - file_print, 113
- file::file_clean, 114
 - file_clean_arr, 114
 - file_clean_unit, 114
- file::file_copy, 115
 - file_copy_arr, 115
 - file_copy_unit, 115
- file::file_del_att, 116
 - file_del_att_name, 116
 - file_del_att_str, 117
- file::file_del_var, 117
 - file_del_var_name, 117
 - file_del_var_str, 118
- file::file_rename, 118
 - file_rename_char, 118
 - file_rename_str, 119
- file::tfile, 253
- file_clean_arr
 - file::file_clean, 114
- file_clean_unit
 - file::file_clean, 114
- file_copy_arr
 - file::file_copy, 115
- file_copy_unit
 - file::file_copy, 115
- file_del_att_name
 - file::file_del_att, 116
- file_del_att_str
 - file::file_del_att, 117
- file_del_var_name
 - file::file_del_var, 117
- file_del_var_str
 - file::file_del_var, 118
- file_rename_char
 - file::file_rename, 118
- file_rename_str
 - file::file_rename, 119
- file_add_att
 - file, 108
- file_add_dim
 - file, 109
- file_add_suffix
 - file, 109
- file_add_var
 - file, 109
- file_check_var_dim
 - file, 110
- file_del_dim
 - file, 110
- file_get_id
 - file, 111
- file_get_type
 - file, 111
- file_get_unit
 - file, 111
- file_init
 - file, 112
- file_move_att
 - file, 112
- file_move_dim
 - file, 113
- file_move_var
 - file, 113
- file_print
 - file, 113
- filter, 119
 - filter::filter_fill_value, 121
 - filter__fill_value_wrapper, 121
- filter__fill_value_wrapper
 - filter::filter_fill_value, 121
- global, 121
- grid, 123
 - grid_add_ghost, 128
 - grid_check_coincidence, 128
 - grid_check_dom, 129
 - grid_del_ghost, 129
 - grid_distance, 130
 - grid_fill_small_dom, 130
 - grid_fill_small_msk, 131
 - grid_is_global, 131
 - grid_is_north_fold, 131
 - grid_split_domain, 132
- grid::grid_get_closest, 132
 - grid_get_closest_arr, 132
 - grid_get_closest_str, 133
- grid::grid_get_coarse_index, 134
 - grid_get_coarse_index_cc, 135
 - grid_get_coarse_index_cf, 135
 - grid_get_coarse_index_fc, 136
 - grid_get_coarse_index_ff, 137
- grid::grid_get_ew_overlap, 137
 - grid_get_ew_overlap_file, 138

- grid_get_ew_overlap_mpp, 138
- grid_get_ew_overlap_var, 139
- grid::grid_get_fine_offset, 139
 - grid_get_fine_offset_cc, 140
 - grid_get_fine_offset_cf, 141
 - grid_get_fine_offset_fc, 141
 - grid_get_fine_offset_ff, 142
- grid::grid_get_ghost, 143
 - grid_get_ghost_mpp, 143
 - grid_get_ghost_var, 143
- grid::grid_get_info, 144
 - grid_get_info_file, 144
 - grid_get_info_mpp, 144
- grid::grid_get_perio, 145
 - grid_get_perio_file, 145
 - grid_get_perio_mpp, 146
 - grid_get_perio_var, 146
- grid::grid_get_pivot, 147
 - grid_get_pivot_file, 147
 - grid_get_pivot_mpp, 148
 - grid_get_pivot_var, 148
- grid_get_closest_arr
 - grid::grid_get_closest, 132
- grid_get_closest_str
 - grid::grid_get_closest, 133
- grid_get_coarse_index_cc
 - grid::grid_get_coarse_index, 135
- grid_get_coarse_index_cf
 - grid::grid_get_coarse_index, 135
- grid_get_coarse_index_fc
 - grid::grid_get_coarse_index, 136
- grid_get_coarse_index_ff
 - grid::grid_get_coarse_index, 137
- grid_get_ew_overlap_file
 - grid::grid_get_ew_overlap, 138
- grid_get_ew_overlap_mpp
 - grid::grid_get_ew_overlap, 138
- grid_get_ew_overlap_var
 - grid::grid_get_ew_overlap, 139
- grid_get_fine_offset_cc
 - grid::grid_get_fine_offset, 140
- grid_get_fine_offset_cf
 - grid::grid_get_fine_offset, 141
- grid_get_fine_offset_fc
 - grid::grid_get_fine_offset, 141
- grid_get_fine_offset_ff
 - grid::grid_get_fine_offset, 142
- grid_get_ghost_mpp
 - grid::grid_get_ghost, 143
- grid_get_ghost_var
 - grid::grid_get_ghost, 143
- grid_get_info_file
 - grid::grid_get_info, 144
- grid_get_info_mpp
 - grid::grid_get_info, 144
- grid_get_perio_file
 - grid::grid_get_perio, 145
- grid_get_perio_mpp
 - grid::grid_get_perio, 146
- grid::grid_get_perio, 146
 - grid_get_perio_var, 146
- grid_get_pivot_file
 - grid::grid_get_pivot, 147
- grid_get_pivot_mpp
 - grid::grid_get_pivot, 148
- grid_get_pivot_var
 - grid::grid_get_pivot, 148
- grid_add_ghost
 - grid, 128
- grid_check_coincidence
 - grid, 128
- grid_check_dom
 - grid, 129
- grid_del_ghost
 - grid, 129
- grid_distance
 - grid, 130
- grid_fill_small_dom
 - grid, 130
- grid_fill_small_msk
 - grid, 131
- grid_hgr, 149
 - grid_hgr_clean, 152
 - grid_hgr_fill, 152
 - grid_hgr_init, 153
 - grid_hgr_nam, 153
- grid_hgr::tnamh, 258
- grid_hgr_clean
 - grid_hgr, 152
- grid_hgr_fill
 - grid_hgr, 152
- grid_hgr_init
 - grid_hgr, 153
- grid_hgr_nam
 - grid_hgr, 153
- grid_is_global
 - grid, 131
- grid_is_north_fold
 - grid, 131
- grid_split_domain
 - grid, 132
- grid_zgr, 153
 - grid_zgr_clean, 156
 - grid_zgr_fill, 156
 - grid_zgr_init, 157
 - grid_zgr_nam, 157
 - grid_zgr_sco_clean, 157
 - grid_zgr_sco_init, 158
 - grid_zgr_sco_stiff, 158
 - grid_zgr_zps_clean, 158
 - grid_zgr_zps_init, 159
- grid_zgr::tnamz, 258
- grid_zgr_clean
 - grid_zgr, 156
- grid_zgr_fill
 - grid_zgr, 156

grid_zgr_init
 grid_zgr, 157
 grid_zgr_nam
 grid_zgr, 157
 grid_zgr_sco_clean
 grid_zgr, 157
 grid_zgr_sco_init
 grid_zgr, 158
 grid_zgr_sco_stiff
 grid_zgr, 158
 grid_zgr_zps_clean
 grid_zgr, 158
 grid_zgr_zps_init
 grid_zgr, 159

 interp, 159
 interp_clean_mixed_grid, 161
 interp_create_mixed_grid, 162
 interp::interp_detect, 163
 interp__detect_wrapper, 164
 interp::interp_fill_value, 164
 interp__fill_value_wrapper, 164
 interp::tinterp, 255
 interp__detect_wrapper
 interp::interp_detect, 164
 interp__fill_value_wrapper
 interp::interp_fill_value, 164
 interp_clean_mixed_grid
 interp, 161
 interp_create_mixed_grid
 interp, 162
 interp_cubic, 162
 interp_cubic_fill, 163
 interp_cubic_fill
 interp_cubic, 163
 interp_linear, 165
 interp_linear_fill, 166
 interp_linear_fill
 interp_linear, 166
 interp_nearest, 166
 interp_nearest_fill, 167
 interp_nearest_fill
 interp_nearest, 167
 iom, 167
 iom_close, 169
 iom_create, 169
 iom_open, 170
 iom_write_file, 170
 iom::iom_read_att, 186
 iom__read_att_varid_id, 187
 iom__read_att_varid_name, 188
 iom__read_att_varname_id, 188
 iom__read_att_varname_name, 188
 iom::iom_read_dim, 189
 iom__read_dim_id, 189
 iom__read_dim_name, 190
 iom::iom_read_var, 190
 iom__read_var_id, 190
 iom__read_var_name, 191
 iom__read_att_varid_id
 iom::iom_read_att, 187
 iom__read_att_varid_name
 iom::iom_read_att, 188
 iom__read_att_varname_id
 iom::iom_read_att, 188
 iom__read_att_varname_name
 iom::iom_read_att, 188
 iom__read_dim_id
 iom::iom_read_dim, 189
 iom__read_dim_name
 iom::iom_read_dim, 190
 iom__read_var_id
 iom::iom_read_var, 190
 iom__read_var_name
 iom::iom_read_var, 191
 iom_cdf, 171
 iom_cdf_close, 172
 iom_cdf_open, 173
 iom_cdf_write_file, 173
 iom_cdf::iom_cdf_fill_var, 174
 iom_cdf__fill_var_all, 174
 iom_cdf__fill_var_id, 174
 iom_cdf__fill_var_name, 175
 iom_cdf::iom_cdf_read_att, 175
 iom_cdf__read_att_id, 175
 iom_cdf__read_att_name, 176
 iom_cdf::iom_cdf_read_dim, 176
 iom_cdf__read_dim_id, 176
 iom_cdf__read_dim_name, 177
 iom_cdf::iom_cdf_read_var, 177
 iom_cdf__read_var_id, 178
 iom_cdf__read_var_name, 178
 iom_cdf__fill_var_all
 iom_cdf::iom_cdf_fill_var, 174
 iom_cdf__fill_var_id
 iom_cdf::iom_cdf_fill_var, 174
 iom_cdf__fill_var_name
 iom_cdf::iom_cdf_fill_var, 175
 iom_cdf__read_att_id
 iom_cdf::iom_cdf_read_att, 175
 iom_cdf__read_att_name
 iom_cdf::iom_cdf_read_att, 176
 iom_cdf__read_dim_id
 iom_cdf::iom_cdf_read_dim, 176
 iom_cdf__read_dim_name
 iom_cdf::iom_cdf_read_dim, 177
 iom_cdf__read_var_id
 iom_cdf::iom_cdf_read_var, 178
 iom_cdf__read_var_name
 iom_cdf::iom_cdf_read_var, 178
 iom_cdf_close
 iom_cdf, 172
 iom_cdf_open
 iom_cdf, 173
 iom_cdf_write_file
 iom_cdf, 173
 iom_close

- iom, 169
- iom_create
 - iom, 169
- iom_dom, 179
 - iom_dom_close, 180
 - iom_dom_open, 180
- iom_dom::iom_dom_read_var, 180
 - iom_dom__read_var_id, 180
 - iom_dom__read_var_name, 181
- iom_dom__read_var_id
 - iom_dom::iom_dom_read_var, 180
- iom_dom__read_var_name
 - iom_dom::iom_dom_read_var, 181
- iom_dom_close
 - iom_dom, 180
- iom_dom_open
 - iom_dom, 180
- iom_mpp, 181
 - iom_mpp_close, 183
 - iom_mpp_create, 184
 - iom_mpp_open, 184
 - iom_mpp_write_file, 184
- iom_mpp::iom_mpp_read_var, 185
 - iom_mpp__read_var_id, 185
 - iom_mpp__read_var_name, 186
- iom_mpp__read_var_id
 - iom_mpp::iom_mpp_read_var, 185
- iom_mpp__read_var_name
 - iom_mpp::iom_mpp_read_var, 186
- iom_mpp_close
 - iom_mpp, 183
- iom_mpp_create
 - iom_mpp, 184
- iom_mpp_open
 - iom_mpp, 184
- iom_mpp_write_file
 - iom_mpp, 184
- iom_open
 - iom, 170
- iom_rstdimg, 191
 - iom_rstdimg_close, 193
 - iom_rstdimg_get_mpp, 193
 - iom_rstdimg_open, 194
 - iom_rstdimg_write_file, 194
- iom_rstdimg::iom_rstdimg_read_dim, 195
 - iom_rstdimg__read_dim_id, 195
 - iom_rstdimg__read_dim_name, 195
- iom_rstdimg::iom_rstdimg_read_var, 196
 - iom_rstdimg__read_var_id, 196
 - iom_rstdimg__read_var_name, 196
- iom_rstdimg__read_dim_id
 - iom_rstdimg::iom_rstdimg_read_dim, 195
- iom_rstdimg__read_dim_name
 - iom_rstdimg::iom_rstdimg_read_dim, 195
- iom_rstdimg__read_var_id
 - iom_rstdimg::iom_rstdimg_read_var, 196
- iom_rstdimg__read_var_name
 - iom_rstdimg::iom_rstdimg_read_var, 196
- iom_rstdimg_close
 - iom_rstdimg, 193
- iom_rstdimg_get_mpp
 - iom_rstdimg, 193
- iom_rstdimg_open
 - iom_rstdimg, 194
- iom_rstdimg_write_file
 - iom_rstdimg, 194
- iom_write_file
 - iom, 170
- kind, 197
- lbc, 198
 - lbc::lbc_hide_nfd, 199
 - lbc_hide_nfd_2d, 199
 - lbc::lbc_hide, 199
 - lbc_hide_lnk_2d, 199
 - lbc::lbc_lnk, 200
 - lbc_lnk_2d, 200
 - lbc_lnk_3d, 200
 - lbc::lbc_nfd, 201
 - lbc_nfd_2d, 201
 - lbc_nfd_3d, 202
 - lbc_hide_lnk_2d
 - lbc::lbc_hide, 199
 - lbc_hide_nfd_2d
 - lbc::lbc_hide_nfd, 199
 - lbc_lnk_2d
 - lbc::lbc_lnk, 200
 - lbc_lnk_3d
 - lbc::lbc_lnk, 200
 - lbc_nfd_2d
 - lbc::lbc_nfd, 201
 - lbc_nfd_3d
 - lbc::lbc_nfd, 202
- logger, 202
 - logger_clean, 205
 - logger_close, 205
 - logger_debug, 206
 - logger_error, 206
 - logger_fatal, 206
 - logger_flush, 207
 - logger_footer, 207
 - logger_header, 207
 - logger_info, 207
 - logger_open, 208
 - logger_trace, 208
 - logger_warn, 209
- logger::tlogger, 256
- logger_clean
 - logger, 205
- logger_close
 - logger, 205
- logger_debug
 - logger, 206
- logger_error
 - logger, 206
- logger_fatal

- logger, 206
- logger_flush
 - logger, 207
- logger_footer
 - logger, 207
- logger_header
 - logger, 207
- logger_info
 - logger, 207
- logger_open
 - logger, 208
- logger_trace
 - logger, 208
- logger_warn
 - logger, 209
- math, 209
 - math_compute, 212
 - math_deriv_1d, 212
 - math_deriv_2d, 212
 - math_deriv_3d, 213
 - math_qsortc, 213
 - math_unwrap, 214
- math::math_mean, 214
 - math__mean_1d, 214
 - math__mean_2d, 215
- math::math_median, 215
 - math__median_1d, 216
 - math__median_2d, 216
- math::math_mwe, 216
 - math__mwe_1d, 217
 - math__mwe_2d, 217
- math__mean_1d
 - math::math_mean, 214
- math__mean_2d
 - math::math_mean, 215
- math__median_1d
 - math::math_median, 216
- math__median_2d
 - math::math_median, 216
- math__mwe_1d
 - math::math_mwe, 217
- math__mwe_2d
 - math::math_mwe, 217
- math_compute
 - math, 212
- math_deriv_1d
 - math, 212
- math_deriv_2d
 - math, 212
- math_deriv_3d
 - math, 213
- math_qsortc
 - math, 213
- math_unwrap
 - math, 214
- merge_bathy
 - merge_bathy.f90, 367
- merge_bathy.f90
 - merge_bathy, 367
 - merge_bathy_get_boundary, 369
 - merge_bathy_interp, 369
- merge_bathy_get_boundary
 - merge_bathy.f90, 369
- merge_bathy_interp
 - merge_bathy.f90, 369
- mpp, 217
 - mpp_add_att, 223
 - mpp_add_dim, 223
 - mpp_add_var, 223
 - mpp_del_dim, 224
 - mpp_get_contour, 224
 - mpp_get_dom, 224
 - mpp_get_index, 225
 - mpp_get_proc_index, 225
 - mpp_get_proc_size, 225
 - mpp_move_att, 226
 - mpp_move_dim, 226
 - mpp_move_var, 226
 - mpp_print, 227
 - mpp_recombine_var, 227
- mpp::mpp__add_proc, 227
 - mpp__add_proc_unit, 228
- mpp::mpp__check_dim, 228
 - mpp__check_proc_dim, 229
 - mpp__check_var_dim, 229
- mpp::mpp__del_proc, 229
 - mpp__del_proc_id, 230
 - mpp__del_proc_str, 230
- mpp::mpp_clean, 230
 - mpp__clean_arr, 231
 - mpp__clean_unit, 231
- mpp::mpp_copy, 231
 - mpp__copy_arr, 231
 - mpp__copy_unit, 232
- mpp::mpp_del_att, 233
 - mpp__del_att_name, 233
 - mpp__del_att_str, 233
- mpp::mpp_del_var, 234
 - mpp__del_var_mpp, 234
 - mpp__del_var_name, 234
 - mpp__del_var_str, 234
- mpp::mpp_get_use, 235
 - mpp__get_use_unit, 235
- mpp::mpp_init, 235
 - mpp__init_file, 236
 - mpp__init_mask, 236
 - mpp__init_var, 237
- mpp::tlay, 255
- mpp::tmpp, 257
- mpp__add_proc_unit
 - mpp::mpp__add_proc, 228
- mpp__check_proc_dim
 - mpp::mpp__check_dim, 229
- mpp__check_var_dim
 - mpp::mpp__check_dim, 229
- mpp__clean_arr

- mpp::mpp_clean, 231
- mpp_clean_unit
 - mpp::mpp_clean, 231
- mpp_copy_arr
 - mpp::mpp_copy, 231
- mpp_copy_unit
 - mpp::mpp_copy, 232
- mpp_del_att_name
 - mpp::mpp_del_att, 233
- mpp_del_att_str
 - mpp::mpp_del_att, 233
- mpp_del_proc_id
 - mpp::mpp_del_proc, 230
- mpp_del_proc_str
 - mpp::mpp_del_proc, 230
- mpp_del_var_mpp
 - mpp::mpp_del_var, 234
- mpp_del_var_name
 - mpp::mpp_del_var, 234
- mpp_del_var_str
 - mpp::mpp_del_var, 234
- mpp_get_use_unit
 - mpp::mpp_get_use, 235
- mpp_init_file
 - mpp::mpp_init, 236
- mpp_init_mask
 - mpp::mpp_init, 236
- mpp_init_var
 - mpp::mpp_init, 237
- mpp_add_att
 - mpp, 223
- mpp_add_dim
 - mpp, 223
- mpp_add_var
 - mpp, 223
- mpp_del_dim
 - mpp, 224
- mpp_get_contour
 - mpp, 224
- mpp_get_dom
 - mpp, 224
- mpp_get_index
 - mpp, 225
- mpp_get_proc_index
 - mpp, 225
- mpp_get_proc_size
 - mpp, 225
- mpp_move_att
 - mpp, 226
- mpp_move_dim
 - mpp, 226
- mpp_move_var
 - mpp, 226
- mpp_print
 - mpp, 227
- mpp_recombine_var
 - mpp, 227
- multi, 238
 - multi__add_mpp, 240
 - multi_clean, 240
 - multi_init, 240
 - multi_print, 241
 - multi::multi_copy, 241
 - multi__copy_unit, 241
 - multi::tmulti, 257
 - multi__add_mpp
 - multi, 240
 - multi__copy_unit
 - multi::multi_copy, 241
 - multi_clean
 - multi, 240
 - multi_init
 - multi, 240
 - multi_print
 - multi, 241
- phycst, 247
- seg__clean_arr
 - boundary::seg__clean, 248
- seg__clean_unit
 - boundary::seg__clean, 248
- seg__copy_arr
 - boundary::seg__copy, 249
- seg__copy_unit
 - boundary::seg__copy, 250
- src/create_bathy.f90, 335
- src/create_boundary.F90, 341
- src/create_coord.f90, 350
- src/create_meshmask.f90, 353
- src/create_restart.f90, 360
- src/merge_bathy.f90, 366
- var, 261
 - var_check_dim, 268
 - var_chg_extra, 268
 - var_chg_fillvalue, 269
 - var_chg_unit, 269
 - var_clean_extra, 270
 - var_concat, 270
 - var_def_extra, 270
 - var_del_dim, 271
 - var_del_value, 271
 - var_get_dummy, 271
 - var_get_id, 272
 - var_get_index, 272
 - var_get_mask, 272
 - var_get_unit, 273
 - var_is_dummy, 273
 - var_limit_value, 274
 - var_max_dim, 274
 - var_move_att, 274
 - var_move_dim, 275
 - var_read_matrix, 275
 - var_reorder, 276
 - var_to_date, 276
- var::tvar, 259

var::var_add_att, 276
 var__add_att_arr, 277
 var__add_att_unit, 277
 var::var_add_dim, 277
 var__add_dim_arr, 278
 var__add_dim_unit, 278
 var::var_add_value, 278
 var__add_value_dp, 279
 var__add_value_i1, 279
 var__add_value_i2, 280
 var__add_value_i4, 280
 var__add_value_i8, 281
 var__add_value_rp, 281
 var::var_clean, 282
 var__clean_arr_1d, 282
 var__clean_arr_2d, 282
 var__clean_arr_3d, 283
 var__clean_unit, 283
 var::var_copy, 284
 var__copy_arr, 284
 var__copy_unit, 284
 var::var_del_att, 285
 var__del_att_name, 285
 var__del_att_str, 286
 var::var_init, 286
 var__init, 288
 var__init_1d_dp, 290
 var__init_1d_i1, 292
 var__init_1d_i2, 293
 var__init_1d_i4, 295
 var__init_1d_i8, 296
 var__init_1d_sp, 298
 var__init_2d_dp, 299
 var__init_2d_i1, 300
 var__init_2d_i2, 302
 var__init_2d_i4, 304
 var__init_2d_i8, 305
 var__init_2d_sp, 307
 var__init_3d_dp, 308
 var__init_3d_i1, 310
 var__init_3d_i2, 311
 var__init_3d_i4, 313
 var__init_3d_i8, 314
 var__init_3d_sp, 316
 var__init_dp, 317
 var__init_i1, 319
 var__init_i2, 320
 var__init_i4, 322
 var__init_i8, 323
 var__init_sp, 325
 var::var_print, 326
 var__print_arr, 326
 var__print_unit, 327
 var__add_att_arr
 var::var_add_att, 277
 var__add_att_unit
 var::var_add_att, 277
 var__add_dim_arr
 var::var_add_dim, 278
 var__add_dim_unit
 var::var_add_dim, 278
 var__add_value_dp
 var::var_add_value, 279
 var__add_value_i1
 var::var_add_value, 279
 var__add_value_i2
 var::var_add_value, 280
 var__add_value_i4
 var::var_add_value, 280
 var__add_value_i8
 var::var_add_value, 281
 var__add_value_rp
 var::var_add_value, 281
 var__clean_arr_1d
 var::var_clean, 282
 var__clean_arr_2d
 var::var_clean, 282
 var__clean_arr_3d
 var::var_clean, 283
 var__clean_unit
 var::var_clean, 283
 var__copy_arr
 var::var_copy, 284
 var__copy_unit
 var::var_copy, 284
 var__del_att_name
 var::var_del_att, 285
 var__del_att_str
 var::var_del_att, 286
 var__init
 var::var_init, 288
 var__init_1d_dp
 var::var_init, 290
 var__init_1d_i1
 var::var_init, 292
 var__init_1d_i2
 var::var_init, 293
 var__init_1d_i4
 var::var_init, 295
 var__init_1d_i8
 var::var_init, 296
 var__init_1d_sp
 var::var_init, 298
 var__init_2d_dp
 var::var_init, 299
 var__init_2d_i1
 var::var_init, 300
 var__init_2d_i2
 var::var_init, 302
 var__init_2d_i4
 var::var_init, 304
 var__init_2d_i8
 var::var_init, 305
 var__init_2d_sp
 var::var_init, 307
 var__init_3d_dp
 var::var_init, 308

var::var_init, 308
var__init_3d_i1
var::var_init, 310
var__init_3d_i2
var::var_init, 311
var__init_3d_i4
var::var_init, 313
var__init_3d_i8
var::var_init, 314
var__init_3d_sp
var::var_init, 316
var__init_dp
var::var_init, 317
var__init_i1
var::var_init, 319
var__init_i2
var::var_init, 320
var__init_i4
var::var_init, 322
var__init_i8
var::var_init, 323
var__init_sp
var::var_init, 325
var__print_arr
var::var_print, 326
var__print_unit
var::var_print, 327
var_check_dim
var, 268
var_chg_extra
var, 268
var_chg_fillvalue
var, 269
var_chg_unit
var, 269
var_clean_extra
var, 270
var_concat
var, 270
var_def_extra
var, 270
var_del_dim
var, 271
var_del_value
var, 271
var_get_dummy
var, 271
var_get_id
var, 272
var_get_index
var, 272
var_get_mask
var, 272
var_get_unit
var, 273
var_is_dummy
var, 273
var_limit_value
var, 274
var_max_dim
var, 274
var_move_att
var, 274
var_move_dim
var, 275
var_read_matrix
var, 275
var_reorder
var, 276
var_to_date
var, 276
vgrid, 327
vgrid_get_level, 329
vgrid_zgr_bat, 330
vgrid_zgr_bat_ctl, 330
vgrid_zgr_z, 331
vgrid_zgr_zps, 331
vgrid_get_level
vgrid, 329
vgrid_zgr_bat
vgrid, 330
vgrid_zgr_bat_ctl
vgrid, 330
vgrid_zgr_z
vgrid, 331
vgrid_zgr_zps
vgrid, 331